

AIX Version 7.3

*Performance Tools Guide and Reference*



**Note**

Before using this information and the product it supports, read the information in [“Notices” on page 331](#).

This edition applies to AIX Version 7.3 and to all subsequent releases and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 2021.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>About this document.....</b>	<b>V</b>
Highlighting.....	v
Case-sensitivity in AIX.....	v
ISO 9000.....	v
<b>Performance Tools Guide and Reference.....</b>	<b>1</b>
What's new.....	2
CPU Utilization Reporting Tool (curt).....	2
Syntax for the curt Command.....	2
Measurement and Sampling.....	3
Examples of the curt command.....	5
Simple performance lock analysis tool (splat).....	33
splat command syntax.....	33
Measurement and sampling.....	35
Examples of generated reports.....	37
Hardware performance monitor APIs and tools.....	56
Performance monitor accuracy.....	57
Performance monitor context and state.....	57
Performance monitoring agent.....	58
POWERCOMPAT events.....	59
Thread accumulation and thread group accumulation.....	64
Access controls to use PMU.....	64
Security considerations.....	65
The pmapi library.....	66
The hpm library and associated tools.....	79
Perfstat API programming.....	88
API characteristics.....	88
Global interfaces.....	89
Component-Specific interfaces.....	109
WPAR Interfaces.....	175
RSET Interfaces.....	185
Cached metrics interfaces.....	190
Node interfaces.....	194
Change history of the perfstat API.....	202
Kernel tuning.....	207
Migration and compatibility.....	207
Tunables file directory.....	208
Tunable parameters type.....	209
Common syntax for tuning commands.....	209
Tunable file-manipulation commands.....	212
Initial setup.....	216
Reboot tuning procedure.....	216
Recovery Procedure.....	216
Kernel tuning using the SMIT interface.....	217
The procmon tool.....	223
Overview of the procmon tool.....	223
Components of the procmon tool.....	223
Filtering processes.....	226
Performing AIX commands on processes.....	226
Profiling tools.....	226

The timing commands .....	226
The prof command .....	227
The gprof command.....	228
The tprof command.....	230
The svmon command.....	237
Security.....	237
The svmon configuration file.....	238
Summary report metrics.....	238
Report formatting options.....	239
Segment details and -O options.....	240
Additional -O options.....	244
Reports details.....	248
Remote Statistics Interface API Overview.....	269
Remote Statistics Interface list of subroutines.....	270
RSI Interface Concepts and Terms.....	271
A Simple Data-Consumer Program.....	276
Expanding the data-consumer program.....	279
Inviting data suppliers.....	281
A Full-Screen, character-based monitor.....	282
List of RSI Error Codes.....	282
The nmon recording tool.....	286
Asynchronous I/O statistics.....	286
nmon recording tool commands.....	286
I/O statistics.....	290
Kernel statistics.....	297
Memory statistics.....	298
Network statistics.....	302
Process Statistics.....	313
Processor statistics.....	316
Recording configuration details.....	327
WLM statistics.....	329
Workload partition statistics.....	329
<b>Notices.....</b>	<b>331</b>
Privacy policy considerations.....	332
Trademarks.....	333
<b>Index.....</b>	<b>335</b>

## About this document

---

The Performance Tools Guide and Reference provides experienced system administrators, application programmers, service representatives, system engineers, end users, and system programmers with complete, detailed information about the various performance tools that are available for monitoring and tuning AIX systems and applications running on those systems.

The information contained in this document pertains to systems running AIX 7.1, or later. Any content that is applicable to earlier releases will be noted as such.

## Highlighting

---

The following highlighting conventions are used in this document:

<b>Bold</b>	Identifies commands, subroutines, keywords, files, structures, directories, and other items whose names are predefined by the system. Also identifies graphical objects such as buttons, labels, and icons that the user selects.
<i>Italics</i>	Identifies parameters whose actual names or values are to be supplied by the user.
Monospace	Identifies examples of specific data values, examples of text similar to what you might see displayed, examples of portions of program code similar to what you might write as a programmer, messages from the system, or information you should actually type.

## Case-sensitivity in AIX

---

Everything in the AIX operating system is case-sensitive, which means that it distinguishes between uppercase and lowercase letters. For example, you can use the **ls** command to list files. If you type **LS**, the system responds that the command is not found. Likewise, **FILEA**, **FiLea**, and **filea** are three distinct file names, even if they reside in the same directory. To avoid causing undesirable actions to be performed, always ensure that you use the correct case.

## ISO 9000

---

ISO 9000 registered quality systems were used in the development and manufacturing of this product.



---

# Performance Tools Guide and Reference

Performance tuning on a new system involves setting base parameters for the operating system and its applications. The CPU Utilization Reporting Tool (curt), Simple performance lock analysis tool (splat), and procmon tool allow for optimal performance tuning.

The path to achieving this objective is a balance between appropriate expectations and optimizing the available system resources. The performance-tuning process demands great skill, knowledge, and experience, and cannot be performed by only analyzing statistics, graphs, and figures. If results are to be achieved, the human aspect of perceived performance must not be neglected. Performance tuning also takes into consideration problem-determination aspects as well as pure performance issues.

Expectations can often be classified as either of the following:

Item	Descriptor
Throughput expectations	A measure of the amount of work performed over a period of time
Response time expectations	The elapsed time between when a request is submitted and when the response from that request is returned

The performance-tuning process can be initiated for a number of reasons:

- To achieve optimal performance in a newly installed system
- To resolve performance problems resulting from the design (sizing) phase
- To resolve performance problems occurring in the run-time (production) phase

Performance tuning on a newly installed system usually involves setting some base parameters for the operating system and applications. Throughout this book, there are sections that describe the characteristics of different system resources and provide guidelines regarding their base tuning parameters, if applicable.

Limitations originating from the sizing phase will either limit the possibility of tuning, or incur greater cost to overcome them. The system might not meet the original performance expectations because of unrealistic expectations, physical problems in the computer environment, or human error in the design or implementation of the system. In the worst case, adding or replacing hardware might be necessary. Be particularly careful when sizing a system to permit enough capacity for unexpected system loads. In other words, do not design the system to be 100 percent busy from the start of the project.

When a system in a productive environment still meets the performance expectations for which it was initially designed, but the demands and needs of the utilizing organization have outgrown the system's basic capacity, performance tuning is performed to delay or even to avoid the cost of adding or replacing hardware.

Many performance-related issues can be traced back to operations performed by a person with limited experience and knowledge who unintentionally restricted some vital logical or physical resource of the system.

**Note:** The metrics reported by any statistics tool such as `lparstat`, `vmstat`, `iostat`, `mpstat` and so on including the applications that are based on Perfstat API or SPMI API varies to a certain extent at any point of time. If the command is run multiple times for an instance, the values may not be similar for that instance.



## What's new in Performance Tools Guide and Reference

---

Read about new or significantly changed information for the Performance Tools Guide and Reference topic collection.

### How to see what's new or changed

To help you see where technical changes have been made, the information center uses:

- The  image to mark where new or changed information begins.
- The  image to mark where new or changed information ends.

### November 2023

The following information is a summary of the updates made to this topic collection:

- Removed **Multiplexing of PMU context** as the feature is no longer supported.

### November 2022

The following information is a summary of the updates made to this topic collection:

- Added `lcpuid_to_bindid` subroutine under **Global interfaces** in **Perfstat API Programming**. It returns the bind CPU ID.
- Added `bindid_to_lcpuid` subroutine under **Global interfaces** in **Perfstat API Programming**. It returns the logical CPU ID.

### December 2021

The following information is a summary of the updates made to this topic collection:

- You can now save and restore all AIX tunable parameter values after the next boot and next live update operations. Updated SMIT instructions in the [“Global manipulation of tuning parameters” on page 217](#) topic.

## CPU Utilization Reporting Tool (curt)

---

The CPU Utilization Reporting Tool (**curt**) command converts an AIX trace file into a number of statistics related to CPU utilization and either process, thread or pthread activity. These statistics ease the tracking of specific application activity.

The **curt** command works with both uniprocessor and multiprocessor AIX Version 4 and AIX Version 5 traces.

### Syntax for the curt Command

Review the syntax, flags, and parameters for the **curt** command.

The syntax for the **curt** command is as follows:

```
curt -i inputfile [-o outputfile] [-n gensymsfile] [-m trcnmfile] [-a pidnamefile] [-f timestamp] [-l timestamp]  
[-r PURR][-ehpstP]
```

#### Flags

Item	Descriptor
-i <i>inputfile</i>	Specifies the input AIX trace file to be analyzed.
-o <i>outputfile</i>	Specifies an output file (default is <b>stdout</b> ).
-n <i>gensymsfile</i>	Specifies a names file produced by <b>gensyms</b> .

Item	Descriptor
<b>-m</b> <i>trcnmfile</i>	Specifies a names file produced by <b>trcnm</b> .
<b>-a</b> <i>pidnamefile</i>	Specifies a PID-to-process name mapping file.
<b>-f</b> <i>timestamp</i>	Starts processing trace at <i>timestamp</i> seconds.
<b>-l</b> <i>timestamp</i>	Stops processing trace at <i>timestamp</i> seconds.
<b>-r</b> <i>PURR</i>	Uses the PURR register to calculate CPU times.
<b>-e</b>	Outputs elapsed time information for system calls.
<b>-h</b>	Displays usage text (this information).
<b>-p</b>	Outputs detailed process information.
<b>-s</b>	Outputs information about errors returned by system calls.
<b>-t</b>	Outputs detailed thread information.
<b>-P</b>	Outputs detailed pthread information.

### Parameters

Item	Descriptor
<b><i>gensymsfile</i></b>	The names file as produced by the <b>gensyms</b> command.
<b><i>inputfile</i></b>	The AIX trace file to be processed by the <b>curt</b> command.
<b><i>outputfile</i></b>	The name of the output file created by the <b>curt</b> command.
<b><i>pidnamefile</i></b>	If the trace process name table is not accurate, or if more descriptive names are desired, use the <b>-a</b> flag to specify a PID to process name mapping file. This is a file with lines consisting of a process ID (in decimal) followed by a space, then an ASCII string to use as the name for that process.
<b><i>timestamp</i></b>	The time in seconds at which to start and stop the trace file processing.
<b><i>trcnmfile</i></b>	The names file as produced by the <b>trcnm</b> command.
<b><i>PURR</i></b>	The name of the register that is used to calculate CPU times.

## Measurement and Sampling

A *raw*, or unformatted, system trace is read by the **curt** command to produce CPU utilization summaries. The summary information is useful for determining which application, system call, Network File System (NFS) operation, hypervisor call, pthread call, or interrupt handler is using most of the CPU time and is a candidate for optimization to improve system performance.

The following table lists the minimum trace hooks required for the **curt** command. Using only these trace hooks will limit the size of the trace file. However, other events on the system might not be captured in this case. This is significant if you intend to analyze the trace in more detail.

Hook ID	Event Name	Event Explanation
100	HKWD_KERN_FLIH	Occurrence of a first level interrupt, such as an I/O interrupt, a data access page fault, or a timer interrupt (scheduler).
101	HKWD_KERN_SVC	A thread has issued a system call.
102	HKWD_KERN_SLIH	Occurrence of a second level interrupt, that is, first level I/O interrupts are being passed on to the second level interrupt handler which then is working directly with the device driver.

Hook ID	Event Name	Event Explanation
103	HKWD_KERN_SLIHRET	Return from a second level interrupt to the caller (usually a first level interrupt handler).
104	HKWD_KERN_SYSCRET	Return from a system call to the caller (usually a thread).
106	HKWD_KERN_DISPATCH	A thread has been dispatched from the run queue to a CPU.
10C	HKWD_KERN_IDLE	The idle process has been dispatched.
119	HKWD_KERN_PIDSIG	A signal has been sent to a process.
134	HKWD_SYSC_EXECVE	An exec supervisor call (SVC) has been issued by a (forked) process.
135	HKWD_SYSC__EXIT	An exit supervisor call (SVC) has been issued by a process.
139	HKWD_SYSC_FORK	A fork SVC has been issued by a process.
200	HKWD_KERN_RESUME	A dispatched thread is being resumed on the CPU.
210	HKWD_KERN_INITP	A kernel process has been created.
215	HKWD_NFS_DISPATCH	An entry or exit NFS V2 and V3 operation has been issued by a process.
38F	HKWD_DR	A processor has been added/removed.
419	HKWD_CPU_PREEMPT	A processor has been preempted.
465	HKWD_SYSC_CRTTHREAD	A <b>thread_create</b> SVC has been issued by a process.
47F	HKWD_KERN_PHANTOM_EXTINT	A phantom interrupt has occurred.
488	HKWD_RFS4_VOPS	An entry or exit NFS V4 client operation (VOPS) has been issued by a process.
489	HKWD_RFS4_VFSOPS	An entry or exit NFS V4 client operation (VFSOPS) has been issued by a process.
48A	HKWD_RFS4_MISCOPS	An entry or exit NFS V4 client operation (MISCOPS) has been issued by a process.
48D	HKWD_RFS4	An entry or exit NFS V4 server operation has been issued by a process.
492	HKWD_KERN_HCALL	A hypervisor call has been issued by the kernel.
605	HKWD_PTHREAD_VPSLEEP	A <b>pthread vp_sleep</b> operation has been done by a pthread.
609	HKWD_PTHREAD_GENERAL	A general pthread operation has been done by a pthread.

Trace hooks 119 and 135 are used to report on the time spent in the **exit** system call. Trace hooks 134, 139, 210, and 465 are used to keep track of TIDs, PIDs and process names.

Trace hook 492 is used to report on the time spent in the hypervisor.

Trace hooks 605 and 609 are used to report on the time spent in the pthreads library.

To get the PTHREAD hooks in the trace, you must execute your pthread application using the instrumented **libpthreads.a** library.

## Examples of the `curl` command

Preparing the `curl` command input is a three-stage process.

Trace and name files are generated using the following process:

1. **Build the raw trace.** On a 4-way machine, this will create files as listed in the example code below. One raw trace file per CPU is produced. The files are named `trace.raw-0`, `trace.raw-1`, and so forth for each CPU. An additional file named `trace.raw` is also generated. This is a master file that has information that ties together the other CPU-specific traces.  
**Note:** If you want pthread information in the `curl` report, you must add the instrumented `libpthread` directory to the library path, `LIBPATH`, when you build the trace. Otherwise, the `export LIBPATH` statement in the example below is unnecessary.
2. **Merge the trace files.** To merge the individual CPU raw trace files to form one trace file, run the `trcrpt` command. If you are tracing a uniprocessor machine, this step is not necessary.
3. **Create the supporting `gensymsfile` and `trcnmfile` files by running the `gensyms` and `trcnm` commands.** Neither the `gensymsfile` nor the `trcnmfile` file are necessary for the `curl` command to run. However, if you provide one or both of these files, or if you use the `trace` command with the `-n` option, the `curl` command outputs names for system calls and interrupt handlers instead of just addresses. The `gensyms` command output includes more information than the `trcnm` command output, and so, while the `trcnmfile` file will contain most of the important address to name mapping data, a `gensymsfile` file will enable the `curl` command to output more names, and is the preferred address to name mapping data collection command.

The following is an example of how to generate input files for the `curl` command:

```
# HOOKS="100,101,102,103,104,106,10C,119,134,135,139,200,210,215,38F,419,465,47F,488,489,48A,
48D,492,605,609"
# SIZE="1000000"
# export HOOKS SIZE
# trace -n -C all -d -j $HOOKS -L $SIZE -T $SIZE -afo trace.raw
# export LIBPATH=/usr/ccs/lib/perf:$LIBPATH
# trcon ; pthread.app ; trcstop
# unset HOOKS SIZE
# ls trace.raw*
trace.raw  trace.raw-0  trace.raw-1  trace.raw-2  trace.raw-3
# trcrpt -C all -r trace.raw > trace.r
# rm trace.raw*
# ls trace*
trace.r
# gensyms > gensyms.out
# trcnm > trace.nm
```

## Overview of information generated by the `curl` command

Review the following information to learn the different information that is generated by the `curl` command, and how you generate specialized reports.

The following is an overview of the content of the report that the `curl` command generates:

- A report header, including the trace file name, the trace size, and the date and time the trace was taken. The header also includes the command that was used when the trace was run. If the `PURR` register was used to calculate CPU times, this information is also included in the report header.
- For each CPU (and a summary of all the CPUs), processing time expressed in milliseconds and as a percentage (idle and non-idle percentages are included) for various CPU usage categories.
- For each CPU (and a summary of all the CPUs), processing time expressed in milliseconds and as a percentage for CPU usage in application mode for various application usage categories.
- Average thread affinity across all CPUs and for each individual CPU.
- For each CPU (and for all the CPUs), the Physical CPU time spent and the percentage of total time this represents.
- Average physical CPU affinity across all CPUs and for each individual CPU.
- The physical CPU dispatch histogram of each CPU.

- The number of preemptions, and the number of **H\_CEDE** and **H\_CONFER** hypervisor calls for each individual CPU.
- The total number of idle and non-idle process dispatches for each individual CPU.
- Average pthread affinity across all CPUs and for each individual CPU.
- The total number of idle and non-idle pthread dispatches for each individual CPU.
- Information on the amount of CPU time spent in application and system call (**syscall**) mode expressed in milliseconds and as a percentage by thread, process, and process type. Also included are the number of threads per process and per process type.
- Information on the amount of CPU time spent executing each kernel process, including the idle process, expressed in milliseconds and as a percentage of the total CPU time.
- Information on the amount of CPU time spent executing calls to **libpthread**, expressed in milliseconds and as percentages of the total time and the total application time.
- Information on completed system calls that includes the name and address of the system call, the number of times the system call was executed, and the total CPU time expressed in milliseconds and as a percentage with average, minimum, and maximum time the system call was running.
- Information on pending system calls, that is, system calls for which the system call return has not occurred at the end of the trace. The information includes the name and address of the system call, the thread or process which made the system call, and the accumulated CPU time the system call was running expressed in milliseconds.
- Information on completed hypervisor calls that includes the name and address of the hypervisor call, the number of times the hypervisor call was executed, and the total CPU time expressed in milliseconds and as a percentage with average, minimum, and maximum time the hypervisor call was running.
- Information on pending hypervisor calls, which are hypervisor calls that were not completed by the end of the trace. The information includes the name and address of the hypervisor call, the thread or process which made the hypervisor call, and the accumulated CPU time the hypervisor call was running, expressed in milliseconds.
- Information on completed pthread calls that includes the name of the pthread call routine, the number of times the pthread call was executed, and the total CPU time expressed in milliseconds and the average, minimum, and maximum time the pthread call was running.
- Information on pending pthread calls, that is, pthread calls for which the pthread call return has not occurred at the end of the trace. The information includes the name of the pthread call, the process, the thread and the pthread which made the pthread call, and the accumulated CPU time the pthread call was running expressed in milliseconds.
- Information on completed NFS operations that includes the name of the NFS operation, the number of times the NFS operation was executed, and the total CPU time, expressed in milliseconds, and as a percentage with average, minimum, and maximum time the NFS operation call was running.
- Information on pending NFS operations, where the NFS operations did not complete before the end of the trace. The information includes the sequence number for NFS V2/V3, or opcode for NFS V4, the thread or process which made the NFS operation, and the accumulated CPU time that the NFS operation was running, expressed in milliseconds.
- Information on the first level interrupt handlers (FLIHs) that includes the type of interrupt, the number of times the interrupt occurred, and the total CPU time spent handling the interrupt with average, minimum, and maximum time. This information is given for all CPUs and for each individual CPU. If there are any pending FLIHs (FLIHs for which the resume has not occurred at the end of the trace), for each CPU the accumulated time and the pending FLIH type is reported.
- Information on the second level interrupt handlers (SLIHs), which includes the interrupt handler name and address, the number of times the interrupt handler was called, and the total CPU time spent handling the interrupt with average, minimum, and maximum time. This information is given for all CPUs and for each individual CPU. If there are any pending SLIHs (SLIHs for which the return has not occurred at the end of the trace), the accumulated time and the pending SLIH name and address is reported for each CPU.

To create additional, specialized reports, run the **curt** command using the following flags:

- | Item | Descriptor  |
|------|---|
| -e   | Produces reports containing statistics and additional information on the System Calls Summary Report, Pending System Calls Summary Report, Hypervisor Calls Summary Report, Pending Hypervisor Calls Summary Report, System NFS Calls Summary Report, Pending NFS Calls Summary, Pthread Calls Summary, and the Pending Pthread Calls Summary. The additional information pertains to the total, average, maximum, and minimum elapsed times that a system call was running.  |
| -s   | Produces a report containing a list of errors returned by system calls.   |
| -t   | Produces a report containing a detailed report on thread status that includes the amount of CPU time the thread was in application and system call mode, what system calls the thread made, processor affinity, the number of times the thread was dispatched, and to which CPU(s) it was dispatched. The report also includes dispatch wait time and details of interrupts.  |
| -p   | Produces a report containing a detailed report on process status that includes the amount of CPU time the process was in application and system call mode, application time details, threads that were in the process, pthreads that were in the process, pthread calls that the process made and system calls that the process made.   |
| -P   | Produces a report containing a detailed report on pthread status that includes the amount of CPU time the pthread was in application and system call mode, system calls made by the pthread, pthread calls made by the pthread, processor affinity, the number of times the pthread was dispatched and to which CPU(s) it was dispatched, thread affinity, and the number of times the pthread was dispatched and to which kernel thread(s) it was dispatched. The report also includes dispatch wait time and details of interrupts. |

## Default report generated by the **curt** command

The **curt** command output always includes this default report in its output, even if one of the flags described in the previous section is used.

This section explains the default report created by the **curt** command, as follows:

```
# curt -i trace.r -n gensyms.out -o curt.out
```

### General information

The general information displays the time and date when the report was generated, and is followed by the syntax of the **curt** command line that was used to produce the report.

This section also contains some information about the AIX **trace** file that was processed by the **curt** command. This information consists of the **trace** file's name, size, and its creation date. The command used to invoke the AIX trace facility and gather the trace file is displayed at the end of the report.

The following is a sample of the general information section:

```
Run on Wed Apr 26 10:51:33 2XXX
Command line was:
curt -i trace.raw -n gensyms.out -o curt.out
----
AIX trace file name = trace.raw
AIX trace file size = 787848
Wed Apr 26 10:50:11 2XXX
System: AIX 5.3 Node: bu Machine: 00CFEDAD4C00
AIX trace file created = Wed Apr 26 10:50:11 2XXX

Command used to gather AIX trace was:
  trace -n -C all -d -j 100,101,102,103,104,106,10C,134,139,200,215,419,465,47F,488,489,48A,48D,492,605,609
        -L 1000000 -T 1000000 -afo trace.raw
```

### System summary

The system summary information produced by the **curt** command describes the time spent by the whole system (all CPUs) in various execution modes.

The following is a sample of the System summary:

```

System Summary
-----
processing      percent      percent
total time     total time   busy time
(msec)         (incl. idle) (excl. idle) processing category
=====
4998.65         45.94        75.21 APPLICATION
591.59          5.44          8.90 SYSCALL
110.40          1.02          1.66 HCALL
48.33           0.44          0.73 KPROC (excluding IDLE and NFS)
352.23          3.24          5.30 NFS
486.19          4.47          7.32 FLIH
49.10           0.45          0.74 SLIH
8.83            0.08          0.13 DISPATCH (all procs. incl. IDLE)
1.04            0.01          0.02 IDLE DISPATCH (only IDLE proc.)
-----
6646.36         61.08        100.00 CPU(s) busy time
4234.76         38.92
-----
10881.12                                TOTAL

Avg. Thread Affinity =          0.99

Total Physical CPU time (msec) = 20417.45
Physical CPU percentage         = 100.00%

```

The System Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>processing total time</b>	Total time in milliseconds for the corresponding processing category.
<b>percent total time</b>	Time from the first column as a percentage of the sum of total trace elapsed time for all processors. This includes whatever amount of time each processor spent running the IDLE process.
<b>percent busy time</b>	Time from the first column as a percentage of the sum of total trace elapsed time for all processors without including the time each processor spent executing the IDLE process.
<b>Avg. Thread Affinity</b>	Probability that a thread was dispatched to the same processor on which it last executed.
<b>Total Physical CPU time</b>	The real time that the virtual processor was running and not preempted.
<b>Physical CPU percentage</b>	Gives the Physical CPU Time as a percentage of total time.

The possible execution modes or processing categories are interpreted as follows:

<b>Item</b>	<b>Descriptor</b>
<b>APPLICATION</b>	The sum of times spent by all processors in User (that is, non-privileged) mode.
<b>SYSCALL</b>	The sum of times spent by all processors doing System Calls. This is the portion of time that a processor spends executing in the kernel code providing services directly requested by a user process.
<b>HCALL</b>	The sum of times spent by all processors doing Hypervisor Calls. This is the portion of time that a processor spends executing in the hypervisor code providing services directly requested by the kernel.
<b>KPROC</b>	The sum of times spent by all processors executing kernel processes other than IDLE and NFS processes. This is the portion of time that a processor spends executing specially created dispatchable processes that only execute kernel code.
<b>NFS</b>	The sum of times spent by all processors executing NFS operations. This is the portion of time that a processor spends executing in the kernel code providing NFS services directly requested by a kernel process.
<b>FLIH</b>	The sum of times spent by all processors executing FLIHs.

<b>Item</b>	<b>Descriptor</b>
<b>SLIH</b>	The sum of times spent by all processors executing SLIHs.
<b>DISPATCH</b>	The sum of times spent by all processors executing the AIX dispatch code. This sum includes the time spent dispatching all threads (that is, it includes dispatches of the IDLE process).
<b>IDLE DISPATCH</b>	The sum of times spent by all processors executing the AIX dispatch code where the process being dispatched was the IDLE process. Because the DISPATCH category includes the IDLE DISPATCH category's time, the IDLE DISPATCH category's time is not separately added to calculate either CPU(s) busy time or TOTAL (see below).
<b>CPU(s) busy time</b>	The sum of times spent by all processors executing in APPLICATION, SYSCALL, KPROC, FLIH, SLIH, and DISPATCH modes.
<b>IDLE</b>	The sum of times spent by all processors executing the IDLE process.
<b>TOTAL</b>	The sum of CPU(s) busy time and IDLE.

The System Summary example indicates that the CPU is spending most of its time in application mode. There is still 4234.76 ms of IDLE time so there is enough CPU to run applications. If there is insufficient CPU power, do not expect to see any IDLE time. The Avg. Thread Affinity value is 0.99 showing good processor affinity; that is, threads returning to the same processor when they are ready to be run again.

### **System application summary**

The system application summary information produced by the **curt** command describes the time spent by the system as a whole (all CPUs) in various execution modes.

The following is a sample of the System Application Summary:

```

System Application Summary
-----
processing    percent    percent
total time   total time  application
(msec)       (incl. idle) time      processing category
=====
      3.95         0.42         0.07  PTHREAD
      4.69         0.49         0.09  PDISPATCH
      0.13         0.01         0.00  PIDLE
    5356.99       563.18       99.84  OTHER
-----
    5365.77       564.11       100.00  APPLICATION

Avg. Pthread Affinity =          0.84

```

The System Application Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>processing total time</b>	Total time in milliseconds for the corresponding processing category.
<b>percent total time</b>	Time from the first column as a percentage of the sum of total trace elapsed time for all processors. This includes whatever amount of time each processor spent running the IDLE process.
<b>percent application time</b>	Time from the first column as a percentage of the sum of total trace elapsed application time for all processors
<b>Avg. Pthread Affinity</b>	Probability that a pthread was dispatched on the same kernel thread on which it last executed.

The possible execution modes or processing categories are interpreted as follows:

<b>Item</b>	<b>Descriptor</b>
<b>PTHREAD</b>	The sum of times spent by all pthreads on all processors in traced pthread library calls.
<b>PDISPATCH</b>	The sum of times spent by all pthreads on all processors executing the libpthreads dispatch code.
<b>PIDLE</b>	The sum of times spent by all kernel threads on all processors executing the <b>libpthreads vp_sleep</b> code.
<b>OTHER</b>	The sum of times spent by all pthreads on all processors in non-traced user mode.
<b>APPLICATION</b>	The sum of times spent by all processors in User (that is, non-privileged) mode.

### ***Processor summary and processor application summary***

This part of the **curt** command output is displayed by a processor-by-processor basis.

The same description that was given for the system summary and system application summary applies here, except that this report covers each processor rather than the whole system.

Below is a sample of this output:

```

Processor Summary processor number 0
-----
processing      percent      percent
total time      total time    busy time
(msec)          (incl. idle)  (excl. idle)  processing category
=====
45.07           0.88         5.16          APPLICATION
591.39         11.58        67.71         SYSCALL
0.00           0.00         0.00         HCALL
47.83          0.94         5.48         KPROC (excluding IDLE and NFS)
0.00           0.00         0.00         NFS
173.78         3.40         19.90        FLIH
9.27           0.18         1.06         SLIH
6.07           0.12         0.70         DISPATCH (all procs. incl. IDLE)
1.04           0.02         0.12         IDLE DISPATCH (only IDLE proc.)
-----
873.42         17.10        100.00       CPU(s) busy time
4232.92        82.90
-----
5106.34                                TOTAL

Avg. Thread Affinity =          0.98

Total number of process dispatches = 1620
Total number of idle dispatches = 782

Total Physical CPU time (msec) = 3246.25
Physical CPU percentage         = 63.57%
Physical processor affinity     = 0.50
Dispatch Histogram for processor (PHYSICAL CPUid : times_dispatched).

PROC 0 : 15
PROC 24 : 15

Total number of preemptions = 30
Total number of H_CEDE      = 6      with preemption = 3
Total number of H_CONFER    = 3      with preemption = 2

```

```

Processor Application Summary processor 0
-----
processing      percent      percent
total time      total time    application
(msec)          (incl. idle)  time          processing category
=====
1.66           0.04         0.06         PTHREAD
2.61           0.05         0.10         PDISPATCH
0.00           0.00         0.00         PIDLE
2685.12        56.67        99.84        OTHER
-----
2689.39        56.76        100.00       APPLICATION

```

Avg. Pthread Affinity = 0.78  
 Total number of pthread dispatches = 104  
 Total number of pthread idle dispatches = 0

```

Processor Summary processor number 1
-----
processing      percent      percent
total time      total time    busy time
(msec)          (incl. idle)  (excl. idle)  processing category
=====
4985.81         97.70         97.70         APPLICATION
0.09           0.00         0.00         SYSCALL
0.00           0.00         0.00         HCALL
0.00           0.00         0.00         KPROC (excluding IDLE and NFS)
0.00           0.00         0.00         NFS
103.86         2.04         2.04         FLIH
12.54          0.25         0.25         SLIH
0.97           0.02         0.02         DISPATCH (all procs. incl. IDLE)
0.00           0.00         0.00         IDLE DISPATCH (only IDLE proc.)
-----
5103.26         100.00        100.00        CPU(s) busy time
0.00           0.00         IDLE
-----
5103.26         TOTAL
  
```

Avg. Thread Affinity = 0.99

Total number of process dispatches = 516  
 Total number of idle dispatches = 0

Total Physical CPU time (msec) = 5103.26  
 Physical CPU percentage = 100.00%  
 Physical processor affinity = 1.00  
 Dispatch Histogram for processor (PHYSICAL CPUid : times\_dispatched).  
 Total number of preemptions = 0  
 Total number of H\_CEDE = 0 with preemption = 0  
 Total number of H\_CONFER = 0 with preemption = 0

```

Processor Application Summary processor 1
-----
processing      percent      percent
total time      total time    application
(msec)          (incl. idle)  time          processing category
=====
2.29           0.05         0.09         PTHREAD
2.09           0.04         0.08         PDISPATCH
0.13           0.00         0.00         PIDLE
2671.86        56.40        99.83         OTHER
-----
2676.38        56.49        100.00        APPLICATION
  
```

Avg. Pthread Affinity = 0.83

Total number of pthread dispatches = 91  
 Total number of pthread idle dispatches = 5

The following terms are referred to in the example above:

**Total number of process dispatches**

The number of times AIX dispatched any non-IDLE process on the processor.

**Total number of idle dispatches**

The number of IDLE process dispatches.

**Total number of pthread dispatches**

The number of times the libpthreads dispatcher was executed on the processor.

**Total number of pthread idle dispatches**

The number of **vp\_sleep** calls.

## Application summary by thread ID (Tid)

The application summary, by Tid, displays an output of all the threads that were running on the system during the time of trace collection and their CPU consumption. The thread that consumed the most CPU time during the time of the trace collection is displayed at the top of the output.

```
Application Summary (by Tid)
-----
-- processing total (msec) --      -- percent of total processing time --
combined  application  syscall  combined  application  syscall  name (Pid  Tid)
=====  =====  =====  =====  =====  =====  =====
4986.2355  4986.2355  0.0000  24.4214  24.4214  0.0000  cpu(18418 32437)
4985.8051  4985.8051  0.0000  24.4193  24.4193  0.0000  cpu(19128 33557)
4982.0331  4982.0331  0.0000  24.4009  24.4009  0.0000  cpu(18894 28671)
83.8436   2.5062   81.3374  0.4106   0.0123   0.3984  disp+work(20390 28397)
72.5809   2.7269   69.8540  0.3555   0.0134   0.3421  disp+work(18584 32777)
69.8023   2.5351   67.2672  0.3419   0.0124   0.3295  disp+work(19916 33033)
63.6399   2.5032   61.1368  0.3117   0.0123   0.2994  disp+work(17580 30199)
63.5906   2.2187   61.3719  0.3115   0.0109   0.3006  disp+work(20154 34321)
62.1134   3.3125   58.8009  0.3042   0.0162   0.2880  disp+work(21424 31493)
60.0789   2.0590   58.0199  0.2943   0.0101   0.2842  disp+work(21992 32539)

...(lines omitted)...
```

The output is divided into two main sections:

- The total processing time of the thread in milliseconds (processing total (msec))
- The CPU time that the thread has consumed, expressed as a percentage of the total CPU time (percent of total processing time)

The Application Summary (by Tid) has the following fields:

Item	Descriptor
<b>name (Pid Tid)</b>	The name of the process associated with the thread, its process id, and its thread id.

The **processing total (msec)** displays the following values:

Item	Descriptor
<b>combined</b>	The total amount of CPU time, expressed in milliseconds, that the thread was running in either application mode or system call mode.
<b>application</b>	The amount of CPU time, expressed in milliseconds, that the thread spent in application mode.
<b>syscall</b>	The amount of CPU time, expressed in milliseconds, that the thread spent in system call mode.

The **percent of total processing time** displays the following values:

Item	Descriptor
<b>combined</b>	The amount of CPU time that the thread was running, expressed as percentage of the total processing time.
<b>application</b>	The amount of CPU time that the thread the thread spent in application mode, expressed as percentage of the total processing time.
<b>syscall</b>	The amount of CPU time that the thread spent in system call mode, expressed as percentage of the total processing time.

In the example above, we can investigate why the system is spending so much time in application mode by looking at the Application Summary (by Tid), where we can see the top three processes of the report are named **cpu**, a test program that uses a great deal of CPU time. The report shows again that the CPU spent most of its time in application mode running the **cpu** process. Therefore the **cpu** process is a candidate to be optimized to improve system performance.

## Application summary by process ID (Pid)

The application summary, by Pid, has the same content as the application summary, by Tid, except that the threads that belong to each process are consolidated and the process that consumed the most CPU time during the monitoring period is at the beginning of the list.

The name (PID) (Thread Count) column shows the process name, its process ID, and the number of threads that belong to this process and that have been accumulated for this line of data.

```

Application Summary (by Pid)
-----
-- processing total (msec) -- -- percent of total processing time --
combined application syscall combined application syscall name (Pid)(Thread Count)
=====
4986.2355 4986.2355 0.0000 24.4214 24.4214 0.0000 cpu(18418) (1)
4985.8051 4985.8051 0.0000 24.4193 24.4193 0.0000 cpu(19128) (1)
4982.0331 4982.0331 0.0000 24.4009 24.4009 0.0000 cpu(18894) (1)
83.8436 2.5062 81.3374 0.4106 0.0123 0.3984 disp+work(20390) (1)
72.5809 2.7269 69.8540 0.3555 0.0134 0.3421 disp+work(18584) (1)
69.8023 2.5351 67.2672 0.3419 0.0124 0.3295 disp+work(19916) (1)
63.6399 2.5032 61.1368 0.3117 0.0123 0.2994 disp+work(17580) (1)
63.5906 2.2187 61.3719 0.3115 0.0109 0.3006 disp+work(20154) (1)
62.1134 3.3125 58.8009 0.3042 0.0162 0.2880 disp+work(21424) (1)
60.0789 2.0590 58.0199 0.2943 0.0101 0.2842 disp+work(21992) (1)
... (lines omitted) ...

```

## Application summary by process type

The application summary by process type consolidates all processes of the same name and sorts them in descending order of combined processing time.

The name (thread count) column shows the name of the process, and the number of threads that belong to this process name (type) and were running on the system during the monitoring period.

```

Application Summary (by process type)
-----
-- processing total (msec) -- -- percent of total processing time --
combined application syscall combined application syscall name (thread count)
=====
14954.0738 14954.0738 0.0000 73.2416 73.2416 0.0000 cpu(3)
573.9466 21.2609 552.6857 2.8111 0.1041 2.7069 disp+work(9)
20.9568 5.5820 15.3748 0.1026 0.0273 0.0753 trcstop(1)
10.6151 2.4241 8.1909 0.0520 0.0119 0.0401 i41lmd(1)
8.7146 5.3062 3.4084 0.0427 0.0260 0.0167 dtgreet(1)
7.6063 1.4893 6.1171 0.0373 0.0073 0.0300 sleep(1)
... (lines omitted) ...

```

## Kproc summary by thread ID (Tid)

The Kproc summary, by Tid, displays an output of all the kernel process threads that were running on the system during the time of trace collection and their CPU consumption. The thread that consumed the most CPU time during the time of the trace collection is displayed at the beginning of the output.

```

Kproc Summary (by Tid)
-----
-- processing total (msec) -- -- percent of total time --
combined kernel operation combined kernel operation name (Pid Tid)
Type)
=====
1930.9312 1930.9312 0.0000 13.6525 13.6525 0.0000 wait(8196 8197 W)
2.1674 2.1674 0.0000 0.0153 0.0153
0.0000 .WSMRefreshServe(0 3 -)
1.9034 1.9034 1.8020 0.0135 0.0135 0.0128 nfsd(36882 49177
N)
0.6609 0.5789 0.0820 0.0002 0.0002 0.0000 kbiod(8050 86295
N)
... (lines omitted) ...

Kproc Types
-----
Type Function Operation
=====

```

```

W  idle thread      -
N  NFS daemon      NFS Remote Procedure Calls

```

The Kproc Summary has the following fields:

Item	Descriptor
<b>name (Pid Tid Type)</b>	The name of the kernel process associated with the thread, its process ID, its thread ID, and its type. The <b>kproc</b> type is defined in the Kproc Types listing following the Kproc Summary.

#### processing total (msec)

Item	Descriptor
<b>combined</b>	The total amount of CPU time, expressed in milliseconds, that the thread was running in either operation or kernel mode.
<b>kernel</b>	The amount of CPU time, expressed in milliseconds, that the thread spent in unidentified kernel mode.
<b>operation</b>	The amount of CPU time, expressed in milliseconds, that the thread spent in traced operations.

#### percent of total time

Item	Descriptor
<b>combined</b>	The amount of CPU time that the thread was running, expressed as percentage of the total processing time.
<b>kernel</b>	The amount of CPU time that the thread spent in unidentified kernel mode, expressed as percentage of the total processing time.
<b>operation</b>	The amount of CPU time that the thread spent in traced operations, expressed as percentage of the total processing time.

#### Kproc Types

Item	Descriptor
<b>Type</b>	A single letter to be used as an index into this listing.
<b>Function</b>	A description of the nominal function of this type of kernel process.
<b>Operation</b>	A description of the traced operations for this type of kernel process.

#### **Application Pthread summary by process ID (Pid)**

The application Pthread summary, by PID, displays an output of all the multi-threaded processes that were running on the system during trace collection and their CPU consumption, and that have spent time making pthread calls. The process that consumed the most CPU time during the trace collection is displays at the beginning of the list.

```

Application Pthread Summary (by Pid)
-----
-- processing total (msec) --      -- percent of total application time --
application  other  pthread  application  other  pthread  name (Pid)(Pthread
Count)
=====  =====  =====  =====  =====  =====
1277.6602  1274.9354  2.7249  23.8113  23.7605  0.0508  ./pth(245964)(52)
802.6445  801.4162  1.2283  14.9586  14.9357  0.0229  ./pth32(245962)(12)

...(lines omitted)...

```

The output is divided into two main sections:

- The total processing time of the process in milliseconds (processing total (msec))
- The CPU time that the process has consumed, expressed as a percentage of the total application time

The Application Pthread Summary has the following fields:

Item	Descriptor
<b>name (Pid) (Pthread Count)</b>	The name of the process associated with the process ID, and the number of pthreads of this process.

#### processing total (msec)

Item	Descriptor
<b>application</b>	The total amount of CPU time, expressed in milliseconds, that the process was running in user mode.
<b>pthread</b>	The amount of CPU time, expressed in milliseconds, that the process spent in traced call to the pthreads library.
<b>other</b>	The amount of CPU time, expressed in milliseconds, that the process spent in non traced user mode.

#### percent of total application time

Item	Descriptor
<b>application</b>	The amount of CPU time that the process was running in user mode, expressed as percentage of the total application time.
<b>pthread</b>	The amount of CPU time that the process spent in calls to the pthreads library, expressed as percentage of the total application time.
<b>other</b>	The amount of CPU time that the process spent in non traced user mode, expressed as percentage of the total application time.

### System calls summary

The System Calls Summary provides a list of all the system calls that have completed execution on the system during the monitoring period. The list is sorted by the total CPU time in milliseconds consumed by each type of system call.

System Calls Summary						
Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	SVC (Address)
605	355.4475	1.74%	0.5875	0.0482	4.5626	kwrite(4259c4)
733	196.3752	0.96%	0.2679	0.0042	2.9948	kread(4259e8)
3	9.2217	0.05%	3.0739	2.8888	3.3418	execve(1c95d8)
38	7.6013	0.04%	0.2000	0.0051	1.6137	__loadx(1c9608)
1244	4.4574	0.02%	0.0036	0.0010	0.0143	lseek(425a60)
45	4.3917	0.02%	0.0976	0.0248	0.1810	access(507860)
63	3.3929	0.02%	0.0539	0.0294	0.0719	_select(4e0ee4)
2	2.6761	0.01%	1.3380	1.3338	1.3423	kfork(1c95c8)
207	2.3958	0.01%	0.0116	0.0030	0.1135	_poll(4e0ecc)
228	1.1583	0.01%	0.0051	0.0011	0.2436	kiocctl(4e07ac)
9	0.8136	0.00%	0.0904	0.0842	0.0988	.smtcheckinit(1b245a8)
5	0.5437	0.00%	0.1087	0.0696	0.1777	open(4e08d8)
15	0.3553	0.00%	0.0237	0.0120	0.0322	.smtcheckinit(1b245cc)
2	0.2692	0.00%	0.1346	0.1339	0.1353	statx(4e0950)
33	0.2350	0.00%	0.0071	0.0009	0.0210	_sigaction(1cada4)
1	0.1999	0.00%	0.1999	0.1999	0.1999	kwaitpid(1cab64)
102	0.1954	0.00%	0.0019	0.0013	0.0178	klseek(425a48)
...(lines omitted)...						

The System Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Count</b>	The number of times that a system call of a certain type (see SVC (Address)) has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing these system calls, expressed in milliseconds.
<b>% sys time</b>	The total CPU time that the system spent processing these system calls, expressed as a percentage of the total processing time.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one system call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one system call of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one system call of this type, expressed in milliseconds.
<b>SVC (Address)</b>	The name of the system call and its kernel address.

### Pending system calls summary

The pending system calls summary provides a list of all the system calls that have been executed on the system during the monitoring period but have not completed. The list is sorted by Tid.

```

Pending System Calls Summary
-----
Accumulated   SVC (Address)                Procname (Pid  Tid)
Time (msec)
=====
0.0656        _select(4e0ee4)             sendmail(7844 5001)
0.0452        _select(4e0ee4)             syslogd(7514 8591)
0.0712        _select(4e0ee4)             snmpd(5426 9293)
0.0156        kioctl(4e07ac)              trcstop(47210 18379)
0.0274        kwaitpid(1cab64)            ksh(20276 44359)
0.0567        kread4259e8)                ksh(23342 50873)

...(lines omitted)...

```

The Pending System Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending system call, expressed in milliseconds.
<b>SVC (Address)</b>	The name of the system call and its kernel address.
<b>Procname (Pid Tid)</b>	The name of the process associated with the thread that made the system call, its process ID, and the thread ID.

### Hypervisor calls summary

The Hypervisor calls summary provides a list of all the hypervisor calls that have completed execution on the system during the monitoring period. The list is sorted by the total CPU time, in milliseconds, consumed by each type of hypervisor call.

```

Hypervisor Calls Summary
-----
Count   Total Time   % sys   Avg Time   Min Time   Max Time   HCALL (Address)
(msec)  (msec)      time   (msec)    (msec)    (msec)
=====
4        0.0077      0.00%  0.0019    0.0014    0.0025    H_XIRR(3ada19c)
4        0.0070      0.00%  0.0017    0.0015    0.0021    H_EOI(3ad6564)

```

The Hypervisor Calls Summary has the following fields:

<b>Item</b>	<b>Description</b>
<b>Count</b>	The number of times that a hypervisor call of a certain type has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing hypervisor calls of this type, expressed in milliseconds.
<b>% sys Time</b>	The total CPU time that the system spent processing the hypervisor calls of this type, expressed as a percentage of the total processing time.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one hypervisor call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one hypervisor call of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one hypervisor call of this type, expressed in milliseconds.
<b>HCALL (address)</b>	The name of the hypervisor call and the kernel address of its caller.

### Pending Hypervisor calls summary

The pending Hypervisor calls summary provides a list of all the hypervisor calls that have been executed on the system during the monitoring period but have not completed. The list is sorted by Tid.

Pending Hypervisor Calls Summary			
Accumulated Time (msec)	HCALL (Address)	Procname (Pid Tid)	
0.0066	H_XIRR(3ada19c)	syncd(3916 5981)	

The Pending Hypervisor Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending hypervisor call, expressed in milliseconds.
<b>HCALL (address)</b>	The name of the hypervisor call and the kernel address of its caller.
<b>Procname (Pid Tid)</b>	The name of the process associated with the thread that made the hypervisor call, its process ID, and the thread ID.

### System NFS calls summary

The system NFS calls summary provides a list of all the system NFS calls that have completed execution on the system during the monitoring period. The list is divided by NFS versions, and each list is sorted by the total CPU time, in milliseconds, consumed by each type of system NFS call.

System NFS Calls Summary							
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	% Tot Count	Opcode
253	48.4115	0.1913	0.0952	1.0097	98.91	98.83	RFS2_READLINK
2	0.3959	0.1980	0.1750	0.2209	0.81	0.78	RFS2_LOOKUP
1	0.1373	0.1373	0.1373	0.1373	0.28	0.39	RFS2_NULL
256	48.9448	0.1912					NFS V2 TOTAL
3015	4086.9121	1.3555	0.1035	31.6976	40.45	17.12	RFS3_READ
145	2296.3158	15.8367	1.1177	42.9125	22.73	0.82	RFS3_WRITE
10525	2263.3336	0.2150	0.0547	2.9737	22.40	59.77	RFS3_LOOKUP
373	777.2854	2.0839	0.2839	17.5724	7.69	2.12	RFS3_READDIRPLUS
2058	385.9510	0.1875	0.0875	1.1993	3.82	11.69	RFS3_GETATTR
942	178.6442	0.1896	0.0554	1.2320	1.77	5.35	RFS3_ACCESS
515	97.0297	0.1884	0.0659	0.9774	0.96	2.92	RFS3_READLINK
25	11.3046	0.4522	0.2364	0.9712	0.11	0.14	RFS3_READDIR
3	2.8648	0.9549	0.8939	0.9936	0.03	0.02	RFS3_CREATE

3	2.8590	0.9530	0.5831	1.4095	0.03	0.02	RFS3_COMMIT
2	1.1824	0.5912	0.2796	0.9028	0.01	0.01	RFS3_FSSTAT
1	0.2773	0.2773	0.2773	0.2773	0.00	0.01	RFS3_SETATTR
1	0.2366	0.2366	0.2366	0.2366	0.00	0.01	RFS3_PATHCONF
1	0.1804	0.1804	0.1804	0.1804	0.00	0.01	RFS3_NULL
-----							
17609	10104.3769	0.5738					NFS V3 TOTAL
-----							
105	2296.3158	15.8367	1.1177	42.9125	22.73	0.82	CLOSE
3025	2263.3336	0.2150	0.0547	2.9737	22.40	59.77	COMMIT
373	777.2854	2.0839	0.2839	17.5724	7.69	2.12	CREATE
2058	385.9510	0.1875	0.0875	1.1993	3.82	11.69	DELEGPURGE
942	178.6442	0.1896	0.0554	1.2320	1.77	5.35	DELEGRETURN
515	97.0297	0.1884	0.0659	0.9774	0.96	2.92	GETATTR
25	11.3046	0.4522	0.2364	0.9712	0.11	0.14	GETFH
3	2.8648	0.9549	0.8939	0.9936	0.03	0.02	LINK
3	2.8590	0.9530	0.5831	1.4095	0.03	0.02	LOCK
2	1.1824	0.5912	0.2796	0.9028	0.01	0.01	LOCKT
1	0.2773	0.2773	0.2773	0.2773	0.00	0.01	LOCKU
1	0.2366	0.2366	0.2366	0.2366	0.00	0.01	OOKUP
1	0.1804	0.1804	0.1804	0.1804	0.00	0.01	LOOKUPP
1	0.1704	0.1704	0.1704	0.1704	0.00	0.01	NVERIFY
-----							
17609	10104.3769	0.5738					NFS V4 SERVER TOTAL
-----							
3	2.8590	0.9530	0.5831	1.4095	0.03	0.02	NFS4_ACCESS
2	1.1824	0.5912	0.2796	0.9028	0.01	0.01	NFS\$ _VALIDATE_CACHES
1	0.2773	0.2773	0.2773	0.2773	0.00	0.01	NFS4_GETATTR
1	0.2366	0.2366	0.2366	0.2366	0.00	0.01	NFS4_CHECK_ACCESS
1	0.0000	0.0000	0.1804	0.1804	0.00	0.01	NFS4_HOLD
1	0.1704	0.1704	0.1704	0.1704	0.00	0.01	NFS4_RELE
-----							
17609	10104.3769	0.5738					NFS V4 CLIENT TOTAL

The System NFS Calls Summary has the following fields:

Item	Descriptor
<b>Count</b>	The number of times that a certain type of system NFS call (see <b>Opcode</b> ) has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing system NFS calls of this type, expressed in milliseconds.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one system NFS call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one system NFS call of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one system NFS call of this type, expressed in milliseconds.
<b>% Tot Time</b>	The total CPU time that the system spent processing the system NFS calls of this type, expressed as a percentage of the total processing time.
<b>% Tot Count</b>	The number of times that a system NFS call of a certain type was made, expressed as a percentage of the total count.
<b>Opcode</b>	The name of the system NFS call.

### Pending NFS calls summary

The pending NFS calls summary provides a list of all the system NFS calls that have executed on the system during the monitoring period but have not completed. The list is sorted by the **Tid**.

```

Pending NFS Calls Summary
-----
Accumulated   Sequence Number  Procname (Pid  Tid)
Time (msec)   Opcode
=====
0.0831        1038711932      nfsd(1007854  331969)
0.0833        1038897247      nfsd(1007854  352459)

```

```

0.0317 1038788652      nfsd(1007854 413931)
0.0029 NFS4_ATTRCACHE kbiod(100098 678934)
..(lines omitted)...

```

The Pending System NFS Calls Summary has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending system NFS call, expressed in milliseconds.
<b>Sequence Number</b>	The sequence number represents the transaction identifier ( <b>XID</b> ) of an NFS operation. It is used to uniquely identify an operation and is used in the RPC call/reply messages. This number is provided instead of the operation name because the name of the operation is unknown until it completes.
<b>Opcode</b>	The name of pending operation NFS V4.
<b>Procname (Pid Tid)</b>	The name of the process associated with the thread that made the system NFS call, its process ID, and the thread ID.

### ***Pthread calls summary***

The Pthread calls summary provides a list of all the pthread calls that have completed execution on the system during the monitoring period. The list is sorted by the total CPU time, in milliseconds, consumed by each type of pthread call.

Pthread Calls Summary						
Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Pthread Routine
=====	=====	=====	=====	=====	=====	=====
62	3.6226	0.04%	0.0584	0.0318	0.1833	pthread_create
10	0.1798	0.00%	0.0180	0.0119	0.0341	pthread_cancel
8	0.0725	0.00%	0.0091	0.0064	0.0205	pthread_join
1	0.0553	0.00%	0.0553	0.0553	0.0553	pthread_detach
1	0.0229	0.00%	0.0229	0.0229	0.0229	pthread_kill

The Pthread Calls Summary report has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Count</b>	The number of times that a pthread call of a certain type has been called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing all pthread calls of this type, expressed in milliseconds.
<b>% sys time</b>	The total CPU time that the system spent processing all calls of this type, expressed as a percentage of the total processing time.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one pthread call of this type, expressed in milliseconds.
<b>Min Time (msec)</b>	The minimum CPU time the system used to process one pthread call of this type, expressed in milliseconds.
<b>Pthread routine</b>	The name of the routine in the pthread library.

### ***Pending Pthread calls summary***

The pending Pthread calls summary provides a list of all the pthread calls that have been executed on the system during the monitoring period but have not completed. The list is sorted by Pid-Ptid.

Pending Pthread Calls Summary		
Accumulated Time (msec)	Pthread Routine	Procname (Pid Tid Ptid)
=====	=====	=====

The Pending Pthread System Calls Summary has the following fields:

Item	Descriptor
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending pthread call, expressed in milliseconds.
<b>Pthread Routine</b>	The name of the pthread routine of the <b>libpthreads</b> library.
<b>Procname (Pid Tid Ptid)</b>	The name of the process associated with the thread and the pthread which made the pthread call, its process ID, the thread ID and the pthread ID.

### FLIH summary

The FLIH (First Level Interrupt Handler) summary lists all first level interrupt handlers that were called during the monitoring period.

The Global FLIH Summary lists the total of first level interrupts on the system, while the Per CPU FLIH Summary lists the first level interrupts per CPU.

```

Global Flih Summary
-----
Count  Total Time  Avg Time  Min Time  Max Time  Flih Type
-----  -----  -----  -----  -----  -----
2183   203.5524    0.0932   0.0041   0.4576   31(DECR_INTR)
946    102.4195    0.1083   0.0063   0.6590   3(DATA_ACC_PG_FLT)
12     1.6720     0.1393   0.0828   0.3366   32(QUEUED_INTR)
1058   183.6655    0.1736   0.0039   0.7001   5(IO_INTR)

Per CPU Flih Summary
-----
CPU Number 0:
Count  Total Time  Avg Time  Min Time  Max Time  Flih Type
-----  -----  -----  -----  -----  -----
635    39.8413    0.0627   0.0041   0.4576   31(DECR_INTR)
936    101.4960    0.1084   0.0063   0.6590   3(DATA_ACC_PG_FLT)
9      1.3946     0.1550   0.0851   0.3366   32(QUEUED_INTR)
266    33.4247    0.1257   0.0039   0.4319   5(IO_INTR)

CPU Number 1:
Count  Total Time  Avg Time  Min Time  Max Time  Flih Type
-----  -----  -----  -----  -----  -----
4      0.2405     0.0601   0.0517   0.0735   3(DATA_ACC_PG_FLT)
258    49.2098    0.1907   0.0060   0.5076   5(IO_INTR)
515    55.3714    0.1075   0.0080   0.3696   31(DECR_INTR)

Pending Flih Summary
-----
Accumulated Time (msec)  Flih Type
-----  -----
0.0123    5(IO_INTR)

...(lines omitted)...

```

The FLIH Summary report has the following fields:

Item	Descriptor
<b>Count</b>	The number of times that a first level interrupt of a certain type (see Flih Type) occurred during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing these first level interrupts, expressed in milliseconds.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one first level interrupt of this type, expressed in milliseconds.

<b>Item</b>	<b>Descriptor</b>
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one first level interrupt of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one first level interrupt of this type, expressed in milliseconds.
<b>Flih Type</b>	The number and name of the first level interrupt.
<b>Accumulated Time (msec)</b>	The accumulated CPU time that the system spent processing the pending first level interrupt, expressed in milliseconds.

*FLIH types in the example*

The following are FLIH types that were depicted in the FLIH summary.

<b>Item</b>	<b>Descriptor</b>
<b>DATA_ACC_PG_FLT</b>	Data access page fault
<b>QUEUED_INTR</b>	Queued interrupt
<b>DECR_INTR</b>	Decrementer interrupt
<b>IO_INTR</b>	I/O interrupt

**SLIH summary**

The Second level interrupt handler (SLIH) Summary lists all second level interrupt handlers that were called during the monitoring period.

The Global Slih Summary lists the total of second level interrupts on the system, while the Per CPU Slih Summary lists the second level interrupts per CPU.

Global Slih Summary					
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Slih Name(Address)
43	7.0434	0.1638	0.0284	0.3763	s_scsiddpin(1a99104)
1015	42.0601	0.0414	0.0096	0.0913	ssapin(1990490)

Per CPU Slih Summary					
Count	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Slih Name(Address)
CPU Number 0:					
8	1.3500	0.1688	0.0289	0.3087	s_scsiddpin(1a99104)
258	7.9232	0.0307	0.0096	0.0733	ssapin(1990490)
CPU Number 1:					
10	1.2685	0.1268	0.0579	0.2818	s_scsiddpin(1a99104)
248	11.2759	0.0455	0.0138	0.0641	ssapin(1990490)

...(lines omitted)...

The SLIH Summary report has the following fields:

<b>Item</b>	<b>Descriptor</b>
<b>Count</b>	The number of times that each second level interrupt handler was called during the monitoring period.
<b>Total Time (msec)</b>	The total CPU time that the system spent processing these second level interrupts, expressed in milliseconds.
<b>Avg Time (msec)</b>	The average CPU time that the system spent processing one second level interrupt of this type, expressed in milliseconds.

<b>Item</b>	<b>Descriptor</b>
<b>Min Time (msec)</b>	The minimum CPU time that the system needed to process one second level interrupt of this type, expressed in milliseconds.
<b>Max Time (msec)</b>	The maximum CPU time that the system needed to process one second level interrupt of this type, expressed in milliseconds.
<b>Slih Name (Address)</b>	The module name and kernel address of the second level interrupt.

### Reports generated with the -e flag

The report generated with the **-e** flag includes the data shown in the default report, and also includes additional information in the System Calls Summary, the Pending System Calls Summary, the Hypervisor Calls Summary, the Pending Hypervisor Calls Summary, the System NFS Calls Summary, the Pending NFS Calls Summary, the Pthread Calls Summary and the Pending Pthread Calls Summary.

The additional information in the System Calls Summary, Hypervisor Calls Summary, System NFS Calls Summary, and the Pthread Calls Summary includes the total, average, maximum, and minimum elapsed time that a call was running. The additional information in the Pending System Calls Summary, Pending Hypervisor Calls Summary, Pending NFS Calls Summary, and the Pending Pthread Calls Summary is the accumulated elapsed time for the pending calls. This additional information is present in all the system call, hypervisor call, NFS call, and pthread call reports: globally, in the process detailed report (-p), the thread detailed report (-t), and the pthread detailed report (-P).

The following is an example of the additional information reported by using the **-e** flag:

```
# curt -e -i trace.r -m trace.nm -n gensyms.out -o curt.out
# cat curt.out

...(lines omitted)...

                        System Calls Summary
                        -----
Count  Total   % sys   Avg   Min   Max   Tot   Avg   Min   Max   SVC (Address)
      Time time   Time Time Time Time ETime ETime ETime ETime
      (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec)
=====
605 355.4475 1.74% 0.5875 0.0482 4.5626 31172.7658 51.5252 0.0482 422.2323 kwrite(4259c4)
733 196.3752 0.96% 0.2679 0.0042 2.9948 12967.9407 17.6916 0.0042 265.1204 kread(4259e8)
3    9.2217 0.05% 3.0739 2.8888 3.3418 57.2051 19.0684 4.5475 40.0557 execve(1c95d8)
38   7.6013 0.04% 0.2000 0.0051 1.6137 12.5002 0.3290 0.0051 3.3120 __loadx(1c9608)
1244 4.4574 0.02% 0.0036 0.0010 0.0143 4.4574 0.0036 0.0010 0.0143 lseek(425a60)
45   4.3917 0.02% 0.0976 0.0248 0.1810 4.6636 0.1036 0.0248 0.3037 access(507860)
63   3.3929 0.02% 0.0539 0.0294 0.0719 5006.0887 79.4617 0.0294 100.4802 _select(4e0ee4)
2    2.6761 0.01% 1.3380 1.3338 1.3423 45.5026 22.7513 7.5745 37.9281 kfork(1c95c8)
207  2.3958 0.01% 0.0116 0.0030 0.1135 4494.9249 21.7146 0.0030 499.1363 _poll(4e0ecc)
228  1.1583 0.01% 0.0051 0.0011 0.2436 1.1583 0.0051 0.0011 0.2436 kiocctl(4e07ac)
9    0.8136 0.00% 0.0904 0.0842 0.0988 4498.7472 499.8608 499.8052 499.8898 .smtcheckinit(1b245a8)
5    0.5437 0.00% 0.1087 0.0696 0.1777 0.5437 0.1087 0.0696 0.1777 open(4e08d8)
15   0.3553 0.00% 0.0237 0.0120 0.0322 0.3553 0.0237 0.0120 0.0322 .smtcheckinit(1b245cc)
2    0.2692 0.00% 0.1346 0.1339 0.1353 0.2692 0.1346 0.1339 0.1353 statx(4e0950)
33   0.2350 0.00% 0.0071 0.0009 0.0210 0.2350 0.0071 0.0009 0.0210 _sigaction(1cada4)
1    0.1999 0.00% 0.1999 0.1999 0.1999 5019.0588 5019.0588 5019.0588 5019.0588 kwaitpid(1cab64)
102  0.1954 0.00% 0.0019 0.0013 0.0178 0.5427 0.0053 0.0013 0.3650 klseek(425a48)

...(lines omitted)...

                        Pending System Calls Summary
                        -----
Accumulated   Accumulated   SVC (Address)   Procname (Pid Tid)
Time (msec)   ETime (msec)
=====
0.0855       93.6498       kread(4259e8)       oracle(143984 48841)

...(lines omitted)...

                        Hypervisor Calls Summary
                        -----
Count  Total Time   % sys   Avg Time   Min Time   Max Time   Tot ETime   Avg ETime   Min ETime   Max ETime   HCALL (Address)
      (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec) (msec)
=====
4      0.0077 0.00% 0.0019 0.0014 0.0025 0.0077 0.0019 0.0014 0.0025 H_XIRR(3ada19c)
4      0.0070 0.00% 0.0017 0.0015 0.0021 0.0070 0.0017 0.0015 0.0021 H_EOI(3ad6564)

                        Pending Hypervisor Calls Summary
```

```

-----
Accumulated      Accumulated      HCALL (Address)      Procname (Pid Tid)
Time (msec)      ETime (msec)
=====
0.0855          93.6498          H_XIRR(3ada19c)      syncd(3916 5981)
=====

```

System NFS Calls Summary

```

-----
Count   Total Time   Avg Time   Min Time   Max Time   % Tot   Total ETime   Avg ETime   Min ETime   Max ETime   % Tot   % Tot
Opcode   (msec)      (msec)    (msec)    (msec)    Time    (msec)      (msec)      (msec)      (msec)      ETime    Count
=====
6647    456.1029    0.0686    0.0376    0.6267    15.83   9267.7256    1.3943     0.0376    304.9501   14.63   27.88
RFS3_LOOKUP
2694    147.1680    0.0546    0.0348    0.5517    5.11    1474.4267    0.5473     0.0348    25.9402   2.33    11.30
RFS3_GETATTR
1702    85.8328    0.0504    0.0339    0.5793    2.98    146.4281    0.0860     0.0339    5.7539    0.23    7.14
RFS3_READLINK
1552    78.1015    0.0503    0.0367    0.5513    2.71    153.5844    0.0990     0.0367    7.5125    0.24    6.51
RFS3_ACCESS
235     33.3158    0.1418    0.0890    0.3312    1.16    1579.4557    6.7211     0.0890    56.0876   2.49    0.99
RFS3_SETATTR
21      5.5979    0.2666    0.0097    0.8142    82.79   127.2616    6.0601     0.0097    89.0570   99.37   25.00
NFS4_WRITE
59      1.1505    0.0195    0.0121    0.0258    17.01   0.7873      0.0133     0.0093    0.0194    0.61    70.24
NFS4_ATTRCACHE
4       0.0135    0.0034    0.0026    0.0044    0.20    0.0135      0.0034     0.0026    0.0044    0.01    4.76
NFS4_GET_UID_GID
...(line omitted)...

```

Pending NFS Calls Summary

```

-----
Accumulated      Accumulated      Sequence Number      Procname (Pid Tid)
Time (msec)      ETime (msec)      Opcode
=====
0.0831          15.1581          1038711932           nfsd(1007854 331969)
0.0833          13.8889          1038897247           nfsd(1007854 352459)
0.0087          10.8976          NFS4_ATTRCACHE       kbiod(100098 678934)
...(line omitted)...

```

Pthread Calls Summary

```

-----
Count   Total Time   % sys   Avg Time   Min Time   Max Time   Tot ETime   Avg ETime   Min ETime   Max ETime   Pthread Routine
(msec)  time      (msec)  (msec)    (msec)    (msec)    (msec)      (msec)      (msec)      (msec)
=====
72      2.0126    0.01%   0.0280    0.0173    0.1222    13.7738     0.1913     0.0975     0.6147    pthread_create
2       0.6948    0.00%   0.3474    0.0740    0.6208    92.3033     46.1517     9.9445     82.3588    pthread_kill
12      0.3087    0.00%   0.0257    0.0058    0.0779    25.0506     2.0876     0.0168     10.0605    pthread_cancel
22      0.0613    0.00%   0.0028    0.0017    0.0104    2329.0179   105.8644    0.0044    1908.3402   pthread_join
2       0.0128    0.00%   0.0064    0.0062    0.0065    0.1528      0.0764     0.0637     0.0891    pthread_detach

```

Pending Pthread Calls Summary

```

-----
Accumulated      Accumulated      Pthread Routine      Procname (pid tid ptid)
Time (msec)      ETime (msec)
=====
3.3102          4946.5433       pthread_join          ./pth32(282718 700515 1)
0.0025          544.4914        pthread_join          ./pth(282720 - 1)

```

The system call, hypervisor call, NFS call, and pthread call reports in the preceding example have the following fields in addition to the default System Calls Summary, Hypervisor Calls Summary, System NFS Calls Summary, and Pthread Calls Summary :

- | Item                    | Descriptor  |
|-------------------------|---|
| <b>Tot ETime (msec)</b> | The total amount of time from when each instance of the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth. |
| <b>Avg ETime (msec)</b> | The average amount of time from when the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.                |
| <b>Min ETime (msec)</b> | The minimum amount of time from when the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.                |

<b>Item</b>	<b>Descriptor</b>
<b>Max ETime (msec)</b>	The maximum amount of time from when the call was started until it completed. This time will include any time spent servicing interrupts, running other processes, and so forth.
<b>Accumulated ETime (msec)</b>	The total amount of time from when the pending call was started until the end of the trace. This time will include any time spent servicing interrupts, running other processes, and so forth.

The preceding example report shows that the maximum elapsed time for the **kwrite** system call was 422.2323 msec, but the maximum CPU time was 4.5626 msec. If this amount of overhead time is unusual for the device being written to, further analysis is needed.

### **Reports generated with the -s flag**

The report generated with the **-s** flag includes the data shown in the default report, and data on errors returned by system calls.

```
# curt -s -i trace.r -m trace.nm -n gensyms.out -o curt.out
# cat curt.out

...(lines omitted)...

                          Errors Returned by System Calls
                          -----

Errors (errno : count : description) returned for System Call: kiocctl(4e07ac)
   25 :      15 : "Not a typewriter"
Errors (errno : count : description) returned for System Call: execve(1c95d8)
   2 :       2 : "No such file or directory"

...(lines omitted)...
```

If a large number of errors of a specific type or on a specific system call point to a system or application problem, other debug measures can be used to determine and fix the problem.

### **Reports generated with the -t flag**

The report generated with the **-t** flag includes the data shown in the default report, and also includes a detailed report on thread status that includes the amount of time the thread was in application and system call mode, what system calls the thread made, processor affinity, the number of times the thread was dispatched, and to which CPUs it was dispatched.

The report also includes dispatch wait time and details of interrupts:

```
...(lines omitted)...
-----
Report for Thread Id: 48841 (hex bec9) Pid: 143984 (hex 23270)
Process Name: oracle
-----
Total Application Time (ms):      70.324465
Total System Call Time (ms):      53.014910
Total Hypervisor Call Time (ms):   0.077000

                          Thread System Call Summary
                          -----

Count   Total Time   Avg Time   Min Time   Max Time   SVC (Address)
=====  =====
   69    34.0819     0.4939    0.1666    1.2762    kwrite(169ff8)
   77    12.0026     0.1559    0.0474    0.2889    kread(16a01c)
  510     4.9743     0.0098    0.0029    0.0467    times(f1e14)
   73     1.2045     0.0165    0.0105    0.0306    select(1d1704)
   68     0.6000     0.0088    0.0023    0.0445    lseek(16a094)
   12     0.1516     0.0126    0.0071    0.0241    getrusage(f1be0)

No Errors Returned by System Calls

                          Pending System Calls Summary
                          -----
Accumulated   SVC (Address)
```

```

Time (msec)
=====
0.1420 kread(16a01c)

Thread Hypervisor Calls Summary
-----
Count    Total Time    % sys    Avg Time    Min Time    Max Time    HCALL (Address)
=====  =====  =====  =====  =====  =====  =====
4         0.0077       0.00%    0.0019     0.0014     0.0025     H_XIRR(3ada19c)

Pending Hypervisor Calls Summary
-----
Accumulated    HCALL (Address)
Time (msec)
=====
0.0066 H_XIRR(3ada19c)

```

processor affinity: 0.583333

Dispatch Histogram for thread (CPUid : times\_dispatched).

```

CPU 0 : 23
CPU 1 : 23
CPU 2 : 9
CPU 3 : 9
CPU 4 : 8
CPU 5 : 14
CPU 6 : 17
CPU 7 : 19
CPU 8 : 1
CPU 9 : 4
CPU 10 : 1
CPU 11 : 4

```

total number of dispatches: 131  
total number of redispaches due to interupts being disabled: 1  
avg. dispatch wait time (ms): 8.273515

Data on Interrupts that Occurred while Thread was Running

```

Type of Interrupt    Count
=====
Data Access Page Faults (DSI): 115
Instr. Fetch Page Faults (ISI): 0
Align. Error Interrupts: 0
IO (external) Interrupts: 0
Program Check Interrupts: 0
FP Unavailable Interrupts: 0
FP Imprecise Interrupts: 0
RunMode Interrupts: 0
Decrementer Interrupts: 18
Queued (Soft level) Interrupts: 15

```

...(lines omitted)...

If the thread belongs to an NFS kernel process, the report will include information on NFS operations instead of System calls:

```

Report for Thread Id: 1966273 (hex 1e00c1) Pid: 1007854 (hex f60ee)
Process Name: nfsd
-----
Total Kernel Time (ms): 3.198998
Total Operation Time (ms): 28.839927
Total Hypervisor Call Time (ms): 0.000000

```

Thread NFS Call Summary

Count Opcode	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	Total ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	% Tot ETime	% Tot Count
28 RFS3_READDIRPLUS	12.2661	0.4381	0.3815	0.4841	42.73	32.0893	1.1460	0.4391	16.6283	11.46	11.52
63 RFS3_LOOKUP	3.8953	0.0618	0.0405	0.1288	13.57	23.1031	0.3667	0.0405	7.0886	8.25	25.93
49 RFS3_READ	3.2795	0.0669	0.0527	0.0960	11.42	103.8431	2.1192	0.0534	35.3617	37.09	20.16
18 RFS3_WRITE	2.8464	0.1581	0.1099	0.2264	9.91	7.9129	0.4396	0.1258	4.3503	2.83	7.41

RFS3_GETATTR	29	1.3331	0.0460	0.0348	0.0620	4.64	1.4953	0.0516	0.0348	0.0940	0.53	11.93
RFS3_REMOVE	5	1.2763	0.2553	0.2374	0.3036	4.45	45.0798	9.0160	0.9015	21.7257	16.10	2.06
RFS3_COMMIT	8	1.1001	0.1375	0.1180	0.1719	3.83	53.6532	6.7067	1.4293	19.9199	19.17	3.29
RFS3_READLINK	20	0.9262	0.0463	0.0367	0.0507	3.23	1.2060	0.0603	0.0367	0.1314	0.43	8.23
RFS3_ACCESS	15	0.6798	0.0453	0.0386	0.0519	2.37	0.8015	0.0534	0.0386	0.0788	0.29	6.17
RFS3_READDIR	2	0.4033	0.2017	0.1982	0.2051	1.40	0.5355	0.2677	0.2677	0.2677	0.19	0.82
RFS3_CREATE	1	0.3015	0.3015	0.3015	0.3015	1.05	6.2614	6.2614	6.2614	6.2614	2.24	0.41
RFS3_SETATTR	2	0.2531	0.1265	0.1000	0.1531	0.88	3.7756	1.8878	0.1000	3.6756	1.35	0.82
RFS3_FSINFO	1	0.0853	0.0426	0.0413	0.0440	0.30	0.1333	0.0667	0.0532	0.0802	0.05	0.82
RFS3_FSSTAT	1	0.0634	0.0634	0.0634	0.0634	0.22	0.0634	0.0634	0.0634	0.0634	0.02	0.41
-----												
NFS V3 TOTAL	243	28.7094	0.1181				279.9534	1.1521				
LINK	4	0.0777	0.0194	0.0164	0.0232	10.00	0.0523	0.0131	0.0115	0.0152	10.00	10.00
-----												
NFS V4 CLIENT TOTAL	4	0.0777	0.0194				0.0523	0.0131				

#### Pending NFS Calls Summary

Accumulated Time (msec)	Accumulated ETime (msec)	Sequence Number Opcode
0.1305	182.6903	1038932778
0.0123	102.6324	NFS4_ATTRCACHE

The following information is included in the threads summary:

Item	Descriptor
<b>Thread ID</b>	The Thread ID of the thread.
<b>Process ID</b>	The Process ID that the thread belongs to.
<b>Process Name</b>	The process name, if known, that the thread belongs to.
<b>Total Application Time (ms)</b>	The amount of time, expressed in milliseconds, that the thread spent in application mode.
<b>Total System Call Time (ms)</b>	The amount of time, expressed in milliseconds, that the thread spent in system call mode.
<b>Thread System Call Summary</b>	A system call summary for the thread; this has the same fields as the global System Calls Summary. It also includes elapsed time if the <b>-e</b> flag is specified and error information if the <b>-s</b> flag is specified.
<b>Pending System Calls Summary</b>	If the thread was executing a system call at the end of the trace, a pending system call summary will be printed. This has the Accumulated Time and Supervisor Call (SVC Address) fields. It also includes elapsed time if the <b>-e</b> flag is specified.
<b>Thread Hypervisor Calls Summary</b>	The hypervisor call summary for the thread; this has the same fields as the global Hypervisor Calls Summary. It also includes elapsed time if the <b>-e</b> flag is specified.
<b>Pending Hypervisor Calls Summary</b>	If the thread was executing a hypervisor call at the end of the trace, a pending hypervisor call summary will be printed. This has the Accumulated Time and Hypervisor Call fields. It also includes elapsed time if the <b>-e</b> flag is specified.
<b>Thread NFS Calls Summary</b>	An NFS call summary for the thread. This has the same fields as the global System NFS Call Summary. It also includes elapsed time if the <b>-e</b> flag is specified.

<b>Item</b>	<b>Descriptor</b>
<b>Pending NFS Calls Summary</b>	If the thread was executing an NFS call at the end of the trace, a pending NFS call summary will be printed. This has the <b>Accumulated Time</b> and <b>Sequence Number</b> or, in the case of NFS V4, <b>Opcode</b> , fields. It also includes elapsed time if the <b>-e</b> flag is specified.
<b>processor affinity</b>	The process affinity, which is the probability that, for any dispatch of the thread, the thread was dispatched to the same processor on which it last executed.
<b>Dispatch Histogram for thread</b>	Shows the number of times the thread was dispatched to each CPU in the system.
<b>total number of dispatches</b>	The total number of times the thread was dispatched (not including redispaches).
<b>total number of redispaches due to interrupts being disabled</b>	The number of redispaches due to interrupts being disabled, which is when the dispatch code is forced to dispatch the same thread that is currently running on that particular CPU because the thread had disabled some interrupts. This total is only reported if the value is non-zero.
<b>avg. dispatch wait time (ms)</b>	The average dispatch wait time is the average elapsed time for the thread from being undispached and its next dispatch.
<b>Data on Interrupts that occurred while Thread was Running</b>	Count of how many times each type of FLIH occurred while this thread was executing.

### **Reports generated with the -p flag**

The report generated with the **-p** flag includes the data shown in the default report and also includes a detailed report for each process that includes the Process ID and name, a count and list of the thread IDs, and the count and list of the pthread IDs belonging to the process. The total application time, the system call time, and the application time details for all the threads of the process are given. Lastly, it includes summary reports of all the completed and pending system calls, and pthread calls for the threads of the process.

The following example shows the report generated for the router process (PID 129190):

```

Process Details for Pid: 129190

  Process Name: router

  7 Tids for this Pid: 245889 245631 244599 82843 78701 75347 28941
  9 Ptds for this Pid: 2057 1800 1543 1286 1029 772 515 258 1

Total Application Time (ms): 124.023749
Total System Call Time (ms): 8.948695
Total Hypervisor Time (ms): 0.000000

Application time details:
Total Pthread Call Time (ms): 1.228271
Total Pthread Dispatch Time (ms): 2.760476
Total Pthread Idle Dispatch Time (ms): 0.110307
Total Other Time (ms): 798.545446
Total number of pthread dispatches: 53
Total number of pthread idle dispatches: 3

```

#### Process System Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	SVC (Address)
=====	=====	=====	=====	=====	=====	=====
93	3.6829	0.05%	0.0396	0.0060	0.3077	kread(19731c)
23	2.2395	0.03%	0.0974	0.0090	0.4537	kwrite(1972f8)
30	0.8885	0.01%	0.0296	0.0073	0.0460	select(208c5c)

1	0.5933	0.01%	0.5933	0.5933	0.5933	fsync(1972a4)
106	0.4902	0.01%	0.0046	0.0035	0.0105	klseek(19737c)
13	0.3285	0.00%	0.0253	0.0130	0.0387	semctl(2089e0)
6	0.2513	0.00%	0.0419	0.0238	0.0650	semop(2089c8)
3	0.1223	0.00%	0.0408	0.0127	0.0730	statx(2086d4)
1	0.0793	0.00%	0.0793	0.0793	0.0793	send(11e1ec)
9	0.0679	0.00%	0.0075	0.0053	0.0147	fstatx(2086c8)
4	0.0524	0.00%	0.0131	0.0023	0.0348	kfcntl(22aa14)
5	0.0448	0.00%	0.0090	0.0086	0.0096	yield(11dbec)
3	0.0444	0.00%	0.0148	0.0049	0.0219	recv(11e1b0)
1	0.0355	0.00%	0.0355	0.0355	0.0355	open(208674)
1	0.0281	0.00%	0.0281	0.0281	0.0281	close(19728c)

Pending System Calls Summary

Accumulated Time (msec)	SVC (Address)	Tid
0.0452	select(208c5c)	245889
0.0425	select(208c5c)	78701
0.0285	select(208c5c)	82843
0.0284	select(208c5c)	245631
0.0274	select(208c5c)	244599
0.0179	select(208c5c)	75347

...(omitted lines)...

Pthread Calls Summary

Count	Total Time (msec)	% sys time	Avg Time (msec)	Min Time (msec)	Max Time (msec)	Pthread Routine
19	0.0477	0.00%	0.0025	0.0017	0.0104	pthread_join
1	0.0065	0.00%	0.0065	0.0065	0.0065	pthread_detach
1	0.6208	0.00%	0.6208	0.6208	0.6208	pthread_kill
6	0.1261	0.00%	0.0210	0.0077	0.0779	pthread_cancel
21	0.7080	0.01%	0.0337	0.0226	0.1222	pthread_create

Pending Pthread Calls Summary

Accumulated Time (msec)	Pthread Routine	Tid	Ptid
3.3102	pthread_join	78701	1

If the process is an NFS kernel process, the report will include information on NFS operations instead of System and Pthread calls:

Process Details for Pid: 1007854  
 Process Name: nfsd  
 252 Tids for this Pid: 2089213 2085115 2081017 2076919 2072821 2068723  
 2040037 2035939 2031841 2027743 2023645 2019547  
 2015449 2011351 2007253 2003155 1999057 1994959  
 ...(lines omitted)..  
 454909 434421 413931 397359 364797 352459  
 340185 331969 315411 303283 299237 266405

Total Kernel Time (ms): 380.237018  
 Total Operation Time (ms): 2891.971209

Process NFS Calls Summary

Count Opcode	Total Time (msec)	Avg Time (msec)	Min Time (msec)	Max Time (msec)	% Tot Time	Total ETime (msec)	Avg ETime (msec)	Min ETime (msec)	Max ETime (msec)	% Tot ETime	% Tot Count	
2254	1018.3621	0.4518	0.3639	0.9966	35.34	1800.5708	0.7988	0.4204	16.6283	2.84	9.45	
RFS3_READDIRPLUS	6647	456.1029	0.0686	0.0376	0.6267	15.83	9267.7256	1.3943	0.0376	304.9501	14.63	27.88
RFS3_LOOKUP	1993	321.4973	0.1613	0.0781	0.6428	11.16	3006.1774	1.5084	0.0781	121.8822	4.75	8.36
RFS3_WRITE	4409	314.3122	0.0713	0.0425	0.6139	10.91	14052.7567	3.1873	0.0425	313.2698	22.19	18.49
RFS3_READ	1001	177.9891	0.1778	0.0903	8.7271	6.18	23187.1693	23.1640	0.7657	298.0521	36.61	4.20
RFS3_COMMIT												

2694	147.1680	0.0546	0.0348	0.5517	5.11	1474.4267	0.5473	0.0348	25.9402	2.33	11.30
RFS3_GETATTR											
495	102.0142	0.2061	0.1837	0.7000	3.54	185.8549	0.3755	0.1895	6.1340	0.29	2.08
RFS3_READDIR											
1702	85.8328	0.0504	0.0339	0.5793	2.98	146.4281	0.0860	0.0339	5.7539	0.23	7.14
RFS3_READLINK											
1552	78.1015	0.0503	0.0367	0.5513	2.71	153.5844	0.0990	0.0367	7.5125	0.24	6.51
RFS3_ACCESS											
186	64.4498	0.3465	0.2194	0.7895	2.24	4201.0235	22.5861	1.0235	117.5351	6.63	0.78
RFS3_CREATE											
208	56.8876	0.2735	0.1928	0.7351	1.97	4245.4378	20.4108	0.9015	181.0121	6.70	0.87
RFS3_REMOVE											
235	33.3158	0.1418	0.0890	0.3312	1.16	1579.4557	6.7211	0.0890	56.0876	2.49	0.99
RFS3_SETATTR											
190	13.3856	0.0705	0.0473	0.5495	0.46	19.3971	0.1021	0.0473	0.6827	0.03	0.80
RFS3_FSSTAT											
275	12.4504	0.0453	0.0343	0.0561	0.43	16.6542	0.0606	0.0343	0.2357	0.03	1.15
RFS3_FSINFO											
-----											
23841	2881.8692	0.1209				63336.6621	2.6566				
NFS V3 TOTAL											
55	1.0983	0.0200	0.0164	0.0258	100.00	0.7434	0.0135	0.0115	0.0194	10.00	10.00
NFS4_ATTRCACHE											
-----											
55	1.0983	0.0200				0.7434	0.0135				
NFS V4 CLIENT TOTAL											

Pending NFS Calls Summary

Accumulated Time (msec)	Accumulated ETime (msec)	Sequence Number Opcode	Tid
0.1812	48.1456	1039026977	2089213
0.0188	14.8878	1038285324	2085115
0.0484	2.7123	1039220089	2081017
0.1070	49.5471	1039103658	2072821
0.0953	58.8009	1038453491	2035939
0.0533	62.9266	1039037391	2031841
0.1195	14.6817	1038686320	2019547
0.2063	37.1826	1039164331	2015449
0.0140	6.0718	1039260848	2011351
0.0671	8.8971	NFS4_WRITE	2012896

...(lines omitted)...

The following information is included in the process detailed report:

Item	Descriptor
<b>Total Application Time (ms)</b>	The amount of time, expressed in milliseconds, that the process spent in application mode.
<b>Total System Call Time (ms)</b>	The amount of time, expressed in milliseconds, that the process spent in system call mode.

The following information is included in the application time details report:

Item	Descriptor
<b>Total Pthread Call Time</b>	The amount of time, expressed in milliseconds, that the process spent in traced pthread library calls.
<b>Total Pthread Dispatch Time</b>	The amount of time, expressed in milliseconds, that the process spent in libpthreads dispatch code.
<b>Total Pthread Idle Dispatch Time</b>	The amount of time, expressed in milliseconds, that the process spent in libpthreads <b>vp_sleep</b> code.
<b>Total Other Time</b>	The amount of time, expressed in milliseconds, that the process spent in non-traced user mode code.
<b>Total number of pthread dispatches</b>	The total number of times a pthread belonging to the process was dispatched by the libpthreads dispatcher.
<b>Total number of pthread idle dispatches</b>	The total number of times a thread belonging to the process was in the libpthreads <b>vp_sleep</b> code.

The following summary information is included in the report:

<b>Item</b>	<b>Descriptor</b>
<b>Process System Calls Summary</b>	A system call summary for the process; this has the same fields as the global System Call Summary. It also includes elapsed time information if the <b>-e</b> flag is specified and error information if the <b>-s</b> flag is specified.
<b>Pending System Calls Summary</b>	If the process was executing a system call at the end of the trace, a pending system call summary will be printed. This has the Accumulated Time and Supervisor Call (SVC Address) fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Process Hypervisor Calls Summary</b>	A summary of the hypervisor calls for the process; this has the same fields as the global Hypervisor Calls Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Hypervisor Calls Summary</b>	If the process was executing a hypervisor call at the end of the trace, a pending hypervisor call summary will be printed. This has the Accumulated Time and Hypervisor Call fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Process NFS Calls Summary</b>	An NFS call summary for the process. This has the same fields as the global System NFS Call Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending NFS Calls Summary</b>	If the process was executing an NFS call at the end of the trace, a pending NFS call summary will be printed. This has the <b>Accumulated Time</b> and <b>Sequence Number</b> or, in the case of NFS V4, <b>Opcode</b> , fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pthread Calls Summary</b>	A summary of the pthread calls for the process. This has the same fields as the global pthread Calls Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Pthread Calls Summary</b>	If the process was executing pthread library calls at the end of the trace, a pending pthread call summary will be printed. This has the Accumulated Time and Pthread Routine fields. It also includes elapsed time information if the <b>-e</b> flag is specified.

### ***Reports generated with the -P flag***

The report generated with the **-P** flag includes the data shown in the default report and also includes a detailed report on pthread status.

The report includes the following:

- The amount of time the pthread was in application and system call mode
- The application time details
- The system calls and pthread calls that the pthread made
- The system calls and pthread calls that were pending at the end of the trace
- The processor affinity
- The number of times the pthread was dispatched
- To which CPU(s) the thread was dispatched
- The thread affinity
- The number of times that the pthread was dispatched
- To which kernel thread(s) the pthread was dispatched

The report also includes dispatch wait time and details of interrupts.

The following is an example of a report generated with the **-P** flag:

```
Report for Pthread Id: 1 (hex 1) Pid: 245962 (hex 3c0ca)
Process Name: ./pth32
-----
Total Application Time      (ms): 3.919091
Total System Call Time     (ms): 8.303156
Total Hypervisor Call Time (ms): 0.000000

Application time details:
  Total Pthread Call Time (ms): 1.139372
  Total Pthread Dispatch Time (ms): 0.115822
  Total Pthread Idle Dispatch Time (ms): 0.036630
  Total Other Time (ms): 2.627266

                          Pthread System Calls Summary
                          -----
Count   Total Time   Avg Time   Min Time   Max Time   SVC (Address)
=====  =====
1       3.3898      3.3898     3.3898     3.3898     _exit(409e50)
61      0.8138      0.0133     0.0089     0.0254     kread(5ffd78)
11      0.4616      0.0420     0.0262     0.0835     thread_create(407360)
22      0.2570      0.0117     0.0062     0.0373     mprotect(6d5bd8)
12      0.2126      0.0177     0.0100     0.0324     thread_setstate(40a660)
115     0.1875      0.0016     0.0012     0.0037     klseek(5ffe38)
12      0.1061      0.0088     0.0032     0.0134     sbrk(6d4f90)
23      0.0803      0.0035     0.0018     0.0072     trcgent(4078d8)

...(lines omitted)...

                          Pending System Calls Summary
                          -----
Accumulated   SVC (Address)
Time (msec)
=====
0.0141  thread_tsleep(40a4f8)

                          Pthread Calls Summary
                          -----
Count   Total Time   % sys   Avg Time   Min Time   Max Time   Pthread Routine
=====  =====
11      0.9545      0.01%   0.0868     0.0457     0.1833     pthread_create
8       0.0725      0.00%   0.0091     0.0064     0.0205     pthread_join
1       0.0553      0.00%   0.0553     0.0553     0.0553     pthread_detach
1       0.0341      0.00%   0.0341     0.0341     0.0341     pthread_cancel
1       0.0229      0.00%   0.0229     0.0229     0.0229     pthread_kill

                          Pending Pthread Calls Summary
                          -----
Accumulated   Pthread Routine
Time (msec)
=====
0.0025  pthread_join

processor affinity: 0.600000

Processor Dispatch Histogram for pthread (CPUid : times_dispatched):
CPU 0 : 4
CPU 1 : 1

total number of dispatches : 5
avg. dispatch wait time (ms): 798.449725

Thread affinity: 0.333333

Thread Dispatch Histogram for pthread (thread id : number dispatches):
Thread id 688279 : 1
Thread id 856237 : 1
Thread id 1007759 : 1

total number of pthread dispatches: 3
avg. dispatch wait time (ms): 1330.749542

Data on Interrupts that Occurred while Pthread was Running
```

Type of Interrupt	Count
Data Access Page Faults (DSI):	452
Instr. Fetch Page Faults (ISI):	0
Align. Error Interrupts:	0
IO (external) Interrupts:	0
Program Check Interrupts:	0
FP Unavailable Interrupts:	0
FP Imprecise Interrupts:	0
RunMode Interrupts:	0
Decrementer Interrupts:	2
Queued (Soft level) Interrupts:	0

The information in the pthreads summary report includes the following:

Item	Descriptor
<b>Pthread ID</b>	The Pthread ID of the thread.
<b>Process ID</b>	The Process ID that the pthread belongs to.
<b>Process Name</b>	The process name, if known, that the pthread belongs to.
<b>Total Application Time (ms)</b>	The amount of time, expressed in milliseconds, that the pthread spent in application mode.
<b>Total System Call Time (ms)</b>	The amount of time, expressed in milliseconds, that the pthread spent in system call mode.

The information in the application time details report includes the following:

Item	Descriptor
<b>Total Pthread Call Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in traced pthread library calls.
<b>Total Pthread Dispatch Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in libpthreads dispatch code.
<b>Total Pthread Idle Dispatch Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in libpthreads <b>vp_sleep</b> code.
<b>Total Other Time</b>	The amount of time, expressed in milliseconds, that the pthread spent in non-traced user mode code.
<b>Total number of pthread dispatches</b>	The total number of times a pthread belonging to the process was dispatched by the libpthreads dispatcher.
<b>Total number of pthread idle dispatches</b>	The total number of times a thread belonging to the process was in the libpthreads <b>vp_sleep</b> code.

The summary information in the report includes the following:

Item	Descriptor
<b>Pthread System Calls Summary</b>	A system call summary for the pthread; this has the same fields as the global System Call Summary. It also includes elapsed time information if the <b>-e</b> flag is specified and error information if the <b>-s</b> flag is specified.
<b>Pending System Calls Summary</b>	If the pthread was executing a system call at the end of the trace, a pending system call summary will be printed. This has the Accumulated Time and Supervisor Call (SVC Address) fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pthread Hypervisor Calls Summary</b>	A summary of the hypervisor calls for the pthread. This has the same fields as the global hypervisor calls summary. It also includes elapsed time information if the <b>-e</b> flag is specified.

Item	Descriptor
<b>Pending Hypervisor Calls Summary</b>	If the pthread was executing a hypervisor call at the end of the trace, a pending hypervisor calls summary will be printed. This has the Accumulated Time and Hypervisor Call fields. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pthread Calls Summary</b>	A summary of the pthread library calls for the pthread. This has the same fields as the global pthread Calls Summary. It also includes elapsed time information if the <b>-e</b> flag is specified.
<b>Pending Pthread Calls Summary</b>	If the pthread was executing a pthread library call at the end of the trace, a pending pthread call summary will be printed. This has the Accumulated Time and Pthread Routine fields. It also includes elapsed time information if the <b>-e</b> flag is specified.

The pthreads summary report also includes the following information:

Item	Descriptor
<b>processor affinity</b>	Probability that for any dispatch of the pthread, the pthread was dispatched to the same processor on which it last executed.
<b>Processor Dispatch Histogram for pthread</b>	The number of times that the pthread was dispatched to each CPU in the system.
<b>avg. dispatch wait time</b>	The average elapsed time for the pthread from being undischatched and its next dispatch.
<b>Thread affinity</b>	The probability that for any dispatch of the pthread, the pthread was dispatched to the same kernel thread on which it last executed
<b>Thread Dispatch Histogram for pthread</b>	The number of times that the pthread was dispatched to each kernel thread in the process.
<b>total number of pthread dispatches</b>	The total number of times the pthread was dispatched by the libpthread dispatcher.
<b>Data on Interrupts that occurred while Pthread was Running</b>	The number of times each type of FLIH occurred while the pthread was executing.

## Simple performance lock analysis tool (splat)

The Simple Performance Lock Analysis Tool (splat) is a software tool that generates reports on the use of synchronization locks. These include the simple and complex locks provided by the AIX kernel, as well as user-level mutexes, read and write locks, and condition variables provided by the **PThread** library.

The **splat** tool is not currently equipped to analyze the behavior of the Virtual Memory Manager (VMM) and PMAP locks used in the AIX kernel.

### splat command syntax

Review the **splat** command syntax, flags, and parameters.

The syntax for the **splat** command is as follows:

```
splat [-i file] [-n file] [-o file] [-d [bfta]] [-l address][-c class] [-s [acelmsS]] [-C#] [-S#] [-t start] [-T stop] [-p]
```

```
splat -h [topic]
```

```
splat -j
```

**Flags**

The flags of the **splat** command are:

---

<b>Item</b>	<b>Descriptor</b>
<b>-i</b> <i>inputfile</i>	Specifies the &SWsym.AIX; trace log file input.
<b>-n</b> <i>namefile</i>	Specifies the file containing output of the <b>gensyms</b> command.
<b>-o</b> <i>outputfile</i>	Specifies an output file (default is <b>stdout</b> ).
<b>-d</b> <i>detail</i>	Specifies the level of detail of the report.
<b>-c</b> <i>class</i>	Specifies class of locks to be reported.
<b>-l</b> <i>address</i>	Specifies the address for which activity on the lock will be reported.
<b>-s</b> <i>criteria</i>	Specifies the sort order of the lock, function, and thread.
<b>-C</b> <i>CPUs</i>	Specifies the number of processors on the MP system that the trace was drawn from. The default is 1. This value is overridden if more processors are observed to be reported in the trace.
<b>-S</b> <i>count</i>	Specifies the number of items to report on for each section. The default is 10. This gives the number of locks to report in the Lock Summary and Lock Detail reports, as well as the number of functions to report in the Function Detail and threads to report in the Thread detail (the <b>-s</b> option specifies how the most significant locks, threads, and functions are selected).
<b>-t</b> <i>starttime</i>	Overrides the start time from the first event recorded in the trace. This flag forces the analysis to begin an event that occurs <i>starttime</i> seconds after the first event in the trace.
<b>-T</b> <i>stoptime</i>	Overrides the stop time from the last event recorded in the trace. This flag forces the analysis to end with an event that occurs <i>stoptime</i> seconds after the first event in the trace.
<b>-j</b>	Prints the list of IDs of the trace hooks used by the <b>splat</b> command.
<b>-h</b> <i>topic</i>	Prints a help message on usage or a specific topic.
<b>-p</b>	Specifies the use of the PURR register to calculate CPU times.

## Parameters

The parameters associated with the **splat** command are:

---

<b>Item</b>	<b>Descriptor</b>
<b>inputfile</b>	The AIX trace log file input. This file can be a merge trace file generated using the <b>trcrpt -r</b> command.
<b>namefile</b>	File containing output of the <b>gensyms</b> command.
<b>outputfile</b>	File to write reports to.
<b>detail</b>	The detail level of the report, it can be one of the following: <b>basic</b> Lock summary plus lock detail (the default) <b>function</b> Basic plus function detail <b>thread</b> Basic plus thread detail <b>all</b> Basic plus function plus thread detail

The parameters associated with the **splat** command are: *(continued)*

Item	Descriptor
<b>class</b>	Activity classes, which is a decimal value found in the <code>/usr/include/sys/lockname.h</code> file.
<b>address</b>	The address to be reported, given in hexadecimal.
<b>criteria</b>	Order the lock, function, and thread reports by the following criteria: <ul style="list-style-type: none"> <li><b>a</b> Acquisitions</li> <li><b>c</b> Percent processor time held</li> <li><b>e</b> Percent elapsed time held</li> <li><b>l</b> Lock address, function address, or thread ID</li> <li><b>m</b> Miss rate</li> <li><b>s</b> Spin count</li> <li><b>S</b> Percent processor spin hold time (the default)</li> </ul>
<b>CPUs</b>	The number of processors on the MP system that the trace was drawn from. The default is 1. This value is overridden if more processors are observed to be reported in the trace.
<b>count</b>	The number of locks to report in the Lock Summary and Lock Detail reports, as well as the number of functions to report in the Function Detail and threads to report in the Thread detail. (The <b>-s</b> option specifies how the most significant locks, threads, and functions are selected).
<b>starttime</b>	The number of seconds after the first event recorded in the trace that the reporting starts.
<b>stoptime</b>	The number of seconds after the first event recorded in the trace that the reporting stops.
<b>topic</b>	Help topics, which are: all overview input names reports sorting

## Measurement and sampling

The **splat** tool takes as input an AIX trace log file or (for an SMP trace) a set of log files, and preferably a **names** file produced by the **gennames** or **gensyms** command.

The procedure for generating these files is shown in the **trace** section. When you run **trace**, you will usually use the flag **-J splat** to capture the events analyzed by **splat** (or without the **-J** flag, to capture all events). The significant trace hooks are shown in the following table:

Hook ID	Event name	Event explanation
106	HKWD_KERN_DISPATCH	The thread is dispatched from the run queue to a processor.
10C	HKWD_KERN_IDLE	The idle process is been dispatched.

Hook ID	Event name	Event explanation
10E	HKWD_KERN_RELOCK	One thread is suspended while another is dispatched; the ownership of a <b>RunQ</b> lock is transferred from the first to the second.
112	HKWD_KERN_LOCK	The thread attempts to secure a kernel lock; the sub-hook shows what happened.
113	HKWD_KERN_UNLOCK	A kernel lock is released.
134	HKWD_SYSC_EXECVE	An exec supervisor call (SVC) has been issued by a (forked) process.
139	HKWD_SYSC_FORK	A fork SVC has been issued by a process.
419	HKWD_CPU_PREEMPT	A process has been preempted.
465	HKWD_SYSC_CRTTHREAD	A thread_create SVC has been issued by a process.
46D	HKWD_KERN_WAITLOCK	The thread is enqueued to wait on a kernel lock.
46E	HKWD_KERN_WAKEUPLOCK	A thread has been awakened.
606	HKWD_PTHREAD_COND	Operations on a Condition Variable.
607	HKWD_PTHREAD_MUTEX	Operations on a Mutex.
608	HKWD_PTHREAD_RWLOCK	Operations on a Read/Write Lock.
609	HKWD_PTHREAD_GENERAL	Operations on a <b>PThread</b> .

## Execution, trace, and analysis Intervals

In some cases, you can use the **trace** tool to capture the entire execution of a workload, while in other cases you will capture only an interval of the execution.

The *execution interval* is the entire time that a workload runs. This interval is arbitrarily long for server workloads that run continuously. The *trace interval* is the time actually captured in the trace log file by **trace**. The length of this trace interval is limited by how large a trace log file will fit on the file system.

In contrast, the analysis interval is the portion of the trace interval that is analyzed by the **splat** command. The **-t** and **-T** flags indicate to the **splat** command to start and finish analysis some number of seconds after the first event in the trace. By default, the **splat** command analyzes the entire trace, so this analysis interval is the same as the trace interval.

**Note:** As an optimization, the **splat** command stops reading the trace when it finishes its analysis, so it indicates that the trace and analysis intervals end at the same time even if they do not.

To most accurately estimate the effect of lock activity on the computation, you will usually want to capture the longest trace interval that you can, and analyze that entire interval with the **splat** command. The **-t** and **-T** flags are usually used for debugging purposes to study the behavior of the **splat** command across a few events in the trace.

As a rule, either use large buffers when collecting a trace, or limit the captured events to the ones you need to run the **splat** command.

## Trace discontinuities

The **splat** command uses the events in the trace to reconstruct the activities of threads and locks in the original system.

If part of the trace is missing, it is because one of the following situations exists:

- Tracing was stopped at one point and restarted at a later point.

- One processor fills its trace buffer and stops tracing, while other processors continue tracing.
- Event records in the trace buffer were overwritten before they could be copied into the trace log file.

In any of the above cases, the **splat** command will not be able to correctly analyze all the events across the trace interval. The policy of **splat** is to finish its analysis at the first point of discontinuity in the trace, issue a warning message, and generate its report. In the first two cases, the message is as follows:

```
TRACE OFF record read at 0.567201 seconds. One or more of the CPUs has
stopped tracing. You might want to generate a longer trace using larger
buffers and re-run splat.
```

In the third case, the message is as follows:

```
TRACEBUFFER WRAPAROUND record read at 0.567201 seconds. The input trace
has some records missing; splat finishes analyzing at this point. You
might want to re-generate the trace using larger buffers and re-run splat.
```

Some versions of the AIX kernel or **PThread** library might be incompletely instrumented, so the traces will be missing events. The **splat** command might not provide correct results in this case.

## Address-to-Name resolution in the splat command

The lock instrumentation in the kernel and **PThread** library is what captures the information for each lock event.

Data addresses are used to identify locks; instruction addresses are used to identify the point of execution. These addresses are captured in the event records in the trace, and used by the **splat** command to identify the locks and the functions that operate on them.

However, these addresses are not of much use to the programmer, who would rather know the names of the lock and function declarations so that they can be located in the program source files. The conversion of names to addresses is determined by the compiler and loader, and can be captured in a file using the **gensyms** command. The **gensyms** command also captures the contents of the **/usr/include/sys/lockname.h** file, which declares classes of kernel locks.

The **gensyms** output file is passed to the **splat** command with the **-n** flag. When **splat** reports on a kernel lock, it provides the best identification that it can.

Kernel locks that are declared are resolved by name. Locks that are created dynamically are identified by class if their class name is given when they are created. The **libpthreads.a** instrumentation is not equipped to capture names or classes of **PThread** synchronizers, so they are always identified by address only.

## Examples of generated reports

The report generated by the **splat** command consists of an execution summary, a gross lock summary, and a per-lock summary, followed by a list of lock detail reports that optionally includes a function detail or a thread detail report.

### Execution summary

The execution summary report is generated by default when you use the **splat** command.

The following example shows a sample of the execution summary.

```
*****
splat Cmd:   splat -p -sa -da -S100 -i trace.cooked -n gensyms -o splat.out

Trace Cmd:   trace -C all -aj 600,603,605,606,607,608,609 -T 20000000 -L 20000000 -o CONDDVAR.raw
Trace Host:  darkwing (0054451E4C00) AIX 5.2
Trace Date:  Thu Sep 27 11:26:16 2002

PURR was used to calculate CPU times.

Elapsed Real Time:      0.098167
```

```

Number of CPUs Traced: 1 (Observed):0
Cumulative CPU Time: 0.098167

```

		----- start -----	----- stop -----
trace interval	(absolute tics)	967436752	969072535
	(relative tics)	0	1635783
	(absolute secs)	58.057947	58.156114
analysis interval	(relative secs)	0.000000	0.098167
	(absolute tics)	967436752	969072535
	(trace-relative tics)	0	1635783
	(self-relative tics)	0	1635783
	(absolute secs)	58.057947	58.156114
	(trace-relative secs)	0.000000	0.098167
	(self-relative secs)	0.000000	0.098167

```

*****

```

From the example above, you can see that the execution summary consists of the following elements:

- The **splat** version and build information, disclaimer, and copyright notice.
- The command used to run **splat**.
- The **trace** command used to collect the trace.
- The host on which the trace was taken.
- The date that the trace was taken.
- A sentence specifying whether the PURR register was used to calculate CPU times.
- The real-time duration of the trace, expressed in seconds.
- The maximum number of processors that were observed in the trace (the number specified in the trace conditions information, and the number specified on the **splat** command line).
- The cumulative processor time, equal to the duration of the trace in seconds times the number of processors that represents the total number of seconds of processor time consumed.
- A table containing the start and stop times of the trace interval, measured in tics and seconds, as absolute timestamps, from the trace records, as well as relative to the first event in the trace
- The start and stop times of the analysis interval, measured in tics and seconds, as absolute timestamps, as well as relative to the beginning of the trace interval and the beginning of the analysis interval.

## Gross lock summary

The gross lock summary report is generated by default when you use the **splat** command.

The following example shows a sample of the gross lock summary report.

```

*****

```

	Total	Unique Addresses	Acquisitions (or Passes)	Acq. or Passes per Second	Total System Spin Time
	-----	-----	-----	-----	-----
AIX (all) Locks:	523	523	1323045	72175.7768	0.003986
RunQ:	2	2	487178	26576.9121	0.000000
Simple:	480	480	824898	45000.4754	0.003986
Transformed:	22	18	234	352.3452	
Krlck:	50	21	76876	32.6548	0.000458
Complex:	41	41	10969	598.3894	0.000000
PThread CondVar:	7	6	160623	8762.4305	0.000000
Mutex:	128	116	1927771	105165.2585	10.280745 *
RWLock:	0	0	0	0.0000	0.000000

```

( spin time goal )
*****

```

The gross lock summary report table consists of the following columns:

<b>Item</b>	<b>Descriptor</b>
<b>Total</b>	The number of AIX Kernel locks, followed by the number of each type of AIX Kernel lock; RunQ, Simple, and Complex. Under some conditions, this will be larger than the sum of the numbers of RunQ, Simple, and Complex locks because we might not observe enough activity on a lock to differentiate its type. This is followed by the number of PThread condition-variables, the number of PThread Mutexes, and the number of PThread Read/Write. The Transformed value represents the number of different simple locks responsible for the allocation (and liberation) of at least one Krlock. In this case, two simple locks will be different if they are not created at the same time or they do not have the same address.
<b>Unique Addresses</b>	The number of unique addresses observed for each synchronizer type. Under some conditions, a lock will be destroyed and re-created at the same address; the <b>splat</b> command produces a separate lock detail report for each instance because the usage might be different. The Transformed value represents the number of different simple locks responsible for the allocation (and liberation) of at least one Krlock. In this case, simple locks created at different times but with the same address increment the counter only once.
<b>Acquisitions (or Passes)</b>	For locks, the total number of times acquired during the analysis interval; for PThread condition-variables, the total number of times the condition passed during the analysis interval. The Transformed value represents the number of acquisitions made by a thread holding the corresponding Krlock.
<b>Acq. or Passes (per Second)</b>	Acquisitions or passes per second, which is the total number of acquisitions or passes divided by the elapsed real time of the trace. The Transformed value represents the acquisition rate for the acquisitions made by threads holding the corresponding krlock.
<b>% Total System spin Time</b>	The cumulative time spent spinning on each synchronizer type, divided by the cumulative processor time, times 100 percent. The general goal is to spin for less than 10 percent of the processor time; a message to this effect is printed at the bottom of the table. If any of the entries in this column exceed 10 percent, they are marked with an asterisk (*). For simple locks, the spin time of the Krlocks is included.

## Per-lock summary

The pre-locl summary report is generated by default when you use the **splat** command.

The following example shows a sample of the per-lock summary report.

```

*****
*****
100 max entries, Summary sorted by Acquisitions:

Lock Names,          T Acqui-      Wait
Comb                p or        or
Class, or Address   e Passes Spins  form      %Miss  %Total  / CSec  CPU  Elapse
Spin
***** * ***** *
*****
PROC_INT_CLASS.0003 Q 486490 0    0    0.0000  36.7705 26539.380 5.3532 100.000
0.0000
THREAD_LOCK_CLASS.0012 S 323277 0    9468 0.0000  24.4343 17635.658 6.8216 6.8216
0.0000
THREAD_LOCK_CLASS.0118 D 323094 0    4568 0.0000  24.4205 17625.674 6.7887 6.7887
0.0000
ELIST_CLASS.003C    S 80453 0    201 0.0000  6.0809 4388.934 1.0564 1.0564
0.0000
ELIST_CLASS.0044    S 80419 0    110 0.0000  6.0783 4387.080 1.1299 1.1299
0.0000
tod_lock            C 10229 0    0    0.0000  0.7731 558.020 0.2212 0.2212
0.0000
LDATA_CONTROL_LOCK.0000 D 1833 0    10 0.0000  0.1385 99.995 0.0204 0.0204

```

```

0.0000
U_TIMER_CLASS.0014      S 1514  0   23      0.0000  0.1144   82.593  0.0536   0.0536
0.0000

( ... lines omitted ... )

000000002FF22B70      L 368838 0   N/A      0.0000 100.000  9622.964 99.9865  99.9865
0.0000
00000000F00C3D74      M 160625 0   0         0.0000 14.2831  8762.540 99.7702  99.7702
0.0000
00000000200017E8      M 160625 175  0         0.1088 14.2831  8762.540 42.9371  42.9371
0.1487
0000000020001820      V 160623 0   624      0.0000 100.000  1271.728 N/A       N/A
N/A
00000000F00C3750      M   37 0   0         0.0000  0.0033   2.018  0.0037  0.0037
0.0000
00000000F00C3800      M   30 0   0         0.0000  0.0027   1.637  0.0698  0.0698
0.0000

( ... lines omitted ... )
*****

```

The first line indicates the maximum number of locks to report (100 in this case, but we show only 14 of the entries here) as specified by the **-S 100** flag. The report also indicates that the entries are sorted by the total number of acquisitions or passes, as specified by the **-sa** flag. The various Kernel locks and **PThread** synchronizers are treated as two separate lists in this report, so the report would produce the top 100 Kernel locks sorted by acquisitions, followed by the top 100 **PThread** synchronizers sorted by acquisitions or passes.

The per-lock summary table consists of the following columns:

<b>Item</b>	<b>Descriptor</b>
<b>Lock Names, Class, or Address</b>	The name, class, or address of the lock, depending on whether the <b>splat</b> command could map the address from a name file.
<b>Type</b>	The type of the lock, identified by one of the following letters: <ul style="list-style-type: none"> <li><b>Q</b> A RunQ lock</li> <li><b>S</b> An enabled simple kernel lock</li> <li><b>D</b> A disabled simple kernel lock</li> <li><b>C</b> A complex kernel lock</li> <li><b>M</b> A <b>PThread</b> mutex</li> <li><b>V</b> A <b>PThread</b> condition-variable</li> <li><b>L</b> A <b>PThread</b> read/write lock</li> </ul>
<b>Acquisitions or Passes</b>	The number of times that the lock was acquired or the condition passed, during the analysis interval.
<b>Spins</b>	The number of times that the lock (or condition-variable) was spun on during the analysis interval.
<b>Wait or Transform</b>	The number of times that a thread was driven into a wait state for that lock or condition-variable during the analysis interval. When Krlocks are enabled, a simple lock never enters the wait state and this value represents the number of Krlocks that the simple lock has allocated, which is the transform count of simple locks.

<b>Item</b>	<b>Descriptor</b>
<b>%Miss</b>	The percentage of access attempts that resulted in a spin as opposed to a successful acquisition or pass.
<b>%Total</b>	The percentage of all acquisitions that were made to this lock, out of all acquisitions to all locks of this type. All AIX locks (RunQ, simple, and complex) are treated as being the same type for this calculation. The <b>PThread</b> synchronizers mutex, condition-variable, and read/write lock are all distinct types.
<b>Locks or Passes / CSec</b>	The number of times that the lock (or condition-variable) was acquired (or passed) divided by the cumulative processor time. This is a measure of the acquisition frequency of the lock.
<b>Percent Holdtime</b>	
<b>Real CPU</b>	The percentage of the cumulative processor time that the lock was held by any thread at all, whether running or suspended. Note that this definition is not applicable to condition-variables because they are not held.
<b>Real Elapse</b>	The percentage of the elapsed real time that the lock was held by any thread at all, whether running or suspended. Note that this definition is not applicable to condition-variables because they are not held.
<b>Comb Spin</b>	The percentage of the cumulative processor time that executing threads spent spinning on the lock. The <b>PThreads</b> library uses waiting for condition-variables, so there is no time actually spent spinning.

## AIX kernel lock details

By default, the **splat** command prints a lock detail report for each entry in the summary report. The AIX Kernel locks can be either simple or complex.

The RunQ lock is a special case of the simple lock, although its pattern of usage will differ markedly from other lock types. The **splat** command distinguishes it from the other simple locks to ease its analysis.

### Disabled simple and RunQ lock details

In an AIX SIMPLE Lock report, the first line starts with either [AIX SIMPLE Lock] or [AIX RunQ lock].

If the **gennames** or **gensyms** output file permits, the ADDRESS is also converted into a lock NAME and CLASS, and the containing kernel extension (KEX) is identified as well. The CLASS is printed with an eight hex-digit extension indicating how many locks of this class were allocated prior to it.

```
[AIX SIMPLE Lock]                ADDRESS: 0000000020000D60                KEX: unknown
=====
Type:      | Miss Spin  Trans-  Busy  |      Secs Held  | Percent Held ( 35.568534s )
Disabled  | Rate Count Count  Count | CPU   Elapsed  | Real  Real   Comb  Real
           |100.000 1    2658   0    |0.000000 0.000000 | 0.00  0.00  0.00  29.62
-----
Total Acquisitions: 12945 |SpinQ  Min  Max  Avg | Krllocks SpinQ Min  Max  Avg
Acq. holding krllock: 2498 |Depth  0   1   0  | Depth          0   1   0
-----
PROD      |          CONFER          | HANDOFF
0         | SELF:    0   TARGET:    0          ALL:    0 | 0
           | w/ preemption: 0   w/ preemption: 0 |
```

#### Lock Activity (mSecs) - Interrupts Disabled

SIMPLE	Count	Minimum	Maximum	Average	Total
+++++++	+++++++	+++++++	+++++++	+++++++	+++++++
LOCK	0	0.000000	0.000000	0.000000	0.000000
w/ KRLOCK	0	0.000000	0.000000	0.000000	0.000000
SPIN	0	0.000000	0.000000	0.000000	0.000000
KRLOCK LOCK	0	0.000000	0.000000	0.000000	0.000000
KRLOCK SPIN	0	0.000000	0.000000	0.000000	0.000000

```

TRANSFORM          0          0.000000          0.000000          0.000000          0.000000

Function Name      Acqui- Miss Spin Transf. Busy Percent Held of Total Time
Address           Offset  sitions Rate Count Count Count CPU Elapse Spin Transf. Return Address Start
^^^^^^^^^^^^^^^^ ^^^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^ ^^^^^^^^^^^^^^^^^
^^^^^^^^^^^^^^^^ ^^^^^^^^^
.dispatch         3177  0.63  20    0    0    0.00  0.02  0.00  0.00  0000000000039CF4
0000000000000000 00039CF4
.dispatch         6053  0.31  19    0    0    0.03  0.07  0.00  0.00  00000000000398E4
0000000000000000 000398E4
.setrq            3160  0.19   6    0    0    0.01  0.02  0.00  0.00  0000000000038E60
0000000000000000 00038E60
.steal_threads    1      0.00  0    0    0    0.00  0.00  0.00  0.00  0000000000066A68
0000000000000000 00066A68
.steal_threads    6      0.00  0    0    0    0.00  0.00  0.00  0.00  0000000000066CE0
0000000000000000 00066CE0
.dispatch         535  2.19  12    0   12   0.01  0.02  0.00  0.00  0000000000039D88
0000000000000000 00039D88
.dispatch         2      0.00  0    0    0    0.00  0.00  0.00  0.00  0000000000039D14
0000000000000000 00039D14
.prio_requeue    7      0.00  0    0    0    0.00  0.00  0.00  0.00  000000000003B2A4
0000000000000000 0003B2A4
.setnewrq         4      0.00  0    0    0    0.00  0.00  0.00  0.00  0000000000038980
0000000000000000 00038980

ThreadID          Acqui- Miss Spin Transf. Busy Percent Held of Total Time
                sitions Rate Count Count Count CPU Elapse Spin Transf. ProcessID Process
                ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~ ~~~~~~
775              11548  0.34  39    0    0    0.06  0.10  0.00  0.00  774      wait
35619            3      25.00  1    0    0    0.00  0.00  0.00  0.00  18392   sleep
31339            21     4.55  1    0    0    0.00  0.00  0.00  0.00  7364   java
35621            2      0.00  0    0    0    0.00  0.00  0.00  0.00  18394   locktrace

(... lines omitted ...)

```

The SIMPLE lock report fields are as follows:

<b>Item</b>	<b>Descriptor</b>
<b>Type</b>	If the simple lock was used with interrupts, this field is enabled. Otherwise, this field is disabled.
<b>Miss Rate</b>	The percentage of attempts that failed to acquire the lock.
<b>Spin Count</b>	The number of unsuccessful attempts to acquire the lock.
<b>Busy Count</b>	The number of <b>simple_lock_try</b> calls that returned busy.
<b>Seconds Held</b>	This field contains the following sub-fields:
	<b>CPU</b>
	The total number of processor seconds that the lock was held by an executing thread.
	<b>Elapsed</b>
	The total number of elapsed seconds that the lock was held by any thread, whether running or suspended.

<b>Item</b>	<b>Descriptor</b>
<b>Percent Held</b>	This field contains the following sub-fields: <b>Real CPU</b> The percentage of the cumulative processor time that the lock was held by an executing thread. <b>Real Elapsed</b> The percentage of the elapsed real time that the lock was held by any thread at all, either running or suspended. <b>Comb(ined) Spin</b> The percentage of the cumulative processor time that running threads spent spinning while trying to acquire this lock. <b>Real Wait</b> The percentage of elapsed real time that any thread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To determine how many threads were waiting simultaneously, look at the WaitQ Depth statistics.
<b>Total Acquisitions</b>	The number of times that the lock was acquired in the analysis interval. This includes successful <b>simple_lock_try</b> calls.
<b>Acq. holding krlock</b>	The number of acquisitions made by threads holding a Krlock.
<b>Transform count</b>	The number of Krlocks that have been used (allocated and freed) by the simple lock.
<b>SpinQ</b>	The minimum, maximum, and average number of threads spinning on the lock, whether executing or suspended, across the analysis interval.
<b>Krlocks SpinQ</b>	The minimum, maximum, and average number of threads spinning on a Krlock allocated by the simple lock, across the analysis interval.
<b>PROD</b>	The associated Krlocks <b>prod</b> calls count.
<b>CONFER SELF</b>	The confer to self calls count for the simple lock and the associated Krlocks.
<b>CONFER TARGET</b>	The confer to target calls count for the simple lock and the associated Krlocks.
<b>CONFER ALL</b>	The confer to all calls count for the simple lock and the associated Krlocks.
<b>HANDOFF</b>	The associated Krlocks <b>handoff</b> calls count.

The Lock Activity with Interrupts Enabled (milliseconds) and Lock Activity with Interrupts Disabled (milliseconds) sections contain information on the time that each lock state is used by the locks.

The states that a thread can be in (with respect to a given simple or complex lock) are as follows:

<b>Item</b>	<b>Descriptor</b>
<b>(no lock reference)</b>	The thread is running, does not hold this lock, and is not attempting to acquire this lock.
<b>LOCK</b>	The thread has successfully acquired the lock and is currently executing.
<b>LOCK with KRLOCK</b>	The thread has successfully acquired the lock, while holding the associated Krlock, and is currently executing.
<b>SPIN</b>	The thread is executing and unsuccessfully attempting to acquire the lock.
<b>KRLOCK LOCK</b>	The thread has successfully acquired the associated Krlock and is currently executing.
<b>KRLOCK SPIN</b>	The thread is executing and unsuccessfully attempting to acquire the associated Krlock.

Item	Descriptor
<b>TRANSFORM</b>	The thread has successfully allocated a Klock that it associates itself to and is executing.

The Lock Activity sections of the report measure the intervals of time (in milliseconds) that each thread spends in each of the states for this lock. The columns report the number of times that a thread entered the given state, followed by the maximum, minimum, and average time that a thread spent in the state once entered, followed by the total time that all threads spent in that state. These sections distinguish whether interrupts were enabled or disabled at the time that the thread was in the given state.

A thread can acquire a lock prior to the beginning of the analysis interval and release the lock during the analysis interval. When the **splat** command observes the lock being released, it recognizes that the lock had been held during the analysis interval up to that point and counts the time as part of the state-machine statistics. For this reason, the state-machine statistics might report that the number of times that the lock state was entered might actually be larger than the number of acquisitions of the lock that were observed in the analysis interval.

RunQ locks are used to protect resources in the thread management logic. These locks are acquired a large number of times and are only held briefly each time. A thread need not be executing to acquire or release a RunQ lock. Further, a thread might spin on a RunQ lock, but it will not go into an UNDISP or WAIT state on the lock. You will see a dramatic difference between the statistics for RunQ versus other simple locks.

### Enabled simple lock details

The Lock Activity sections of the report measure the intervals of time (in milliseconds) that each thread spends in each of the states for this lock. The columns report the number of times that a thread entered the given state, followed by the maximum, minimum, and average time that a thread spent in the state once entered, followed by the total time that all threads spent in that state.

These sections of the report distinguish whether interrupts were enabled or disabled at the time that the thread was in the given state.

The following example is an enabled simple lock detail report:

```
[AIX SIMPLE Lock]                CLASS:      PROC_INT_CLASS.00000004
ADDRESS: 000000000200786C
=====
Type      | Miss  Spin  Wait  Busy  |      Secs Held      | Percent Held ( 26.235284s )
Enabled   | Rate  Count Count Count | CPU      Elapsed   | Real  Real  Comb Real
          |      |      |      |      | CPU      Elapsed   | CPU  Elapsed Spin Wait
          |-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|
          | 0.438 57    2658  12    | 0.022852 0.032960 | 0.04  0.13  0.00  0.00
-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|
Total Acquisitions: 2498 | SpinQ  Min  Max  Avg | WaitQ  Min  Max  Avg
                   | Depth  0   1   0   | Depth  0   0   0
-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|-----|

                          Lock Activity (mSecs) - Interrupts Enabled

SIMPLE      Count      Minimum      Maximum      Average      Total
+++++++    ++++++    ++++++      ++++++      ++++++      ++++++
LOCK        8027      0.000597    0.022486    0.002847    22.852000
SPIN        45        0.001376    0.008960    0.004738    0.213212
UNDISP      0         0.000000    0.000000    0.000000    0.000000
WAIT        0         0.000000    0.000000    0.000000    0.000000
PREEMPT    4918      0.000811    0.009728    0.001955    9.615807

Function Name  Acqui-  Miss  Spin  Wait  Busy  Percent Held of Total Time
Address        sitions Rate  Count Count Count  CPU  Elapse Spin  Wait  Return Address  Start
^^^^^^^^^^^^  ^^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^^^^^^^^^^^
^^^^^^^^^^^^  ^^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^^^^^^^^^^^
.dispatch     3177    0.63  20    0    0    0.00  0.02  0.00  0.00  0000000000039CF4
0000000000000000 00039CF4
.dispatch     6053    0.31  19    0    0    0.03  0.07  0.00  0.00  00000000000398E4
0000000000000000 000398E4
.setrq        3160    0.19  6     0    0    0.01  0.02  0.00  0.00  0000000000038E60
0000000000000000 00038E60
```

```

.steal_threads 1 0.00 0 0 0 0.00 0.00 0.00 0.00 00000000000066A68
0000000000000000 00066A68
.steal_threads 6 0.00 0 0 0 0.00 0.00 0.00 0.00 00000000000066CE0
0000000000000000 00066CE0
.dispatch 535 2.19 12 0 12 0.01 0.02 0.00 0.00 00000000000039D88
0000000000000000 00039D88
.dispatch 2 0.00 0 0 0 0.00 0.00 0.00 0.00 00000000000039D14
0000000000000000 00039D14
.prio_requeue 7 0.00 0 0 0 0.00 0.00 0.00 0.00 0000000000003B2A4
0000000000000000 0003B2A4
.setnewirq 4 0.00 0 0 0 0.00 0.00 0.00 0.00 00000000000038980
0000000000000000 00038980

```

ThreadID	Acqui- sitions	Miss Rate	Spin Count	Wait Count	Busy Count	Percent CPU	Held of Elapse	Total Spin	Time Wait	ProcessID	Process Name
775	11548	0.34	39	0	0	0.06	0.10	0.00	0.00	774	wait
35619	3	25.00	1	0	0	0.00	0.00	0.00	0.00	18392	sleep
31339	21	4.55	1	0	0	0.00	0.00	0.00	0.00	7364	java
35621	2	0.00	0	0	0	0.00	0.00	0.00	0.00	18394	locktrace

(... lines omitted ...)

The SIMPLE lock report fields are as follows:

<b>Item</b>	<b>Descriptor</b>
<b>Type</b>	If the simple lock was used with interrupts, this field is enabled. Otherwise, this field is disabled.
<b>Total Acquisitions</b>	The number of times that the lock was acquired in the analysis interval. This includes successful <b>simple_lock_try</b> calls.
<b>Miss Rate</b>	The percentage of attempts that failed to acquire the lock.
<b>Spin Count</b>	The number of unsuccessful attempts to acquire the lock.
<b>Wait Count</b>	The number of times that a thread was forced into a suspended wait state, waiting for the lock to come available.
<b>Busy Count</b>	The number of <b>simple_lock_try</b> calls that returned busy.
<b>Seconds Held</b>	This field contains the following sub-fields:
	<b>CPU</b>
	The total number of processor seconds that the lock was held by an executing thread.
	<b>Elapsed</b>
	The total number of elapsed seconds that the lock was held by any thread, whether running or suspended.

<b>Item</b>	<b>Descriptor</b>
<b>Percent Held</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Real CPU</b> The percentage of the cumulative processor time that the lock was held by an executing thread.</li> <li><b>Real Elapsed</b> The percentage of the elapsed real time that the lock was held by any thread at all, either running or suspended.</li> <li><b>Comb(ined) Spin</b> The percentage of the cumulative processor time that running threads spent spinning while trying to acquire this lock.</li> <li><b>Real Wait</b> The percentage of elapsed real time that any thread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To determine how many threads were waiting simultaneously, look at the WaitQ Depth statistics.</li> </ul>
<b>SpinQ</b>	The minimum, maximum, and average number of threads spinning on the lock, whether executing or suspended, across the analysis interval.
<b>WaitQ</b>	The minimum, maximum, and average number of threads waiting on the lock, across the analysis interval.

The Lock Activity with Interrupts Enabled (milliseconds) and Lock Activity with Interrupts Disabled (milliseconds) sections contain information on the time that each lock state is used by the locks.

The states that a thread can be in (with respect to a given simple or complex lock) are as follows:

<b>Item</b>	<b>Descriptor</b>
<b>(no lock reference)</b>	The thread is running, does not hold this lock, and is not attempting to acquire this lock.
<b>LOCK</b>	The thread has successfully acquired the lock and is currently executing.
<b>SPIN</b>	The thread is executing and unsuccessfully attempting to acquire the lock.
<b>UNDISP</b>	The thread has become undispached while unsuccessfully attempting to acquire the lock.
<b>WAIT</b>	The thread has been suspended until the lock comes available. It does not necessarily acquire the lock at that time, but instead returns to a SPIN state.
<b>PREEMPT</b>	The thread is holding this lock and has become undispached.

A thread can acquire a lock prior to the beginning of the analysis interval and release the lock during the analysis interval. When the **splat** command observes the lock being released, it recognizes that the lock had been held during the analysis interval up to that point and counts the time as part of the state-machine statistics. For this reason, the state-machine statistics can report that the number of times that the lock state was entered might actually be larger than the number of acquisitions of the lock that were observed in the analysis interval.

RunQ locks are used to protect resources in the thread management logic. These locks are acquired a large number of times and are only held briefly each time. A thread need not be executing to acquire or release a RunQ lock. Further, a thread might spin on a RunQ lock, but it will not go into an UNDISP or WAIT state on the lock. You will see a dramatic difference between the statistics for RunQ versus other simple locks.

## Function detail

The function detail report is obtained by using the **-df** or **-da** options of **splat**.

The columns are defined as follows:

Item	Descriptor
<b>Function Name</b>	The name of the function that acquired or attempted to acquire this lock, if it could be resolved.
<b>Acquisitions</b>	The number of times that the function was able to acquire this lock. For complex lock and read/write, there is a distinction between acquisition for writing, <b>Acquisition Write</b> , and for reading, <b>Acquisition Read</b> .
<b>Miss Rate</b>	The percentage of acquisition attempts that failed.
<b>Spin Count</b>	The number of unsuccessful attempts by the function to acquire this lock. For complex lock and read/write there is a distinction between spin count for writing, <b>Spin Count Write</b> , and for reading, <b>Spin Count Read</b> .
<b>Transf. Count</b>	The number of times that a simple lock has allocated a Klock, while a thread was trying to acquire the simple lock.
<b>Busy Count</b>	The number of times <b>simple_lock_try</b> calls returned busy.
<b>Percent Held of Total Time</b>	Contains the following sub-fields: <b>CPU</b> Percentage of the cumulative processor time that the lock was held by an executing thread that had acquired the lock through a call to this function. <b>Elapse(d)</b> The percentage of the elapsed real time that the lock was held by any thread at all, whether running or suspended, that had acquired the lock through a call to this function. <b>Spin</b> The percentage of cumulative processor time that executing threads spent spinning on the lock while trying to acquire the lock through a call to this function. <b>Wait</b> The percentage of elapsed real time that executing threads spent waiting for the lock while trying to acquire the lock through a call to this function.
<b>Return Address</b>	The return address to this calling function, in hexadecimal.
<b>Start Address</b>	The start address to this calling function, in hexadecimal.
<b>Offset</b>	The offset from the function start address to the return address, in hexadecimal.

The functions are ordered by the same sorting criterion as the locks, controlled by the **-s** option of **splat**. Further, the number of functions listed is controlled by the **-S** parameter. The default is the top ten functions.

## Thread Detail

The Thread Detail report is obtained by using the **-dt** or **-da** options of **splat**.

At any point in time, a single thread is either running or it is not. When a single thread runs, it only runs on one processor. Some of the composite statistics are measured relative to the cumulative processor time when they measure activities that can happen simultaneously on more than one processor, and the magnitude of the measurements can be proportional to the number of processors in the system. In contrast, the thread statistics are generally measured relative to the elapsed real time, which is the amount of time that a single processor spends processing and the amount of time that a single thread spends in an executing or suspended state.

The Thread Detail report columns are defined as follows:

<b>Item</b>	<b>Descriptor</b>
<b>ThreadID</b>	The thread identifier.
<b>Acquisitions</b>	The number of times that this thread acquired the lock.
<b>Miss Rate</b>	The percentage of acquisition attempts by the thread that failed to secure the lock.
<b>Spin Count</b>	The number of unsuccessful attempts by this thread to secure the lock.
<b>Transf. Count</b>	The number of times that a simple lock has allocated a Klock, while a thread was trying to acquire the simple lock.
<b>Wait Count</b>	The number of times that this thread was forced to wait until the lock came available.
<b>Busy Count</b>	The number of <b>simple_lock_try()</b> calls that returned busy.
<b>Percent Held of Total Time</b>	Consists of the following sub-fields: <b>CPU</b> The percentage of the elapsed real time that this thread executed while holding the lock. <b>Elapse(d)</b> The percentage of the elapsed real time that this thread held the lock while running or suspended. <b>Spin</b> The percentage of elapsed real time that this thread executed while spinning on the lock. <b>Wait</b> The percentage of elapsed real time that this thread spent waiting on the lock.
<b>Process ID</b>	The Process identifier (only for simple and complex lock report).
<b>Process Name</b>	Name of the process using the lock (only for simple and complex lock report).

### ***Complex-Lock report***

AIX Complex lock supports recursive locking, where a thread can acquire the lock more than once before releasing it, as well as differentiating between write-locking, which is exclusive, from read-locking, which is not exclusive.

This report begins with [AIX COMPLEX Lock]. Most of the entries are identical to the simple lock report, while some of them are differentiated by read/write/upgrade. For example, the SpinQ and WaitQ statistics include the minimum, maximum, and average number of threads spinning or waiting on the lock. They also include the minimum, maximum, and average number of threads attempting to acquire the lock for reading versus writing. Because an arbitrary number of threads can hold the lock for reading, the report includes the minimum, maximum, and average number of readers in the LockQ that holds the lock.

A thread might hold a lock for writing; this is exclusive and prevents any other thread from securing the lock for reading or for writing. The thread downgrades the lock by simultaneously releasing it for writing and acquiring it for reading; this permits other threads to also acquire the lock for reading. The reverse of this operation is an upgrade; if the thread holds the lock for reading and no other thread holds it as well, the thread simultaneously releases the lock for reading and acquires it for writing. The upgrade operation might require that the thread wait until other threads release their read-locks. The downgrade operation does not.

A thread might acquire the lock to some recursive depth; it must release the lock the same number of times to free it. This is useful in library code where a lock must be secured at each entry-point to the library; a thread will secure the lock once as it enters the library, and internal calls to the library entry-

points simply re-secure the lock, and release it when returning from the call. The minimum, maximum, and average recursion depths of any thread holding this lock are reported in the table.

A thread holding a recursive write-lock is not permitted to downgrade it because the downgrade is intended to apply to only the last write-acquisition of the lock, and the prior acquisitions had a real reason to keep the acquisition exclusive. Instead, the lock is marked as being in the downgraded state, which is erased when the this latest acquisition is released or upgraded. A thread holding a recursive read-lock can only upgrade the latest acquisition of the lock, in which case the lock is marked as being upgraded. The thread will have to wait until the lock is released by any other threads holding it for reading. The minimum, maximum, and average recursion-depths of any thread holding this lock in an upgraded or downgraded state are reported in the table.

The Lock Activity report also breaks down the time based on what task the lock is being secured for (reading, writing, or upgrading).

No time is reported to perform a downgrade because this is performed without any contention. The upgrade state is only reported for the case where a recursive read-lock is upgraded. Otherwise, the thread activity is measured as releasing a read-lock and acquiring a write-lock.

The function and thread details also break down the acquisition, spin, and wait counts by whether the lock is to be acquired for reading or writing.

## PThread synchronizer reports

By default, the **splat** command prints a detailed report for each **PThread** entry in the summary report. The **PThread** synchronizers are of the following types: mutex, read/write lock, and condition-variable.

The mutex and read/write lock are related to the AIX complex lock. You can view the similarities in the lock detail reports. The condition-variable differs significantly from a lock, and this is reflected in the report details.

The **PThread** library instrumentation does not provide names or classes of synchronizers, so the addresses are the only way we have to identify them. Under certain conditions, the instrumentation can capture the return addresses of the function call stack, and these addresses are used with the **gensyms** output to identify the call chains when these synchronizers are created. The creation and deletion times of the synchronizer can sometimes be determined as well, along with the ID of the **PThread** that created them.

### Mutex reports

The **PThread** mutex is similar to an AIX simple lock in that only one thread can acquire the lock, and is like an AIX complex lock in that it can be held recursively.

```
[PThread MUTEX]    ADDRESS:    00000000F0154CD0
Parent Thread:    0000000000000001    creation time:    26.232305
Pid: 18396        Process Name: trcstop
Creation call-chain =====
00000000D268606C    .pthread_mutex_lock
00000000D268EB88    .pthread_once
00000000D01FE588    .__libs_init
00000000D01EB2FC    .__libc_inline_callbacks
00000000D01EB280    .__libc_declare_data_functions
00000000D269F960    .__pth_init_libc
00000000D268A2B4    .pthread_init
00000000D01EAC08    .__modinit
000000001000014C    .__start
=====
Acqui- | Miss Spin Wait Busy |      Secs Held | Percent Held ( 26.235284s )
sitions | Rate Count Count Count | CPU Elapsed | Real Real Comb Real
1 | 0.000 0 0 0 | 0.000006 0.000006 | 0.00 0.00 0.00 0.00
-----
Depth   Min  Max  Avg
SpinQ   0   0   0
WaitQ   0   0   0
Recursion 0   1   0

PThreadID  Acqui-  Miss  Spin  Wait  Busy  Percent Held of Total Time
           sitions Rate Count Count Count CPU Elapse Spin Wait
-----
1          1    0.00  0    0    0    0.00  0.00  0.00  0.00
-----
Function Name  Acqui-  Miss  Spin  Wait  Busy  Percent Held of Total Time
               sitions Rate Count Count Count CPU Elapse Spin Wait Return Address Start Address
```



<b>Item</b>	<b>Descriptor</b>
<b>Depth</b>	This field contains the following sub-fields:
	<b>SpinQ</b> The minimum, maximum, and average number of threads spinning on the lock, whether executing or suspended, across the analysis interval.
	<b>WaitQ</b> The minimum, maximum, and average number of threads waiting on the lock, across the analysis interval.
	<b>Recursion</b> The minimum, maximum, and average recursion depth to which each thread held the lock.

### ***Mutex Pthread detail***

If the **-dt** or **-da** options are used, the **splat** command reports the following pthread details.

<b>Item</b>	<b>Descriptor</b>
<b>PThreadID</b>	The <b>PThread</b> identifier.
<b>Acquisitions</b>	The number of times that this pthread acquired the mutex.
<b>Miss Rate</b>	The percentage of acquisition attempts by the pthread that failed to secure the mutex.
<b>Spin Count</b>	The number of unsuccessful attempts by this pthread to secure the mutex.
<b>Wait Count</b>	The number of times that this pthread was forced to wait until the mutex came available.
<b>Busy Count</b>	The number of <b>trylock</b> calls that returned busy.
<b>Percent Held of Total Time</b>	This field contains the following sub-fields:
	<b>CPU</b> The percentage of the elapsed real time that this pthread executed while holding the mutex.
	<b>Elapse(d)</b> The percentage of the elapsed real time that this pthread held the mutex while running or suspended.
	<b>Spin</b> The percentage of elapsed real time that this pthread executed while spinning on the mutex.
	<b>Wait</b> The percentage of elapsed real time that this pthread spent waiting on the mutex.

### ***Mutex function detail***

If the **-df** or **-da** options are used, the **splat** command reports the function details.

The **splat** command reports the following function details:

---

<b>Item</b>	<b>Descriptor</b>
<b>PThreadID</b>	The <b>PThread</b> identifier.
<b>Acquisitions</b>	The number of times that this function acquired the mutex.
<b>Miss Rate</b>	The percentage of acquisition attempts by the function that failed to secure the mutex.
<b>Spin Count</b>	The number of unsuccessful attempts by this function to secure the mutex.

The **splat** command reports the following function details: *(continued)*

<b>Item</b>	<b>Descriptor</b>
<b>Wait Count</b>	The number of times that this function was forced to wait until the mutex came available.
<b>Busy Count</b>	The number of <b>trylock</b> calls that returned busy.
<b>Percent Held of Total Time</b>	This field contains the following sub-fields: <b>CPU</b> The percentage of the elapsed real time that this function executed while holding the mutex. <b>Elapse(d)</b> The percentage of the elapsed real time that this function held the mutex while running or suspended. <b>Spin</b> The percentage of elapsed real time that this function executed while spinning on the mutex. <b>Wait</b> The percentage of elapsed real time that this function spent waiting for the mutex.
<b>Return Address</b>	The return address to this calling function, in hexadecimal.
<b>Start Address</b>	The start address to this calling function, in hexadecimal.
<b>Offset</b>	The offset from the function start address to the return address, in hexadecimal.

### Read/Write lock reports

The **PThread** read/write lock is similar to an AIX complex lock in that it can be acquired for reading or writing.

Writing is exclusive in that a single thread can only acquire the lock for writing, and no other thread can hold the lock for reading or writing at that point. Reading is not exclusive, so more than one thread can hold the lock for reading. Reading is recursive in that a single thread can hold multiple read-acquisitions on the lock. Writing is not recursive.

```
[PThread RWLock] ADDRESS: 000000002FF228E0
Parent Thread: 0000000000000001 creation time: 5.236585 deletion time: 6.090511
Pid: 7362 Process Name: /home/testrwlock
Creation call-chain =====
0000000010000458 .main
00000000100001DC .__start
=====
Acqui- | Miss Spin Wait | Secs Held | Percent Held ( 26.235284s )
sitions | Rate Count Count | CPU Elapsed | CPU Elapsed Comb Real
1150 | 40.568 785 0 | 21.037942 12.0346 | 80.19 99.22 30.45 46.29
-----
Depth Readers Writers Total
LockQ Min Max Avg Min Max Avg Min Max Avg
SpinQ 0 2 0 0 1 0 0 0 2 0
WaitQ 0 768 601 0 15 11 0 782 612
WaitQ 0 769 166 0 15 3 0 783 169
-----
PthreadID Acquisitions Miss Spin Count Wait Count Busy Percent Held of Total Time
Write Read Rate Write Read Write Read Count CPU Elapse Spin Wait
-----
772 0 207 78.70 0 765 0 796 0 11.58 15.13 29.69 23.21
515 765 0 1.80 14 0 14 0 0 80.10 80.19 49.76 23.08
258 0 178 3.26 0 6 0 5 0 12.56 17.10 10.00 20.02
-----
Function Name Acquisitions Miss Spin Count Wait Count Busy Percent Held of Total Time
Start Address Write Read Rate Write Read Write Read Count CPU Elapse Spin Wait Return Address
-----
AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA
AAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAAA
```

In addition to the common header information and the **[PThread RWLock]** identifier, this report lists the following lock details:

<b>Item</b>	<b>Descriptor</b>
<b>Parent Thread</b>	Pthread id of the parent pthread.
<b>creation time</b>	Elapsed time in seconds after the first event recorded in trace (if available).
<b>deletion time</b>	Elapsed time in seconds after the first event recorded in trace (if available).
<b>PID</b>	Process identifier.
<b>Process Name</b>	Name of the process using the lock.
<b>Call-chain</b>	Stack of called methods (if available).
<b>Acquisitions</b>	The number of times that the lock was acquired in the analysis interval.
<b>Miss Rate</b>	The percentage of attempts that failed to acquire the lock.
<b>Spin Count</b>	The number of unsuccessful attempts to acquire the lock.
<b>Wait Count</b>	The current <b>PThread</b> implementation does not force pthreads to wait for read/write locks. This reports the number of times a thread, spinning on this lock, is undispatched.
<b>Seconds Held</b>	This field contains the following sub-fields: <b>CPU</b> The total number of processor seconds that the lock was held by an executing pthread. If the lock is held multiple times by the same pthread, only one hold interval is counted. <b>EIapse(d)</b> The total number of elapsed seconds that the lock was held by any pthread, whether the pthread was running or suspended.
<b>Percent Held</b>	This field contains the following sub-fields: <b>Real CPU</b> The percentage of the cumulative processor time that the lock was held by any executing pthread. <b>Real Elapsed</b> The percentage of the elapsed real time that the lock was held by any pthread, either running or suspended. <b>Comb(ined) Spin</b> The percentage of the cumulative processor time that running pthreads spent spinning while trying to acquire this lock. <b>Real Wait</b> The percentage of elapsed real time that any pthread was waiting to acquire this lock. If two or more threads are waiting simultaneously, this wait time will only be charged once. To learn how many pthreads were waiting simultaneously, look at the WaitQ Depth statistics.

**Item** **Descriptor****Depth**

This field contains the following sub-fields:

**LockQ**

The minimum, maximum, and average number of pthreads holding the lock, whether executing or suspended, across the analysis interval. This is broken down by read-acquisitions, write-acquisitions, and total acquisitions.

**SpinQ**

The minimum, maximum, and average number of pthreads spinning on the lock, whether executing or suspended, across the analysis interval. This is broken down by read-acquisitions, write-acquisitions, and total acquisitions.

**WaitQ**

The minimum, maximum, and average number of pthreads in a timed-wait state for the lock, across the analysis interval. This is broken down by read-acquisitions, write-acquisitions, and total acquisitions.

**Note:** The pthread and function details for read/write locks are similar to the mutex detail reports, except that they break down the acquisition, spin, and wait counts by whether the lock is to be acquired for reading or writing.

**Condition-Variable report**

The **PThread** condition-variable is a synchronizer, but not a lock. A **PThread** is suspended until a signal indicates that the condition now holds.

```
[PThread CondVar] ADDRESS: 0000000020000A18
Parent Thread: 0000000000000001 creation time: 0.216301
Pid: 7360 Process Name: /home/splat/test/condition
Creation call-chain =====
00000000D26A0EE8 .pthread_cond_timedwait
0000000010000510 .main
00000000100001DC .__start
=====
          | | | | | Spin / Wait Time ( 26.235284s )
          | | | | | Comb   Comb
Passes   | | | | | Spin  Wait
1        | | | | | 26.02  0.00
-----|-----
Depth    Min  Max  Avg
SpinQ    0   1   1
WaitQ    0   0   0
          | | | | |
PThreadID Passes  Fail Rate  Spin Count  Wait Count  % Total Time
          | | | | | Spin  Wait
          | | | | | 99.1755 0.0000

Function Name  Passes  Rate  Fail Count  Spin Count  Wait Spin  % Total Time
Address  Offset  Rate  Count      Count      Spin      Wait  Return Address  Start
^^^^^^^^^^^^  ^^^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^  ^^^^^^^^^^^^^
          | | | | | 50.0000  1    0    99.1755 0.0000 00000000100001DC
0000000010000000 000001DC
```

In addition to the common header information and the **[PThread CondVar]** identifier, this report lists the following details:

**Item** **Descriptor**

**Passes** The number of times that the condition was signaled to hold during the analysis interval.

**Fail Rate** The percentage of times that the condition was tested and was not found to be true.

<b>Item</b>	<b>Descriptor</b>
<b>Spin Count</b>	The number of times that the condition was tested and was not found to be true.
<b>Wait Count</b>	The number of times that a pthread was forced into a suspended wait state waiting for the condition to be signaled.
<b>Spin / Wait Time</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Comb Spin</b> The total number of processor seconds that pthreads spun while waiting for the condition.</li> <li><b>Comb Wait</b> The total number of elapsed seconds that pthreads spent in a wait state for the condition.</li> </ul>
<b>Depth</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>SpinQ</b> The minimum, maximum, and average number of pthreads spinning while waiting for the condition, across the analysis interval.</li> <li><b>WaitQ</b> The minimum, maximum, and average number of pthreads waiting for the condition, across the analysis interval.</li> </ul>

### ***Condition-Variable Pthread detail***

If the **-dt** or **-da** options are used, the **splat** command reports the following pthread details.

The pthread details that the **splat** command reports are:

<b>Item</b>	<b>Descriptor</b>
<b>PThreadID</b>	The <b>PThread</b> identifier.
<b>Passes</b>	The number of times that this pthread was notified that the condition passed.
<b>Fail Rate</b>	The percentage of times that the pthread checked the condition and did not find it to be true.
<b>Spin Count</b>	The number of times that the pthread checked the condition and did not find it to be true.
<b>Wait Count</b>	The number of times that this pthread was forced to wait until the condition became true.
<b>Percent Total Time</b>	This field contains the following sub-fields: <ul style="list-style-type: none"> <li><b>Spin</b> The percentage of elapsed real time that this pthread spun while testing the condition.</li> <li><b>Wait</b> The percentage of elapsed real time that this pthread spent waiting for the condition to hold.</li> </ul>

### ***Condition-Variable function detail***

If the **-df** or **-da** options are used, the **splat** command reports the following function details.

<b>Item</b>	<b>Descriptor</b>
<b>Function Name</b>	The name of the function that passed or attempted to pass this condition.
<b>Passes</b>	The number of times that this function was notified that the condition passed.

<b>Item</b>	<b>Descriptor</b>
<b>Fail Rate</b>	The percentage of times that the function checked the condition and did not find it to be true.
<b>Spin Count</b>	The number of times that the function checked the condition and did not find it to be true.
<b>Wait Count</b>	The number of times that this function was forced to wait until the condition became true.
<b>Percent Total Time</b>	This field contains the following sub-fields: <b>Spin</b> The percentage of elapsed real time that this function spun while testing the condition. <b>Wait</b> The percentage of elapsed real time that this function spent waiting for the condition to hold.
<b>Return Address</b>	The return address to this calling function, in hexadecimal.
<b>Start Address</b>	The start address to this calling function, in hexadecimal.
<b>Offset</b>	The offset from the function start address to the return address, in hexadecimal.

## Hardware performance monitor APIs and tools

---

The **bos.pmapi** fileset contains libraries and tools that are designed to provide access to some of the counting facilities of the Performance Monitor feature included in select IBM microprocessors.

They include the following:

- The **pmapi** library, which contains a set of low-level application programming interfaces, APIs, includes the following:
  - A set of system-level APIs to permit counting of the activity of a whole machine or of a set of processes with a common ancestor.
  - A set of first party kernel-thread-level APIs to permit threads to count their own activity.
  - A set of third party kernel-thread-level APIs to permit a debug program to count the activity of target threads.
- The **pmcycles** command, which returns the processor clock and decremter speeds.
- The **pmlist** command, which displays information about processors, events, event groups and sets, and derived metrics supported.
- The **hpm** and **hpm\_r** libraries, which contain a set of high-level APIs that enable the following:
  - Nested instrumentation of sections of code
  - Automatic calculation of derived metrics, and gathering of operating system resource-consumption metrics in addition to the raw hardware counter values
- The **hpmstat** command, which collects the hardware performance monitor raw and derived metrics concerning total system activity of a machine.
- The **hpmcount** command, which executes applications and provides the applications' execution wall clock time, the raw and derived hardware performance monitor metrics and the operating system resource-utilization statistics.

**Note:** The APIs and the events available on each of the supported processors have been completely separated by design. The events available, their descriptions, and their current testing status (which are different on each processor) are in separately installable tables, and are not described here because none of the API calls depend on the availability or status of any of the events.

The status of an event, as returned by the **pm\_initialize** API initialization routine, can be *verified*, *unverified*, *caveat*, *broken*, *group-only*, *thresholdable*, or *shared* (see [“Performance monitor accuracy”](#) on page 57 about testing status and event accuracy).

An event filter (which is any combination of the status bits) must be passed to the **pm\_initialize** routine to force the return of events with status matching the filter. If no filter is passed to the **pm\_initialize** routine, no events will be returned.

## Performance monitor accuracy

Only events marked *verified* have gone through full verification. Events marked *caveat* have been verified within the limitations documented in the event description returned by the **pm\_initialize** routine.

Events marked *unverified* have undefined accuracy. Use caution with *unverified* events. The Performance Monitor API is essentially providing a service to read hardware registers that might not have any meaningful content.

Users can experiment with *unverified* event counters and determine for themselves if they can be used for specific tuning situations.

## Performance monitor context and state

To provide Performance Monitor data access at various levels, the AIX operating system supports optional performance monitoring contexts.

These contexts are an extension to the regular processor and thread contexts and include one 64-bit counter per hardware counter and a set of control words. The control words define which events are counted and when counting is on or off.

### System-level context and accumulation

For the system-level APIs, optional Performance Monitor contexts can be associated with each of the processors.

### Thread context

Optional Performance Monitor contexts can also be associated with each thread. The AIX operating system and the Performance Monitor kernel extension automatically maintain sets of 64-bit counters for each of these contexts.

### Thread counting-group and process context

The concept of thread counting-group is optionally supported by the thread-level APIs. All the threads within a group, in addition to their own performance monitor context, share a group accumulation context.

A thread group is defined as all the threads created by a common ancestor thread. By definition, all the threads in a thread group count the same set of events, and, with one exception described below, the group must be created before any of the descendant threads are created. This restriction is due to the fact that, after descendant threads are created, it is impossible to determine a list of threads with a common ancestor.

One special case of a group is the collection of all the threads belonging to a process. Such a group can be created at any time regardless of when the descendant threads are created, because a list of threads belonging to a process can be generated. Multiple groups can coexist within a process, but each thread can be a member of only one Performance Monitor counting-group. Because all the threads within a group must be counting the same events, a process group creation will fail if any thread within the process already has a context.

## Performance monitor state inheritance

The performance monitor is defined as the combination of the Performance Monitor programming (the events being counted), the counting state (on or off), and the optional thread group membership.

A counting state is associated with each group. When the group is created, its counting state is inherited from the initial thread in the group. For thread members of a group, the effective counting state is the result of AND-ing their own counting state with the group counting state. This provides a way to effectively control the counting state for all threads in a group. Simply manipulating the group-counting state will affect the effective counting state of all the threads in the group. Threads inherit their complete Performance Monitor state from their parents when the thread is created. A thread Performance Monitor context data (the value of the 64-bit counters) is not inherited, that is, newly created threads start with counters set to zero.

## Performance monitoring agent

The performance monitoring agent (**perfagent.server** fileset) is a collection of programs that make it possible for a host to act as a provider of performance statistics across a network or locally. The key program is the daemon **xmtopas**.

The following are the main components of the performance monitoring agent:

### **xmtopas**

The data-supplier daemon, which permits a system where this daemon runs to supply performance statistics to data-consumer programs on the local or remote hosts. This daemon also provides the interface to SNMP.

**Note:** The interface to SNMP is available only on System p Agents.

### **xmtrend**

A long-term recording daemon. This daemon also provides large metric set trend recordings for post-processing by **jazizo** and **jtopas**.

### **xmscheck**

A program that lets you pre-check the **xmservd** recording configuration file. This program is useful when you want to start and stop **xmservd** recording at predetermined times.

### **filtd**

A daemon that can be used to do data reduction of existing statistics and to define alarm conditions and triggering of alarms.

### **xmpeek**

A program that allows you to display the status of **xmservd** on the local or a remote host and to list all available statistics from the daemon.

### **iphosts**

A program to initiate monitoring of Internet Protocol performance by specifying which hosts to monitor. The program accepts a list of hosts from the command line or from a file.

### **armtoleg**

A program that can convert a pre-existing Application Response Management (ARM) library into an ARM library that can be accessed concurrently with the ARM library shipped with PTX. This program is only required and available on operating systems.

### **SpmiArmd**

A daemon that collects Application Response Management (ARM) data and interfaces to the Spmi library code to allow monitoring of ARM metrics from any PTX manager program.

### **SpmiResp**

A daemon that polls for IP response times for selected hosts and interfaces to the Spmi library code to allow monitoring of IP response time metrics from any PTX manager program.

### **Application Response Management API and Libraries**

A header file and two libraries support the PTX implementation of ARM. The implementation allows for coexistence and simultaneous use of the PTX ARM library and one previously installed ARM library.

## System Performance Measurement Interface API and Library

Header files and a library to allow you to develop your own data-supplier and local data-consumer programs.

### Sample Programs

Sample dynamic data-supplier and data-consumer programs that illustrate the use of the API.

### Remote System Performance Measurement Interface API

This API is available for those who want to develop programs that access the statistics available from one or more **xmtopas** daemons.

## POWERCOMPAT events

The POWERCOMPAT events provide a list of hardware events that are available for processor compatibility modes and are used as a subset of the actual processor events.

You can use the processor compatibility modes to move logical partitions between systems that have different processor types without upgrading the operating system environments in the logical partition. The processor compatibility mode allows the destination system to provide the logical partition with a subset of processor capabilities that are supported by the operating systems environment in the logical partition.

The following hardware events are supported in the POWERCOMPAT compatibility mode for different versions of the AIX operating system.

Counter	Event name	Supported AIX version
1	PM_1PLUS_PPC_CMPL	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_CYC	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_DATA_FROM_L1.5	<ul style="list-style-type: none"><li>• AIX 6 with 6100-07, or earlier</li><li>• AIX 7 with 7100-01, or earlier</li></ul>
1	PM_FLOP	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_GCT_NOSLOT_CYC	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_IERAT_MISS	<ul style="list-style-type: none"><li>• AIX 6.1 with 6100-04, or later</li><li>• AIX 7.1, or later</li></ul>
1	PM_INST_CMPL	<ul style="list-style-type: none"><li>• AIX 6 with 6100-07, or earlier</li><li>• AIX 7 with 7100-01, or earlier</li></ul>
1	PM_INST_IMC_MATCH_CMPL	<ul style="list-style-type: none"><li>• AIX 6 with 6100-07, or earlier</li><li>• AIX 7 with 7100-01, or earlier</li></ul>
1	PM_LSU_DERAT_MISS_CYC	<ul style="list-style-type: none"><li>• AIX 6 with 6100-07, or earlier</li><li>• AIX 7 with 7100-01, or earlier</li></ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
1	PM_PMC4_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
1	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
1	PM_ANY_THRD_RUN_CYC	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
1	PM_MRK_INST_DISP	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_MRK_BR_TAKEN_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_MRK_L1_ICACHE_MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_THRESH_EXC_4096	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_THRESH_EXC_256	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_MRK_L1_RELOAD_VALID	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
1	PM_THRESH_MET	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_DATA_FROM_L2MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_EXT_INT	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_INST_DISP	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_L1_ICACHE_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
2	PM_LSU_DERAT_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_PMC1_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_RUN_CYC	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_ST_FIN	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
2	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
2	PM_MRK_DATA_FROM_MEM	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_MRK_LD_MISS_L1	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_MRK_DATA_FROM_L3MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_THRESH_EXC_32	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
2	PM_THRESH_EXC_512	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_DATA_FROM_L3MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_DTLB_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_INST_DISP	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_L1_DCACHE_RELOAD_VALID	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
3	PM_PMC2_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_ST_MISS_L1	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
3	PM_TB_BIT_TRANS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_THRD_CONC_RUN_INST	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
3	PM_BR_TAKEN_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_MRK_ST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_MRK_BR_MPRED_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_MRK_DERAT_MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_THRESH_EXC_64	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
3	PM_THRESH_EXC_1024	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_1PLUS_PPC_DISP	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_BR_MPRED_CMPL	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_CYC	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_FLUSH	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>

Table 1. POWERCOMPAT events (continued)

Counter	Event name	Supported AIX version
4	PM_ITLB_MISS	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_LD_MISS_L1	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_PMC3_OVERFLOW	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_RUN_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_RUN_PURR	<ul style="list-style-type: none"> <li>• AIX 6.1 with 6100-04, or later</li> <li>• AIX 7.1, or later</li> </ul>
4	PM_SUSPENDED	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-07, or earlier</li> <li>• AIX 7 with 7100-01, or earlier</li> </ul>
4	PM_MRK_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_MRK_DTLB_MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_MRK_INST_FROM_L3MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_MRK_DATA_FROM_L2MISS	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_THRESH_EXC_128	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_THRESH_EXC_2048	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
4	PM_DATA_FROM_MEM	<ul style="list-style-type: none"> <li>• AIX 6 with 6100-08, or later</li> <li>• AIX 7 with 7100-02, or later</li> </ul>
5	PM_RUN_INST_CMPL	<ul style="list-style-type: none"> <li>• AIX 6.1, or later</li> <li>• AIX 7.1, or later</li> </ul>
6	PM_RUN_CYC	<ul style="list-style-type: none"> <li>• AIX 6.1, or later</li> <li>• AIX 7.1, or later</li> </ul>

## Thread accumulation and thread group accumulation

When a thread gets suspended (or redispached), its 64-bit accumulation counters are updated. If the thread is member of a group, the group accumulation counters are updated at the same time.

Similarly, when a thread stops counting or reads its Performance Monitor data, its 64 bit accumulation counters are also updated by adding the current value of the Performance Monitor hardware counters to them. Again, if the thread is a member of a group, the group accumulation counters are also updated, regardless of whether the counter read or stop was for the thread or for the thread group.

The group-level accumulation data is kept consistent with the individual Performance Monitor data for the thread members of the group, whenever possible. When a thread voluntarily leaves a group, that is, deletes its Performance Monitor context, its accumulated data is automatically subtracted from the group-level accumulated data. Similarly, when a thread member in a group resets its own data, the data in question is subtracted from the group level accumulated data. When a thread dies, no action is taken on the group-accumulated data.

The only situation where the group-level accumulation is not consistent with the sum of the data for each of its members is when the group-level accumulated data has been reset, and the group has more than one member. This situation is detected and marked by a bit returned when the group data is read.

## Access controls to use PMU

The access control to the PMU is managed through `pmuaccess` parameter and RBAC privileges.

- System wide access control will be managed through a `pmuaccess` parameter in `sys0`
- Access at process level will be controlled through RBAC privileges.

### System wide control

Valid values for `pmuaccess` are listed in the following table:

<b>pmuaccess values</b>	<b>Description</b>
none	In this mode, access to PMU is completely disabled, even root user will not be able to use PMU.
priv	In this mode, access to PMU is available only to the privileged RBAC user.
all	In this mode, any user can access the PMU. This will be the default value set.

A system administrator can disable or provide privileged access to the PMU by running `chdev` command on the `sys0` device.

The following example shows how to use the `chdev` command to modify the PMU access.

1. To get the current PMU access

```
lsattr -E -l sys0 -a pmuaccess
```

```
pmuaccess priv controls the PMU mode of operations True
```

2. To modify the PMU access

```
chdev -l sys0 -a pmuaccess = [none|priv|all]
```

### RBAC Privileges

`libpmapi` APIs can perform privileged operations, Only privileged users can run privileged operations when `sys0 pmuaccess` attribute is set to `priv`.

The following provides information on the privileges required to use `libpmapi` calls.

Table 3. Privileges required to use libpmapi calls

PMU Privileges	APIs
PV_PMU_SYSTEM	PV_PMU_SYSTEM pm_cycles_measured pm_start_* pm_tstart* pm_get_data_* pm_get_tdata* pm_get_Tdata*
PV_PMU_THREAD	pm_start_mythread_* pm_start_thread_* pm_start_group_* pm_tstart_mythread_* pm_tstart_group_* pm_tstart_thread_* pm_get_Tdata_* pm_get_data_* pm_get_tdata_* pm_get_program_* pm_get_data_generic pm_set_counter_frequency_*
PV_PMU_USERMODE	pm_set_ebb_handler pm_clear_ebb_handler

## Security considerations

The system-level APIs calls are only available from the root user except when the process tree option is used. In that case, a locking mechanism prevents calls being made from more than one process. This mechanism ensures ownership of the API and exclusive access by one process from the time that the system-level contexts are created until they are deleted.

Enabling the process tree option results in counting for only the calling process and its descendants; the default is to count all activities on each processor.

Because the system-level APIs would report bogus data if thread contexts were in use, system-level API calls are not enabled at the same time as thread-level API calls. The allocation of the first thread context will take the system-level API lock, which will not be released until the last context has been deallocated.

When using first party calls, a thread is only permitted to modify its own Performance Monitor context. The only exception to this rule is when making group level calls, which obviously affect the group context, but can also affect other threads' context. Deleting a group deletes all the contexts associated with the group, that is, the caller context, the group context, and all the contexts belonging to all the threads in the group.

Access to a Performance Monitor context not belonging to the calling thread or its group is available only from the target process's debugger program. The third party API calls are only permitted when the

target process is either being **ptraced** by the API caller, that is, the caller is already attached to the target process, and the target process is stopped or the target process is stopped on a **/proc** file system event and the caller has the privilege required to open its control file.

The fact that the debugger program must already have been attached to the debugged thread before any third party call to the API can be made, ensures that the security level of the API will be the same as the one used between debugger programs and process being debugged.

## The pmapi library

Review the rules that are for the pmapi library.

The following rules are common to the Performance Monitor APIs:

- – The **pm\_initialize** routine must be called before any API call is made, and only events returned by a given **pm\_initialize** call with its associated filter setting can be used in subsequent **pm\_set\_program** calls.
- PM contexts cannot be reprogrammed or reused at any time. This means that none of the APIs support more than one call to a **pm\_set\_program** interface without a call to a **pm\_delete\_program** interface. This also means that when creating a process group, none of the threads in the process is permitted to already have a context.
- All the API calls return 0 when successful or a positive error code (which can be decoded using **pm\_error**) otherwise.

## Access controls to use PMU

The access control to the PMU is managed through pmuaccess parameter and RBAC privileges.

- System wide access control will be managed through a pmuaccess parameter in sys0
- Access at process level will be controlled through RBAC privileges.

### System wide control

Valid values for pmuaccess are listed in the following table:

<i>Table 4. Valid pmuaccess values</i>	
<b>pmuaccess values</b>	<b>Description</b>
none	In this mode, access to PMU is completely disabled, even root user will not be able to use PMU.
priv	In this mode, access to PMU is available only to the privileged RBAC user.
all	In this mode, any user can access the PMU. This will be the default value set.

A system administrator can disable or provide privileged access to the PMU by running chdev command on the sys0 device.

The following example shows how to use the chdev command to modify the PMU access.

1. To get the current PMU access

```
lsattr -E -l sys0 -a pmuaccess
```

```
pmuaccess priv controls the PMU mode of operations True
```

2. To modify the PMU access

```
chdev -l sys0 -a pmuaccess = [none|priv|all]
```

### RBAC Privileges

libpmapi APIs can perform privileged operations, Only privileged users can run privileged operations when sys0 pmuaccess attribute is set to priv.

The following provides information on the privileges required to use libpmapi calls.

<i>Table 5. Privileges required to use libpmapi calls</i>	
<b>PMU Privileges</b>	<b>APIs</b>
PV_PMU_SYSTEM	PV_PMU_SYSTEM pm_cycles_measured pm_start_* pm_tstart* pm_get_data_* pm_get_tdata* pm_get_Tdata*
PV_PMU_THREAD	pm_start_mythread_* pm_start_thread_* pm_start_group_* pm_tstart_mythread_* pm_tstart_group_* pm_tstart_thread_* pm_get_Tdata_* pm_get_data_* pm_get_tdata_* pm_get_program_* pm_get_data_generic pm_set_counter_frequency_*
PV_PMU_USERMODE	pm_set_ebb_handler pm_clear_ebb_handler

## The pm\_init API initialization routine

The **pm\_init** routine returns (in a structure of type **pm\_info\_t** pointed to by its second parameter) the processor name, the number of counters available, the list of available events for each counter, and the threshold multipliers supported.

Some processor support two threshold multipliers, others none, meaning that thresholding is not supported at all. You can not use the **pm\_init** routine with processors newer than POWER4. You must use the **pm\_initialize** routine for newer processors.

For each event returned, in addition to the testing status, the **pm\_init** routine also returns the identifier to be used in subsequent API calls, a short name, and a long name. The short name is a mnemonic name in the form PM\_MNEMONIC. Events that are the same on different processors will have the same mnemonic name. For instance, PM\_CYC and PM\_INST\_CMPL are respectively the number of processor cycles and instruction completed and should exist on all processors. For each event returned, a thresholdable flag is also returned. This flag indicates whether an event can be used with a threshold. If so, then specifying a

threshold defers counting until a number of cycles equal to the threshold multiplied by the processor's selected threshold multiplier has been exceeded.

The Performance Monitoring API enables the specification of event groups instead of individual events. Event groups are predefined sets of events. Rather than each event being individually specified, a single group ID is specified. The interface to the **pm\_init** routine has been enhanced to return the list of supported event groups in a structure of type **pm\_groups\_info\_t** pointed to by a new optional third parameter. To preserve binary compatibility, the third parameter must be explicitly announced by OR-ing the **PM\_GET\_GROUPS** bitflag into the filter. Some events on some platforms can only be used from within a group. This is indicated in the threshold flag associated with each event returned. The following convention is used:

Item	Descriptor
<b>y</b>	A thresholdable event
<b>g</b>	An event that can only be used in a group
<b>G</b>	A thresholdable event that can only be used in a group
<b>n</b>	A non-thresholdable event that is usable individually

On some platforms, use of event groups is required because all the events are marked **g** or **G**. Each of the event groups that are returned includes a short name, a long name, and a description similar to those associated with events, as well as a group identifier to be used in subsequent API calls and the events contained in the group (in the form of an array of event identifiers).

The testing status of a group is defined as the lowest common denominator among the testing status of the events that it includes. If at least one event has a testing status of *caveat*, the group testing status is at best *caveat*, and if at least one event has a status of *unverified*, then the group status is *unverified*. This is not returned as a group characteristic, but it is taken into account by the filter. Like events, only groups with status matching the filter are returned.

## The **pm\_initialize** API initialize routine

The **pm\_initialize** routine returns the processor name in a structure of type **pm\_info2\_t** defined by its second parameter, its characteristics, the number of counters available, and the list of available events for each counter.

For each event a status is returned, indicating the event status: *validated*, *unvalidated*, or *validated with caveat*. The status also indicates if the event can be used in a group or not, if it is a thresholdable event and if it is a shared event.

Some events on some platforms can be used only within a group. In the case where an event group is specified instead of individual events, the events are defined as *grouped only* events.

For each returned event, a thresholdable state is also returned. It indicates whether an event can be used with a threshold. If so, specifying a threshold defers counting until it exceeds a number of cycles equal to the threshold multiplied by the selected processor threshold multiplier.

Some processors support two hardware threads per physical processing unit. Each thread implements a set of counters, but some events defined for those processors are shared events. A shared event, is controlled by a signal not specific to a particular thread's activity and sent simultaneously to both sets of hardware counters, one for each thread. Those events are marked by the *shared* status.

For each returned event, in addition to the testing status, the **pm\_initialize** routine returns the identifier to be used in subsequent API calls, as a short name and a long name. The short name is a mnemonic name in the form **PM\_MNEMONIC**. The same events on different processors will have the same mnemonic name. For instance, **PM\_CYC** and **PM\_INST\_CMPL** are respectively the number of processor cycles and the number of completed instructions, and should exist on all processors.

The Performance Monitoring API enables the specification of event groups instead of individual events. Event groups are predefined sets of events. Rather than to specify individually each event, a single group

ID can be specified. The interface to the **pm\_initialize** routine returns the list of supported event groups in a structure of type **pm\_groups\_info\_t** whose address is returned in the third parameter.

On some platforms, the use of event groups is required because all events are marked as group-only. Each event group that is returned includes a short name, a long name, and a description similar to those associated with events, as well as a group identifier to be used in subsequent API calls and the events contained in the group (in the form of an array of event identifiers).

The testing status of a group is defined as the lowest common denominator among the testing status of the events that it includes. If the testing status of at least one event is *caveat*, then the group testing status is at best *caveat*, and if the status of at least one event is *unverified*, then the group status is *unverified*. This is not returned as a group characteristic, but it is taken into account by the filter. Like events, only groups whose status match the filter are returned.

If the **proctype** parameter is not set to **PM\_CURRENT**, the Performance Monitor APIs library is not initialized and the subroutine only returns information about the specified processor in its parameters, **pm\_info2\_t** and **pm\_groups\_info\_t**, taking into account the filter. If the **proctype** parameter is set to **PM\_CURRENT**, in addition to returning the information described, the Performance Monitor APIs library is initialized and ready to accept other calls.

## Basic pmapi library calls

Each of the following sections describes a system-wide API call that has variations for first- and third-party kernel thread or group counting. Variations are indicated by suffixes to the function call names, such as **pm\_set\_program**, **pm\_set\_program\_mythread**, and **pm\_set\_program\_group**.

### **pm\_set\_program**

Sets the counting configuration. Use this call to specify the events (as a list of event identifiers, one per counter, or as a single event-group identifier) to be counted, and a mode in which to count. The list of events to choose from is returned by the **pm\_init** routine. If the list includes a thresholdable event, you can also use this call to specify a threshold, and a threshold multiplier.

The mode in which to count can include user-mode and kernel-mode counting, and whether to start counting immediately. For the system-wide API call, the mode also includes whether to turn counting on only for a process and its descendants or for the whole system. For counting group API calls, the mode includes the type of counting group to create, that is, a group containing the initial thread and its future descendants, or a process-level group, which includes all the threads in a process.

By default, the time spent during interrupts handling is counted. It is possible to override this default behavior by modifying the counting mode.

### **pm\_get\_program**

Retrieves the current Performance Monitor settings. This includes mode information and the list of events (or the event group) being counted. If the list includes a thresholdable event, this call also returns a threshold and the multiplier used.

### **pm\_delete\_program**

Deletes the Performance Monitor configuration. Use this call to undo **pm\_set\_program**.

### **pm\_start, pm\_tstart**

Starts Performance Monitor counting. **pm\_tstart** returns a timestamp associated with the time the Performance Monitoring counters started counting. This is a timebase value that can be converted to time using **time\_base\_to\_time**.

### **pm\_stop, pm\_tstop**

Stops Performance Monitor counting. **pm\_tstop** returns a timestamp associated with the time the Performance Monitoring counters stopped counting. This is a timebase value that can be converted to time using **time\_base\_to\_time**.

### **pm\_get\_data, pm\_get\_tdata, pm\_get\_Tdata**

Returns Performance Monitor counting data. The data is a set of 64-bit values, one per hardware counter. For the counting group API calls, the group information is also returned. (See [“Thread counting-group information”](#) on page 70.)

**pm\_get\_tdata** is similar to **pm\_get\_data**, but includes a timestamp that indicates the last time that the hardware Performance Monitoring counters were read. This is a timebase value that can be converted to time by using **time\_base\_to\_time**.

**pm\_get\_Tdata** is also similar to **pm\_get\_data** but includes accumulated times corresponding to the interval during which the hardware Performance Monitoring counters were active. The interval is measured in real time, PURR and SPURR (on processors supporting those) values, and returned in timebase units convertible to time using **time\_base\_to\_time**.

The **pm\_get\_data\_cpu**, **pm\_get\_tdata\_cpu** and **pm\_get\_Tdata\_cpu** interfaces return the Performance Monitor counting data for a single processor. The specified processor number represents a contiguous number going from 0 to **\_system\_configuration.ncpus**. This number can represent a different processor from call to call if dynamic reconfiguration operations have occurred.

The **pm\_get\_data\_lcpu**, **pm\_get\_tdata\_lcpu** and **pm\_get\_Tdata\_lcpu** interfaces return the Performance Monitor counting data for a single logical processor. The logical processor numbering is not contiguous, and the call to these interfaces returns an error if the specified logical processor has not been on line since the last call to **pm\_set\_program**. A logical processor number always designates the same processor even if dynamic reconfiguration operations have occurred. To get data for all processors, these interfaces must be called in a loop from 0 to **\_system\_configuration.max\_ncpus**.

#### **pm\_reset\_data**

Resets Performance Monitor counting data. All values are set to 0.

## **Thread counting-group information**

This the following information is returned by the **pm\_get\_data\_mygroup** and **pm\_get\_data\_pgroup** interfaces in a **pm\_groupinfo\_t** structure.

The following information is associated with each thread counting-group:

#### **member count**

The number of threads that are members of the group. This includes deceased threads that were members of the group when running.

If the consistency flag is on, the count will be the number of threads that have contributed to the group-level data.

#### **process flag**

Indicates that the group includes all the threads in the process.

#### **consistency flag**

Indicates that the group PM data is consistent with the sum of the individual PM data for the thread members.

## **Counter multiplexing mode**

You can set the counting for more events than available hardware counters using counter multiplexing. This mode is meant to be used to analyze workloads with homogenous performance characteristics. This avoids the requirement to run the workload multiple times to collect more events than available hardware counters.

In this mode, the pmapi periodically changes the setting of the counting and accumulates values and counting time for multiple sets of events. The time each event set is counted before switching to the next set can be in the range of 10 ms to 30 s. The default value is 100 ms.

The values returned include the number of times all sets of events have been counted, and for each set, the accumulated counter values and the accumulated time the set was counted. The accumulated time is measured up to three different ways: using Time Base, and when available, using the PURR time and one the SPURR time. These times are stored in a timebase format that can be converted to time by using the **time\_base\_to\_time** function. These times are meant to be used to normalize the results across the complete measurement interval.

Several basic pmapi calls have the following multiplexing mode variations indicated by the **\_mx** suffix:

#### **pm\_set\_program\_mx**

Sets the counting configuration. It differs from the **pm\_set\_program** function in that it accepts a set of groups (or event lists) to be counted, and the time each set must be counted before switching to the next set.

#### **pm\_get\_program\_mx**

Retrieves the current Performance Monitor settings. It differs from the **pm\_get\_program** function in that it returns a set of groups (or event lists).

#### **pm\_get\_data\_mx**

Returns the Performance Monitor counting data. It returns a set of counting data, one per group (or event list) configured. The returned data includes in addition to the accumulated counter values, the number of times all the configured sets have been counted, and for each set, the accumulated time it was counted.

#### **pm\_get\_tdata\_mx**

Same as **pm\_get\_data\_mx**, but includes a timestamp indicating the last time that the hardware Performance Monitor counters were read.

#### **pm\_get\_data\_cpu\_mx/pm\_get\_tdata\_cpu\_mx**

Same as **pm\_get\_data\_mx** or **pm\_get\_tdata\_mx**, but returns the Performance Monitor counting data for a single processor. The specified processor number must be in the range 0 to **\_system\_configuration.ncpus**. This number might represent different processors from call to call if dynamic reconfiguration operations have occurred.

#### **pm\_get\_data\_lcpu\_mx/pm\_get\_tdata\_lcpu\_mx**

Same as **pm\_get\_data\_cpu\_mx** or **pm\_get\_tdata\_cpu\_mx**, but returns the Performance Monitor counting data for a single logical processor. The logical processor numbering is not contiguous, and the call to these interfaces return an error if the specified logical processor has not been online since the last call to **pm\_set\_program\_mx**. A logical processor number always designates the same processor even if dynamic reconfiguration operations have occurred. To get data for all processors, these interfaces must be called in a loop from 0 to **\_system\_configuration.max\_ncpus**.

## **Counter multi-mode**

Counter multi-mode is similar to multiplexing mode. The counting mode in multiplexing mode is common to all the event sets.

The multi-mode allows you to associate a counting mode with each event set, but as the counting mode differs for an event set to another one, the results of the counting cannot be normalized on the complete measurement interval.

Several basic pmapi calls have the following multi-mode variations indicated by the **\_mm** suffix:

#### **pm\_set\_program\_mm**

Sets the counting configuration. It differs from the **pm\_set\_program\_mx** function in that it accepts a set of groups and associated counting mode to be counted.

#### **pm\_get\_program\_mm**

Retrieves the current Performance Monitor settings. It differs from the **pm\_get\_program\_mx** function in that it accepts a set of groups and associated counting mode.

## **WPAR counting**

It is possible to monitor the system-wide activity of a specific WPAR from the Global WPAR. In this case, only the activity of the processes running in this WPAR will be monitored.

Several basic pmapi calls have the following per-WPAR variations indicated by the **\_wp** suffix:

#### **pm\_set\_program\_wp, pm\_set\_program\_wp\_mm**

Same as the **pm\_set\_program** subroutine or the **pm\_set\_program\_mm** subroutine, except that the programming is set for the specified WPAR only (identified by its WPAR Configured ID). Notice that there is no **pm\_set\_program\_wp\_mx** subroutine.

### **pm\_get\_program, pm\_get\_program\_wp**

Same as the **pm\_get\_program** subroutine or the **pm\_get\_program\_wp** subroutine, except that it retrieves the programming for the specified WPAR only (identified by its WPAR Configured ID). Notice that there is no **pm\_get\_program\_wp\_mx** subroutine.

### **pm\_start\_wp, pm\_tstart, pm\_start\_wp, pm\_tstart\_wp**

Same as the **pm\_start** subroutine or the **pm\_tstart** subroutine, except that it targets a specific WPAR (identified by its WPAR Configured ID).

### **pm\_stop\_wp, pm\_tstop, pm\_stop\_wp, pm\_tstop\_wp**

Same as the **pm\_stop** subroutine or the **pm\_tstop** subroutine, except that it targets a specific WPAR (identified by its WPAR Configured ID).

### **pm\_get\_data\_wp, pm\_get\_tdata\_wp, pm\_get\_Tdata**

Same as the **pm\_get\_data** subroutine or the **pm\_get\_tdata** subroutine or the **pm\_get\_Tdata** subroutine, except that it retrieves Performance Monitor counting data for the specified WPAR only (identified by its handle, see the **pm\_get\_wplist** subroutines).

### **pm\_reset\_data**

Same as the **pm\_get\_data** routine or the **pm\_get\_tdatas** subroutine or the **pm\_get\_Tdata** subroutine, except that it retrieves Performance Monitor counting data for the specified WPAR only (identified by its handle, see the **pm\_get\_wplist** subroutines).

### **pm\_get\_wplist**

Retrieves the list of WPARs contexts that were active during the last system-wide counting. A WPAR context includes the WPAR Configured ID, the WPAR name, and a WPAR handle that uniquely identifies the WPAR. The WPAR handle can then be used to retrieve the Performance Monitor counting data for a specified WPAR using one of the **pm\_get\_data\_wp** subroutines.

## **Examples of pmapi library usage**

The following examples demonstrate the use of Performance Monitor APIs in pseudo-code. Functional sample code is available in the `/usr/samples/pmapi` directory.

### ***Simple single-threaded program example***

The following example displays a single-threaded program.

```
# include <pmapi.h>
main()
{
    pm_info_t pminfo;
    pm_prog_t prog;
    pm_data_t data;
    int filter = PM_VERIFIED; /* use only verified events */

    pm_init(filter, &pminfo)

    prog.mode.w      = 0; /* start with clean mode */
    prog.mode.b.user = 1; /* count only user mode */

    for (i = 0; i < pminfo.maxpmcs; i++)
        prog.events[i] = COUNT_NOTHING;

    prog.events[0] = 1; /* count event 1 in first counter */
    prog.events[1] = 2; /* count event 2 in second counter */

    pm_set_program_mythread(&prog);
    pm_start_mythread();

(1)    ... usefull work ...

    pm_stop_mythread();
    pm_get_data_mythread(&data);

    ... print results ...
}
```

## Initialization example using an event group

The following example displays initialization using an event group.

```
# include <pmapi.h>
main()
{
    pm_info2_t      pminfo;
    pm_prog_t      prog;
    pm_groups_info_t pmginfo;

    int filter = PM_VERIFIED; /* get list of verified events */

    pm_initialize(filter, &pminfo, &pmginfo, PM_CURRENT )

    prog.mode.w      = 0; /* start with clean mode */
    prog.mode.b.user = 1; /* count only user mode */
    prog.mode.b.is_group = 1; /* specify event group */

    for (i = 0; i < pminfo.maxpmcs; i++)
        prog.events[i] = COUNT_NOTHING;

    prog.events[0]   = 1; /* count events in group 1 */
    .....
}
```

## Get the information about all the event-groups for a specific processor example

The following example displays how to obtain all the event-groups that are supported for a specific processor.

```
#include <stdio.h>
#include <stdlib.h>
#include <pmapi.h>

int main()
{
    int rc = 0;
    pm_info2_t events;
    pm_groups_info_t groups;

    pm_events2_t *ev_ptr = NULL;

    int filter = 0;
    /*
    * Get the events and groups supported for POWER4.
    * To get the events and groups supported for the current processor,
    * use PM_CURRENT.
    */
    int processor_type = PM_POWER4;

    int group_idx = 0;
    int counter_idx = 0;
    int ev_count = 0;
    int event_found = 0;

    /*
    * PM_VERIFIED      - To get list of verified events
    * PM_UNVERIFIED    - To get list of unverified events
    * PM_CAVEAT        - To get list of events that are usable but with caveats
    */
    filter |= PM_VERIFIED | PM_UNVERIFIED | PM_CAVEAT;

    /* Get list of events-groups */
    filter |= PM_GET_GROUPS;

    if ((rc = pm_initialize(filter, &events, &groups, processor_type)) != 0)
    {
        pm_error("pm_initialize", rc);
        exit(-1);
    }
    for(group_idx = 0; group_idx < groups.maxgroups; group_idx++)
    {
        printf("=====\n");
        printf("Group ID: %d.\n", groups.event_groups[group_idx].group_id);
        printf("Group Name: %s.\n", groups.event_groups[group_idx].short_name);
        printf("Group Long Name: %s.\n", groups.event_groups[group_idx].long_name);
        printf("Group Description: %s.\n", groups.event_groups[group_idx].description);
        printf("Events in this Group: \n");
    }
}
```

```

for(counter_idx = 0; counter_idx < events.maxpmcs; counter_idx++)
{
    event_found = 0;
    for(ev_ptr = events.list_events[counter_idx], ev_count = 0;
        ev_count < events.maxevents[counter_idx];
        ev_ptr++, ev_count++)
    {
        /* If the event ID in "groups" matches with event ID supported
        * in the counter */
        if(groups.event_groups[group_idx].events[counter_idx] == ev_count)
        {
            printf("\tCounter ID: %d.\n", counter_idx+1);
            printf("\tEvent ID: %d.\n", ev_count);
            printf("\tEvent Name: %s.\n", ev_ptr->short_name);
            event_found = 1;
            break;
        }
        /* We have found the event for this counter. Move on to
        * next counter. */
        if(event_found) break;
    }
}
printf("\n");
}
return 0;
}

```

### ***Debugger program example for initialization program***

The following example illustrates how to look at the performance monitor data while the program is executing.

```

from a debugger at breakpoint (1)

(2) pm_initialize(filter);
    pm_get_program_pthread(pid, tid, ptid, &prog);
    ... display PM programming ...

(3) pm_get_data_pthread(pid, tid, ptid);
    ... display PM data ...

    pm_delete_program_pthread(pid, tid, ptid);
    prog.events[0] = 2; /* change counter 1 to count event number 2 */
    pm_set_program_pthread(pid, tid, ptid, &prog);

continue program

```

The preceding scenario would also work if the program being executed under the debugger did not have any embedded Performance Monitor API calls. The only difference would be that the calls at (2) and (3) would fail, and that when the program continues, it will be counting only event number 2 in counter 1, and nothing in other counters.

### ***Count a single WPAR from the Global WPAR***

The following program is an example of a count of a single WPAR from the global WPAR.

```

main ()
{
    pm_prog_t prog;
    pm_wpar_ctx_info_t wp_list;
    int nwpars = 1;
    cid_t cid;

    /* set programming for WPAR ``wpar1'' */
    getcorralid("wpar1", &cid);
    pm_set_program_wp(cid, &prog);

    pm_start_wp(cid);
    ... workload ...
    pm_stop_wp(cid);

    /* retrieve data for WPAR ``wpar1'' */
    pm_get_wplist("wpar1", &wp_list, &nwpars);
    pm_get_data_wp(wp_list.wp_handle, &data);
}

```

```

    pm_delete_program_wp(cid);
}

```

### **Count all active WPARs from the Global WPAR and retrieve per-WPAR data**

The following program is an example of a count of all active WPARS from the global WPAR and also retrieves per-WPAR data.

```

main ()
{
    pm_prog_t prog;
    pm_wpar_ctx_info_t *wp_list;
    int nwpars;

    /* set programming */
    ...
    prog.mode.b.wpar_all = 1; /* collect per-WPAR data */
    pm_set_program(&prog);

    pm_start();
    ... workload ...
    pm_stop();

    /* retrieve the number of WPARs that were active during the counting */
    nwpars = 0;
    pm_get_wplist(NULL, NULL, &nwpars);
    /* allocate an array large enough to retrieve WPARs contexts */
    wp_list = malloc(nwpars * sizeof (pm_wpar_ctx_info_t));
    /* retrieve WPARs contexts */
    pm_get_wplist(NULL, wp_list, &nwpars);

    /* retrieve and print data for each WPAR */
    for (i = 0; i < nwpars; i++) {
        printf("WPAR: %s (CID=%d)\n", wp_list[i].name, wp_list[i].cid);
        pm_get_data_wp(wp_list[i].hwpar, &data);
    }

    free(wp_list);

    pm_delete_program();
}

```

### **Simple multi-threaded example**

The following is a simple multi-threaded example with independent threads counting the same set of events.

```

#include <pmapi.h>
pm_data_t data2;

void *
doit(void *)
{
    (1)    pm_start_mythread();
        ... usefull work ....

    pm_stop_mythread();
    pm_get_data_mythread(&data2);
}

main()
{
    pthread_t threadid;
    pthread_attr_t attr;
    pthread_addr_t status;

    ... same initialization as in previous example ...

    pm_program_mythread(&prog);

    /* setup 1:1 mode */
    pthread_attr_init(&attr);
    pthread_attr_setscope(&attr, PTHREAD_SCOPE_SYSTEM);
    pthread_create(&threadid, &attr, doit, NULL);

    (2)    pm_start_mythread();
}

```

```

... usefull work ....

pm_stop_mythread();
pm_get_data_mythread(&data);

... print main thread results (data )...

pthread_join(threadid, &status);

... print auxiliary thread results (data2) ...
}

```

In the preceding example, counting starts at (1) and (2) for the main and auxiliary threads respectively because the initial counting state was off and it was inherited by the auxiliary thread from its creator.

### ***Simple thread counting-group example***

The following example has two threads in a counting-group. The body of the auxiliary thread's initialization routine is the same as in the previous example.

```

main()
{
    ... same initialization as in previous example ...

(1)  pm_set_program_mygroup(&prog); /* create counting group */
    pm_start_mygroup()

    pthread_create(&threadid, &attr, doit, NULL)

(2)  pm_start_mythread();

    ... usefull work ....

    pm_stop_mythread();
    pm_get_data_mythread(&data)

    ... print main thread results ...

    pthread_join(threadid, &status);

    ... print auxiliary thread results ...

    pm_get_data_mygroup(&data)

    ... print group results ...
}

```

In the preceding example, the call in (2) is necessary because the call in (1) only turns on counting for the group, not the individual threads in it. At the end, the group results are the sum of both threads results.

### ***Simple thread counting-group with counter-multiplexing example***

The following example has two threads in a counting-group. The body of the auxiliary thread's initialization routine is the same as in the previous example.

```

main()
{
    pm_info2_t          pminfo;
    pm_groups_info_t   pmginfo;
    pm_prog_mx_r       prog;
    pm_events_prog_t   event_set[2];
    pm_data_mx_t       data;
    int filter = PM_VERIFIED; /* get list of verified events */
    pm_initialize(filter, &pminfo, &pmginfo, PM_CURRENT )
    prog.mode.w         = 0; /* start with clean mode */
    prog.mode.b.user    = 1; /* count only user mode */
    prog.mode.b.is_group = 1; /* specify event group */
    prog.events_set     = event_set;
    prog.nb_events_prog = 2; /* two event group counted */
    prog.slice_duration = 200; /* slice duration for each event group is 200ms */
    for (i = 0; i < pminfo.maxpmcs; i++) {
        event_set[0][i] = COUNT_NOTHING;
        event_set[1][i] = COUNT_NOTHING;
    }
}

```

```

event_set[0][0]      = 1; /* count events in group 1 in the first set */
event_set[1][0]      = 3; /* count events in group 3 in the first set */
pm_set_program_mygroup_mx(&prog); /* create counting group */
pm_start_mygroup()
pthread_create(&threadid, &attr, doit, NULL)
pm_start_mythread();
... usefull work ...
pm_stop_mythread();
pm_get_data_mythread_mx(&data)
printf ("Main thread results:\n");
for (i = 0; i < 2 ; i++) {
    group_number = event_set[i][0];
    printf ("Group #%d: %s\n", group_number,
pminfo.event_groups[group_number].short_name);
    printf ("    counting time: %d ms\n", data.accu_set[i].accu_time);
    printf ("    counting values:\n");

    for (counter = 0; counter < pminfo.maxpmcs; counter++) {
        printf ("event %d: %d\n", counter, data.accu_set[i].accu_data[counter]);
    }
}
(1) free(data.accu_set); /* free the memory allocated for the main thread results */
pthread_join(threadid, &status);
... print auxiliary thread results ...
free(data.accu_set); /* free the memory allocated for the thread results */
pm_get_data_mygroup_mx(&data)
... print group results ...
free(data.accu_set); /* free the memoory allocated for the group results */
pm_delete_program()
}
(1) Each time data are got in time slice mode, the buffer allocated to return the counters */
must be freed after used.

```

### ***Simple thread counting-group with counter-multiplexing and multi-mode example***

The following example has two threads in a counting-group. The body of the auxiliary thread's initialization routine is the same as in the previous example.

This example is similar to the previous one except that it uses the multi-mode functionality, and associates a mode with each group counted.

```

main()
{
    pm_info2_t      pminfo;
    pm_groups_info_t pminfo;
    pm_prog_mm_t    prog;
    pm_data_mx_t    data;
    pm_prog_t      prog_set[2];
    int filter = PM_VERIFIED; /* get list of verified events */
    pm_initialize(filter, &pminfo, &pminfo, PM_CURRENT );
    prog_prog_set = prog_set;
    prog_nb_set_prog = 2; /* two groups counted */
    prog_slice_duration = 200; /* slice duration for each event group is 200ms */
    prog_set[0].mode.w = 0; /* start with clean mode */
    prog_set[0].mode.b.user = 1; /* grp 0: count only user mode */
    prog_set[0].mode.b.is_group = 1; /* specify event group */
    prog_set[0].mode.b.proctree = 1; /* turns process tree counting on:
    this option is common to all counted groups */
    prog_set[1].mode.w = 0; /* start with clean mode */
    prog_set[1].mode.b.kernel = 1; /* grp 1: count only kernel mode */
    prog_set[1].mode.b.is_group = 1; /* specify event group */
    for (i = 0; i < pminfo.maxpmcs; i++) {
        prog_set[0].events[i] = COUNT_NOTHING;
        prog_set[1].events[i] = COUNT_NOTHING;
    }
    prog_set[0].events[0] = 1; /* count events in group 1 in the first set */
    prog_set[1].events[0] = 3; /* count events in group 3 in the first set */
    pm_set_program_mygroup_mm(&prog); /* create counting group */
    pm_start_mygroup();
    pthread_create(&threadid, &attr, doit, NULL);
    pm_start_mythread();
    ... usefull work ...
    pm_stop_mythread();
    pm_get_data_mythread_mx(&data);
    printf ("Main thread results:\n");
    for (i = 0; i < 2 ; i++) {
        group_number = prog_set[i].events[0];
        printf ("Group #%d: %s\n", group_number,

```

```

pmginfo.event_groups[group_number].short_name);
    printf ("      counting time: %d ms\n", data.accu_set[i].accu_time);
    printf ("      counting values:\n");
    for (counter = 0; counter < pminfo.maxpmcs; counter++) {
        printf ("event %d: %d\n", counter, data.accu_set[i].accu_data[counter]);
    }
}
(1) free(data.accu_set); /* free the memory allocated for the main thread results */
pthread_join(threadid, &status);
... print auxiliary thread results ...
free(data.accu_set); /* free the memory allocated for the thread results */
pm_get_data_mygroup_mx(&data)
... print group results ...
free(data.accu_set); /* free the memory allocated for the group results */
pm_delete_program();
}
(1) Each time data are got in time slice mode, the buffer allocated to return the
counters must be freed after used.
}

```

### Thread counting example with reset

The following example with a reset call illustrates the impact on the group data. The body of the auxiliary thread is the same as before, except for the **pm\_start\_mythread** call, which is not necessary in this case.

```

main()
{
    ... same initialization as in previous example...

    prog.mode.b.count = 1; /* start counting immediately */
    pm_set_program_mygroup(&prog);

    pthread_create(&threadid, pthread_attr_default, doit, NULL)

    ... usefull work ....

    pm_stop_mythread()
    pm_reset_data_mythread()

    pthread_join(threadid, &status);

    ...print auxiliary thread results...

    pm_get_data_mygroup(&data)

    ...print group results...
}

```

In the preceding example, the main thread and the group counting state are both on before the auxiliary thread is created, so the auxiliary thread will inherit that state and start counting immediately.

At the end, **data1** is equal to **data** because the **pm\_reset\_data\_mythread** automatically subtracted the main thread data from the group data to keep it consistent. In fact, the group data remains equal to the sum of the auxiliary and the main thread data, but in this case, the main thread data is null.

### Accessing PMU registers from user applications

You cannot access Performance Monitoring Unit (PMU) registers from user applications (user-mode) when a system starts, from another PMU-based profiler, or from Live Partition Mobility (LPM) with libpmapi pragmas.

A libpmapi pragma is a light-weight subroutine that is exported through the libpmapi library, which provides access to the PMU registers. A libpmapi pragma uses the mtspr and mfspr instructions instead of the pmsvcs kernel extension to avoid system calls.

The following libpmapi pragmas are included in the AIX operating system:

- mmcr\_read Subroutine
- mmcr\_write Subroutine
- pmc\_read\_1to4 Subroutine
- pmc\_read\_5to6 Subroutine

- pmc\_write Subroutine

In the following scenarios, if you use the libpmapi pragmas for read and write access to the PMU registers, -1 is returned, which indicates that the option is not available. Therefore, you cannot access the PMU registers from a user application in the following scenarios:

- When a system starts

```
MMCR0[PMCC] is set to 00
PMCs 1-6, MMCR0, MMCR1 and MMCR2 registers are read only.
Access using pmc_read_1to4 , pmc_read_5to6 and mmcr_read returns 0
Access using pmc_write and mmcr_write returns -1
```

- Another PMU-based profiler is used

```
MMCR0[PMCC] is set to 00
PMCs 1-6, MMCR0, MMCR1 and MMCR2 registers are read only.
Access using pmc_read_1to4 , pmc_read_5to6 and mmcr_read returns 0
Access using pmc_write and mmcr_write returns -1
```

- During LPM

```
Prior to the Mobility operation, any running PMU counting is stopped and MMCR0[PMCC] is set to 00.
Post Mobility operation, PMCs 1-6, MMCR0, MMCR1 and MMCR2 registers are read only.
Access using pmc_read_1to4 , pmc_read_5to6 and mmcr_read returns 0
Access using pmc_write and mmcr_write returns -1
```

Instead of using the libpmapi pragmas, if you use the mtspr and the mfspr instructions to access the PMU registers, a SIGILL signal is generated for any write operations.

Sample programs are located in the /usr/samples/pmapi directory.

### Related information

[mmcr\\_read subroutine](#)

[mmcr\\_write subroutine](#)

[pmc\\_read\\_1to4 subroutine](#)

[pmc\\_read\\_5to6 subroutine](#)

[pmc\\_write subroutine](#)

## The hpm library and associated tools

The hpm libraries are higher-level instrumentation libraries based on the pmapi library. They support multiple instrumentation sections, nested instrumentation, and each instrumented section can be called multiple times.

When nested instrumentation is used, exclusive duration is generated for the outer sections. Average and standard deviation is provided when an instrumented section is activated multiple times.

The libraries support OpenMP and threaded applications, which requires linking with the thread-safe version of the library, **libhpm\_r**. Both 32-bit and 64-bit library modules are provided.

The libraries collect information and hardware Performance Monitor summarization during run-time. So, there could be considerable overhead if instrumentation sections are inserted inside inner loops.

### Compiling and linking

The functionality of the **libhpm\_r** library depends upon the corresponding functions in the **libpmapi** and **libm** libraries. Therefore, the **lpmpapi -lm** flag must be specified when compiling applications using the hpm libraries.

By default, argument passing from Fortran applications to the hpm libraries is done by reference, or pointer, not by value. Also, there is an extra length argument following character strings. You can modify the default argument passing method by using the **%VAL** and **%REF** built-in functions.

## Overhead and measurement error issues

It is expected for any software instrumentation to incur some overhead. Since it is not possible to eliminate the overhead, the goal is to minimize it. In the hpm library, most of the overhead is due to time measurement, which tends to be an expensive operation in most systems.

A second source of overhead is due to run-time accumulation and storage of performance data. The hpm libraries collect information and perform summarization during run-time. Hence, there could be a considerable amount of overhead if instrumentation sections are inserted inside inner loops.

The hpm library uses hardware counters during the initialization and finalization of the library, retaining the minimum of the two for each counter as an estimate of the cost of one call to the start and stop functions. The estimated overhead is subtracted from the values obtained on each instrumented code section, which ensures that the measurement of error becomes close to zero. However, since this is a statistical approximation, in some situations where estimated overhead is larger than a measured count for the application, the approach fails. When the approach fails, you might get the following error message, which indicates that the estimated overhead was not subtracted from the measured values:

```
WARNING: Measurement error for <event name> not removed
```

You can deactivate the procedure that attempts to remove measurement errors by setting the **HPM\_WITH\_MEASUREMENT\_ERROR** environment variable to TRUE (1).

## Common hpm library rules

Review common hpm library rules.

The following rules are common to the hpm library APIs:

- The **hpmInit()** or **f\_hpminit()** function must be called before any other function in the API.
- The initialization function can only be called once in an application.
- Performance Monitor contexts, like the event set, event group, or counter/event pairs, cannot be reprogrammed at any time.
- All functions of the API are specified as void and return no value or status.

## Overview of the hpm library API calls

The following table lists the hpm library API calls.

API Call	Purpose
<b>hpmInit</b> or <b>f_hpminit</b>	Performs initialization for a specified node ID and program name.
<b>hpmStart</b> or <b>f_hpmstart</b>	Indicates the beginning of an instrumented code segment, which is identified by an instrumentation identifier, InstID.
<b>hpmStop</b> or <b>f_hpmstop</b>	Indicates the end of an instrumented code segment. For each call to the <b>hpmStart()</b> or <b>f_hpmstart()</b> function, there should be a corresponding call to the <b>hpmStop()</b> or <b>f_hpmstop()</b> function with the matching instrumentation identifier.
<b>hpmTstart</b> or <b>f_hpmtstart</b>	Performs the same function as the <b>hpmStart()</b> and <b>f_hpmstart()</b> functions, but they are used in threaded applications.
<b>hpmTstop</b> or <b>f_hpmtstop</b>	Performs the same function as the <b>hpmStop()</b> and <b>f_hpmstop()</b> functions, but they are used in threaded applications.
<b>hpmGetTimeAndCounters</b> or <b>f_hpmgetttimeandcounters</b>	Returns the time, in seconds, and the accumulated counts since the call to the <b>hpmInit()</b> or <b>f_hpminit()</b> initialization function.
<b>hpmGetCounters</b> or <b>f_hpmgetcounter</b>	Returns all the accumulated counts since the call to the <b>hpmInit()</b> or <b>f_hpminit()</b> initialization function.

API Call	Purpose
<b>hpmTerminate</b> or <b>f_hpmterminate</b>	Performs termination and generates output. If an application exits without calling the <b>hpmTerminate()</b> or <b>f_hpmterminate()</b> function, no performance information is generated.

## Threaded applications

The **T/tstart** and **T/tstop** functions respectively start and stop the counters independently on each thread. If two distinct threads use the same **instID** parameter, the output indicates multiple calls. However, the counts are accumulated.

The **instID** parameter is always a constant variable or integer. It cannot be an expression because the declarations in the **libhpm.h**, **f\_hpm.h**, and **f\_hpm\_i8.h** header files that contain **#define** statements are evaluated during the compiler pre-processing phase, which permits the collection of line numbers and source file names.

## Selecting events when using the hpm libraries and tools

The hpm libraries use the same set of hardware counters and events used by the **hpmcount** and **hpmstat** tools. The events are selected by sets. Sets are specially marked event groups for whichever derived metrics are available.

For the hpm libraries, you can select the event set to be used by any of the following methods:

- The **HPM\_EVENT\_SET** environment variable, which is either explicitly set in the environment or specified in the **HPM\_flags.env** file.
- The content of the **libHPMevents** file.

For the **hpmcount** and **hpmstat** commands, you can specify which event types you want to be monitored and the associated hardware performance counters by any of the following methods:

- Using the **-s** option
- The **HPM\_EVENT\_SET** environment variable, which you can set directly or define in the **HPM\_flags.env** file
- The content of the **libHPM\_events** file

In all cases, the **HPM\_flags.env** file takes precedence over the explicit setting of the **HPM\_EVENT\_SET** environment variable and the content of the **libHPMevents** or **libHPM\_events** file takes precedence over the **HPM\_EVENT\_SET** environment variable.

An event group can be specified instead of an event set, using any of the following methods:

- The **-g** option
- The **HPM\_EVENT\_GROUP** environment variable that you can set directly or define in the **HPM\_flags.env** file

In all cases, the **HPM\_flags.env** file takes precedence over the explicit setting of the **HPM\_EVENT\_GROUP** environment variable. The **HPM\_EVENT\_GROUP** environment variable takes precedence over the explicit setting of the **HPM\_EVENT\_SET** environment variable. The **HPM\_EVENT\_GROUP** is a comma separated list of group names or group numbers.

A list of derived metric groups to be evaluated can be specified, using any of the following methods:

- The **-m** option
- The **HPM\_PMD\_GROUP** environment variable that you can set directly or define in the **HPM\_flags.env** file

In all cases, the **HPM\_flags.env** file take precedence over the explicit setting of the **HPM\_PMD\_GROUP** environment variable. The **HPM\_PMD\_GROUP** is a comma-separated list of derived metric group names.

Each set, group or derived metric group can be qualified by a counting mode. The allowed counting modes are:

- u: user mode
- k: kernel mode
- h: hypervisor mode
- r: runlatch mode
- n: nointerrupt mode

The counting mode qualifier is separated from the set or group by a colon ":". For example:

```
HPM_EVENT_GROUP=pm_utilization:uk,pm_completion:u
```

To use the time slice functionality, specify a comma-separated list of sets instead of a single set number. By default, the time slice duration for each set is 100 ms, but this can be modified with the **HPM\_MX\_DURATION** environment variable. This value must be expressed in ms, and in the range 10 ms to 30000 ms.

### ***The libHPMevents and libHPM\_events files***

The **libHPMevents** and **libHPM\_events** files are both supplied by the user and have the same format.

For POWER3 or PowerPC 604 RISC Microprocessor systems, the file contains the counter number and the event name, like in the following example:

```
0 PM_LD_MISS_L2HIT
1 PM_TAG_BURSTRD_L2MISS
2 PM_TAG_ST_MISS_L2
3 PM_FPU0_DENORM
4 PM_LSU_IDLE
5 PM_LQ_FULL
6 PM_FPU_FMA
7 PM_FPU_IDLE
```

For POWER4 and later systems, the file contains the event group name, like in the following example:

```
pm_hpmcount1
```

### ***The HPM\_flags.env file***

The **HPM\_flags.env** file contains environment variables that are used to specify the event set and for the computation of derived metrics

### **Example**

```
HPM_L2_LATENCY 12
HPM_EVENT_SET 5
```

## **Output files of the hpm library**

When the **hpmTerminate** function is called, a summary report is written to the **<progName>\_<pid>\_<taskID>.hpm** file, by default. The taskID and progName values are the first and second parameters of the **hpmInit()** function, respectively.

You can define the name of the output file with the **HPM\_OUTPUT\_NAME** environment variable. The hpm libraries always add the **\_<taskID>.hpm** suffix to the specified value. You can also include the date and time in the file name using the **HPM\_OUTPUT\_NAME** environment variable. For example, if you use the following code:

```
MYDATE=$(date +"m%d:2/2/06M%S")
export HPM_OUTPUT_NAME=myprogram_${MYDATE}
```

the output file for task 27 is named **myprogram\_yyyymmdd:HHMMSS\_0027.hpm**.

You can also generate an XML output file by setting the **HPM\_VIZ\_OUTPUT=TRUE** environment variable. The generated output files are named either **<progName>\_<pid>\_<taskID>.viz** or **HPM\_OUTPUT\_NAME\_<taskID>.viz**.

## Output files of the `hpmcount` command

The output file for the `hpmcount` command depend on the environment variables set and the execution environment.

The following are the output files of the `hpmcount` command:

### File name

#### Description

#### `file_<myID>.<pid>`

The value for *file* is specified with the `-o` option and the *myID* value is assigned the value of the `MP_CHILD` environment variable, which has a default value of 0000.

#### `HPM_LOG_DIR/hpm_log.<pid>`

When the `HPM_LOG_DIR` environment variable is set to an existing directory, results are additionally written to the `hpm_log.<pid>` file.

#### `HPM_LOG_DIR/hpm_log.MP_PARTITION`

The `MP_PARTITION` environment variable is provided in POE environments. The `hpm_log.MP_PARTITION` file contains the aggregate counts.

An XML output can be provided by using the `-x` option.

An alternative time base for the result normalization can be selected using any of the following methods:

- The `-b time|purr|spurr` option
- The `HPM_NORMALIZE` environment variable that you can set directly or define in the `HPM_flags.env` file

## Derived metrics and related environment variables

In relation to the hardware events that are selected to be counted and the hardware platform that is used, the output for the `hpm` library tools and the `hpmterminate` function includes derived metrics.

You can list the globally supported metrics for a given processor with the `pmlist -D -1 [-p Processor_name]` command.

You can supply the following environment variables to specify estimations of memory, cache, and TLB miss latencies for the computation of related derived metrics:

- `HPM_MEM_LATENCY`
- `HPM_L3_LATENCY`
- `HPM_L35_LATENCY`
- `HPM_AVG_L3_LATENCY`
- `HPM_AVG_L2_LATENCY`
- `HPM_L2_LATENCY`
- `HPM_L25_LATENCY`
- `HPM_L275_LATENCY`
- `HPM_L1_LATENCY`
- `HPM_TLB_LATENCY`

Precedence is given to variables that are defined in the `HPM_flags.env` file.

You can use the `HPM_DIV_WEIGHT` environment variable to compute the weighted flips on systems that are POWER4 and later.

## Examples of the hpm tools

The examples in this section demonstrate the usage of the following hpm library commands:

### *The pmlist command*

The following is an example of the **pmlist** command on a POWER5 processor-based system.

```
# pmlist -s

POWER5 supports 6 counters

Number of groups      : 144
Number of sets       : 8

Threshold multiplier (lower): 1
Threshold multiplier (upper): 32
Threshold multiplier (hyper): 64
Hypervisor counting mode is supported
Runlatch counting mode is supported
```

The following is another example of the **pmlist** command:

```
# pmlist -D -1 -p POWER5
Derived metrics supported:
PMD_UTI_RATE           Utilization rate
PMD_MIPS               MIPS
PMD_INST_PER_CYC      Instructions per cycle
PMD_HW_FP_PER_CYC     HW floating point instructions per Cycle
PMD_HW_FP_PER_UTIME   HW floating point instructions / user time
PMD_HW_FP_RATE        HW floating point rate
PMD_FX                Total Fixed point operations
PMD_FX_PER_CYC        Fixed point operations per Cycle
PMD_FP_LD_ST          Floating point load and store operations
PMD_INST_PER_FP_LD_ST Instructions per floating point load/store
PMD_PRC_INST_DISP_CMPL % Instructions dispatched that completed
PMD_DATA_L2           Total L2 data cache accesses
PMD_PRC_L2_ACCESS     % accesses from L2 per cycle
PMD_L2_TRAF           L2 traffic
PMD_L2_BDW            L2 bandwidth per processor
PMD_L2_LD_EST_LAT_AVG Estimated latency from loads from L2 (Average)
PMD_UTI_RATE_RC       Utilization rate (versus run cycles)
PMD_INST_PER_CYC_RC   Instructions per run cycle
PMD_LD_ST             Total load and store operations
PMD_INST_PER_LD_ST    Instructions per load/store
PMD_LD_PER_LD_MISS    Number of loads per load miss
PMD_LD_PER_DTLB       Number of loads per DTLB miss
PMD_ST_PER_ST_MISS    Number of stores per store miss
PMD_LD_PER_TLB        Number of loads per TLB miss
PMD_LD_ST_PER_TLB     Number of load/store per TLB miss
PMD_TLB_EST_LAT       Estimated latency from TLB miss
PMD_MEM_LD_TRAF       Memory load traffic
PMD_MEM_BDW           Memory bandwidth per processor
PMD_MEM_LD_EST_LAT    Estimated latency from loads from memory
PMD_LD_LMEM_PER_LD_RMEM Number of loads from local memory per loads from remote
memory
PMD_PRC_MEM_LD_RC     % loads from memory per run cycle
```

### *The hpmcount command*

The following is example output from the of the **hpmcount** command.

```
# hpmcount -m cpi_breakdown ls
bar      foo
Workload context: ls (pid:42234)
Execution time (wall clock time): 0.004222 seconds
##### Resource Usage Statistics #####
Total amount of time in user mode      : 0.001783 seconds
Total amount of time in system mode    : 0.000378 seconds
Maximum resident set size              : 220 Kbytes
Average shared memory use in text segment : 0 Kbytes*sec
Average unshared memory use in data segment : 0 Kbytes*sec
Number of page faults without I/O activity : 63
Number of page faults with I/O activity  : 0
Number of times process was swapped out  : 0
Number of times file system performed INPUT : 0
Number of times file system performed OUTPUT : 0
Number of IPC messages sent            : 0
```

```

Number of IPC messages received      : 0
Number of signals delivered         : 0
Number of voluntary context switches : 0
Number of involuntary context switches : 0
##### End of Resource Statistics #####
Counting mode: user
PM_1PLUS_PPC_CMPL (One or more PPC instruction completed) : 143749896
PM_GCT_EMPTY_CYC (Cycles GCT empty) : 12905400
PM_GRP_CMPL (Group completed) : 144626424
PM_CYC (Processor cycles) : 434717274
PM_INST_CMPL (Instructions completed) : 193121895
PM_RUN_CYC (Run cycles) : 378397903
PM_GCT_NOSLOT_CYC (Cycles no GCT slot allocated) : 87592746
PM_GCT_NOSLOT_IC_MISS : 16066248
  (No slot in GCT caused by I cache miss)
PM_GCT_NOSLOT_SRQ_FULL (No slot in GCT caused by SRQ full) : 0
PM_GCT_NOSLOT_BR_MPRED : 27869700
  (No slot in GCT caused by branch mispredict)
PM_GRP_MRK (Group marked in IDU) : 6041616
PM_CMPLU_STALL_LSU : 117973392
  (Completion stall caused by LSU instruction)
PM_IOPS_CMPL (Internal operations completed) : 162398665
PM_CMPLU_STALL_REJECT (Completion stall caused by reject) : 24318036
PM_CMPLU_STALL_DCACHE_MISS : 25055262
  (Completion stall caused by D cache miss)
PM_CMPLU_STALL_ERAT_MISS : 17332764
  (Completion stall caused by ERAT miss)
PM_GRP_IC_MISS_BR_REDIR_NONSPEC : 2551038
  (Group experienced non-speculative I cache miss or branch redirect)
PM_CMPLU_STALL_FXU : 69575412
  (Completion stall caused by FXU instruction)
PM_CMPLU_STALL_DIV : 45664068
  (Completion stall caused by DIV instruction)
PM_FPU_FULL_CYC (Cycles FPU issue queue full) : 27660
PM_CMPLU_STALL_FDIV : 319104
  (Completion stall caused by FDIV or FQRT instruction)
PM_CMPLU_STALL_FPU : 500274
  (Completion stall caused by FPU instruction)
Derived metric group: cpi_breakdown
Total cycles : 2.250999
  Completion cycles : 0.748887
  Completion Table empty (GCT empty) : 0.266825
  I-Cache Miss Penalty : 0.083192
  Branch Mispredication Penalty : 0.144311
  Others GCT stalls : 0.039322
  Completion Stall cycles : 1.435288
    Stall by LSU instruction : 0.610875
      Stall by LSU Reject : 0.125921
        Stall by LSU Translation Reject : 0.089750
        Stall by LSU Other Reject : 0.036170
      Stall by LSU D-cache miss : 0.129738
      Stall by LSU basic latency, LSU Flush penalty : 0.355217
    Stall by FXU instruction : 0.360267
    Stall by any form of DIV/MTSPR/MFSPR instruction : 0.236452
    Stall by FXU basic latency : 0.123815
    Stall by FPU instruction : 0.002590
    Stall by any form of FDIV/FSQRT instruction : 0.001652
    Stall by FPU basic latency : 0.000938
    Stall by others : 0.462493

```

## The hpmstat command

The following is an example output from the **hpmstat** command.

```

# hpmstat -s 7
Execution time (wall clock time): 1.003946 seconds
Counting mode: user
PM_TLB_MISS (TLB misses) : 260847
PM_CYC (Processor cycles) : 3013964331
PM_ST_REF_L1 (L1 D cache store references) : 161377371
PM_LD_REF_L1 (L1 D cache load references) : 255317480
PM_INST_CMPL (Instructions completed) : 1027391919
PM_RUN_CYC (Run cycles) : 1495147343
Derived metric group: default
Utilization rate : 181.243 %
Total load and store operations : 416.695 M
Instructions per load/store : 2.466
MIPS : 1023.354
Instructions per cycle : 0.341

```

The following is an example of the **hpmstat** command with counter multiplexing:

```
# hpmstat -s 1,2 -d
Execution time (wall clock time): 2.129755 seconds
Set: 1
Counting duration: 1.065 seconds
PM_INST_CMPL (Instructions completed) : 244687
PM_FPU1_CMPL (FPU1 produced a result) : 0
PM_ST_CMPL (Store instruction completed) : 31295
PM_LD_CMPL (Loads completed) : 67414
PM_FPU0_CMPL (Floating-point unit produced a result) : 19
PM_CYC (Processor cycles) : 295427
PM_FPU_FMA (FPU executed multiply-add instruction) : 0
PM_TLB_MISS (TLB misses) : 788
Set: 2
Counting duration: 1.064 seconds
PM_TLB_MISS (TLB misses) : 379472
PM_ST_MISS_L1 (L1 D cache store misses) : 79943
PM_LD_MISS_L1 (L1 D cache load misses) : 307338
PM_INST_CMPL (Instructions completed) : 848878245
PM_LSU_IDLE (Cycles LSU is idle) : 229922845
PM_CYC (Processor cycles) : 757442686
PM_ST_DISP (Store instructions dispatched) : 125440562
PM_LD_DISP (Load instr dispatched) : 258031257
Counting mode: user
PM_TLB_MISS (TLB misses) : 380260
PM_ST_MISS_L1 (L1 D cache store misses) : 160017
PM_LD_MISS_L1 (L1 D cache load misses) : 615182
PM_INST_CMPL (Instructions completed) : 848822932
PM_LSU_IDLE (Cycles LSU is idle) : 460224933
PM_CYC (Processor cycles) : 757738113
PM_ST_DISP (Store instructions dispatched) : 251088030
PM_LD_DISP (Load instr dispatched) : 516488120
PM_FPU1_CMPL (FPU1 produced a result) : 0
PM_ST_CMPL (Store instruction completed) : 62582
PM_LD_CMPL (Loads completed) : 134812
PM_FPU0_CMPL (Floating-point unit produced a result) : 38
PM_FPU_FMA (FPU executed multiply-add instruction) : 0
Derived metric group: default
Utilization rate : 189.830 %
% TLB misses per cycle : 0.050 %
number of loads per TLB miss : 0.355
Total L2 data cache accesses : 0.775 M
% accesses from L2 per cycle : 0.102 %
L2 traffic : 47.276 MBytes
L2 bandwidth per processor : 44.431 MBytes/sec
Total load and store operations : 0.197 M
Instructions per load/store : 4300.145
number of loads per load miss : 839.569
number of stores per store miss : 1569.133
number of load/stores per D1 miss : 990.164
L1 cache hit rate : 0.999 %
% Cycles LSU is idle : 30.355 %
MIPS : 199.113
Instructions per cycle : 1.120
```

## Examples of hpm library usage

The following are examples of hpm library usage:

### ***A C programming language example***

The following C program contains two instrumented sections which perform a trivial floating point operation, print the results, and then launch the command interpreter to execute the **ls -R / 2>&1 >/dev/null** command.

```
#include <sys/wait.h>
#include <unistd.h>
#include <stdio.h>
#include <libhpm.h>

void
do_work()
{
    pid_t p, wpid;
    int i, status;
    float f1 = 9.7641, f2 = 2.441, f3 = 0.0;
```

```

    f3 = f1 / f2;
    printf("f3=%f\n", f3);

    p = fork();

    if (p == -1) {
        perror("Mike fork error");
        exit(1);
    }

    if (p == 0) {
        i = execl("/usr/bin/sh", "sh", "-c", "ls -R / 2>&1 >/dev/null", 0);
        perror("Mike execl error");
        exit(2);
    }
    else
        wpid = waitpid(p, &status, WUNTRACED | WCONTINUED);

    if (wpid == -1) {
        perror("Mike waitpid error");
        exit(3);
    }

    return;
}

main(int argc, char **argv)
{
    int taskID = 999;

    hpmInit(taskID, "my_program");
    hpmStart(1, "outer call");
    do_work();
    hpmStart(2, "inner call");
    do_work();
    hpmStop(2);
    hpmStop(1);
    hpmTerminate(taskID);
}

```

### ***A Fortran programming language example***

The following declaration is required on all source files that have instrumentation calls.

```
#include "f_hpm.h"
```

Fortran programs call functions that include the `f_` prefix, as you can see in the following example:

```

call f_hpminit( taskID, "my_program" )
call f_hpmstart( 1, "Do Loop" )
do ...
    call do_work()
    call f_hpmstart( 5, "computing meaning of life" );
    call do_more_work();
    call f_hpmstop( 5 );
end do
call f_hpmstop( 1 )
call f_hpmterminate( taskID )

```

### ***Multithreaded application instrumentation example***

When placing instrumentation inside of parallel regions, you should use a different ID for each thread.

The following is an example multithreaded application instrumentation:

```

!$OMP PARALLEL
!$OMP&PRIVATE (instID)
    instID = 30+omp_get_thread_num()
    call f_hpmtstart( instID, "computing meaning of life" )
!$OMP DO
    do ...
        do_work()
    end do
    call f_hpmtstop( instID )
!$OMP END PARALLEL

```

The library accepts the use of the same `instID` for different threads, but the counters are accumulated for all instances with the same `instID`.

## Perfstat API programming

---

The **perfstat** application programming interface (API) is a collection of C programming language subroutines that is used in user space. It uses the **perfstat** kernel extension to extract various AIX performance metrics.

System component information is also retrieved from the Object Data Manager (ODM) and returned with the performance metrics.

The **perfstat** API is thread-safe, and does not require root authority.

The API supports extensions so binary compatibility is maintained across all releases of AIX. This interface is accomplished by using one of the parameters in all the API calls to specify the size of the data structure to be returned. The interface permits the library to determine the version it is using, using the structures that are growing. It helps the user from being dependent on the different versions. For the list of extensions in earlier versions of AIX, see the [Change History](#) section.

The **perfstat** API subroutines are present in the **libperfstat.a** library that are part of the **bos.perf.libperfstat** file set, which is installable from the AIX base installation media and requires that the **bos.perf.perfstat** file set is installed. The latter contains the kernel extension and is automatically installed with AIX.

The **/usr/include/libperfstat.h** file contains the interface declarations and type definitions of the data structures to use when calling the interfaces. The **include** file is also part of the **bos.perf.libperfstat** file set. Sample source code is provided with **bos.perf.libperfstat** file set and is present in the **/usr/samples/libperfstat** directory.

### Related information

[libperfstat.h command](#)

## API characteristics

Five types of APIs are available. Global types return global metrics related to a set of components, while individual types return metrics related to individual components. Both types of interfaces have similar signatures, but slightly different behavior.

AIX supports different types of APIs such as WPAR and RSET. WPAR types return usage metrics related to a set of components or individual components specific to a workload partition (WPAR). RSET types return usage metrics of processors that belong to an RSET. With AIX Version 6.1 Technology Level (TL) 6, a new type of APIs, called as NODE is available. The NODE types return usage metrics that are related to a set of components or individual components specific to a remote node in a cluster. The `perfstat_config` (`PERFSTAT_ENABLE | PERFSTAT_CLUSTER_STATS`, `NULL`) must be used to enable the remote node statistics collection (that is available in a cluster environment).

All the interfaces return raw data; that is, values of running counters. Multiple calls must be made at regular intervals to calculate rates.

Several interfaces return data retrieved from the ODM (object data manager) database. This information is automatically cached into a dictionary that is assumed to be "frozen" after it is loaded. The **perfstat\_reset** subroutine must be called to clear the dictionary whenever the system configuration has changed. In order to do a more selective reset, you can use the **perfstat\_partial\_reset** function. For more details, see the ["Cached metrics interfaces"](#) on page 190 section.

Most types returned are unsigned long long; that is, unsigned 64 bit data.

Excessive and redundant calls to Perfstat APIs in a short time span can have a performance impact because time-consuming statistics collected by them are not cached.

For examples of API characteristics, see the sample programs in the `/usr/samples/libperfstat` directory. All of the sample programs can be compiled using the provided makefile (`/usr/samples/libperfstat/Makefile.samples`).

## Global interfaces

Global interfaces report metrics related to a set of components on a system (such as processors, disks, or memory).

The following are the global interfaces:

Item	Descriptor
<b>perfstat_cpu_total</b>	Retrieves global processor usage metrics
<b>perfstat_memory_total</b>	Retrieves global memory usage metrics
<b>perfstat_disk_total</b>	Retrieves global disk usage metrics  <b>Note:</b> This API does not return any data when started from an application running inside WPAR.
<b>perfstat_netinterface_total</b>	Retrieves global network interfaces metrics  <b>Note:</b> This API does not return any data when started from an application running inside WPAR.
<b>perfstat_partition_config</b>	Retrieves Operating System and partition related information
<b>perfstat_partition_total</b>	Retrieves global partition metrics
<b>perfstat_tape_total</b>	Retrieves global tape usage metrics  <b>Note:</b> This API does not return any data when started from an application running inside WPAR.
> <b>bindid_to_lcpuid</b> <	Returns the logical CPU ID.
> <b>lcpuid_to_bindid</b> <	Returns the bind CPU ID.

The common signature used by all of the global interfaces is as follows:

```
int perfstat_subsystem_total(perfstat_id_t *name,
                           perfstat_subsystem_total_t *userbuff,
                           int sizeof_struct,
                           int desired_number);
```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<b>perfstat_id_t *name</b>	Reserved for future use, must be NULL
<b>perfstat_subsystem_total_t *userbuff</b>	A pointer to a memory area with enough space for the returned structure
<b>int sizeof_struct</b>	Should be set to <b>sizeof(perfstat_subsystem_t)</b>
<b>int desired_number</b>	Reserved for future use, must be set to 0 or 1

The return value is -1 in case of errors. Otherwise, the number of structures copied is returned. This is always 1.

The following sections provide examples of the type of data returned and code using each of the interfaces.

The following code shows an example of how **perfstat\_netinterface\_total** is used:

```
#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    perfstat_netinterface_total_t ninfo;
    int rc;
    rc = perfstat_netinterface_total(NULL, &ninfo, sizeof(perfstat_netinterface_total_t), 1);
    if (rc != 1)
    {
        perror("perfstat_netinterface_total");
        exit(-1);
    }
    perfstat_netinterface_total(NULL, &ninfo, sizeof(perfstat_netinterface_total_t), 1);

    printf("Network interfaces statistics\n");
    printf("-----\n");
    printf("number of interfaces : %d\n", ninfo.number);
    printf("\ninput statistics:\n");
    printf("number of packets : %llu\n", ninfo.ipackets);
    printf("number of errors : %llu\n", ninfo.ierrors);
    printf("number of bytes : %llu\n", ninfo.ibytes);
    printf("\noutput statistics:\n");
    printf("number of packets : %llu\n", ninfo.opackets);
    printf("number of bytes : %llu\n", ninfo.obytes);
    printf("number of errors : %llu\n", ninfo.oerrors);
}
```

The program produces output similar to the following:

```
Network interfaces statistics
-----
number of interfaces : 2

input statistics:
number of packets : 306688
number of errors : 0
number of bytes : 24852688

output statistics:
number of packets : 63005
number of bytes : 11518591
number of errors : 0
```

The preceding program emulates **ifstat's** behavior and also shows how **perfstat\_netinterface\_total** is used.

## perfstat\_cpu\_total Interface

The **perfstat\_cpu\_total** interface returns a **perfstat\_cpu\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_total\_t** structure include:

Item	Descriptor
<b>purrr_coalescing</b>	PURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero.
<b>spurr_coalescing</b>	SPURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero.
<b>processorHz</b>	Processor speed in Hertz (from ODM)
<b>description</b>	Processor type (from ODM)
<b>CPUs</b>	Current number of active processors
<b>ncpus_cfg</b>	Number of configured processors; that is, the maximum number of processors that this copy of AIX® can handle simultaneously
<b>ncpus_high</b>	Maximum number of active processors; that is, the maximum number of active processors since the last reboot

Item	Descriptor
<b>user</b>	Number of clock ticks spent in user mode
<b>sys</b>	Number of clock ticks spent in system (kernel) mode
<b>idle</b>	Number of clock ticks spent idle with no I/O pending
<b>wait</b>	Number of clock ticks spent idle with I/O pending

**Note:** Page coalescing is a transparent operation wherein the hypervisor detects duplicate pages, directs all user reads to a single copy, and reclaims the other duplicate physical memory pages.

Several other processor-related counters (such as number of system calls, number of reads, write, forks, execs, and load average) are also returned. For a complete list, see the **perfstat\_cpu\_total\_t** section of the [libperfstat.h](#) header file.

The following program emulates **lparstat's** behavior and also shows an example of how the **perfstat\_cpu\_total** interface is used:

```
#include <stdio.h>
#include <sys/time.h>
#include <sys/errno.h>
#include <sys/proc.h>
#include <wpars/wparcfg.h>
#include <libperfstat.h>
#include <stdlib.h>

/* default values for interval and count */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* values for wpar status */
#define ACTIVE 0
#define NOTACTIVE 1

/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror("malloc");\
    exit(2);\
}\
}

/* Non zero WPAR ID indicates WPAR */
#define IS_WPAR(X) ((X))

/* stores wpar id for perfstat library */
perfstat_id_wpar_t wparid;
perfstat_wpar_total_t wparinfo;
perfstat_wpar_total_t *wparlist;

/*Corral id for WPAR */
cid_t cid;

int interval = INTERVAL_DEFAULT, count = COUNT_DEFAULT;
int totalwpar, activewpar; /* to store and number of wpars available and active wpars */

/*
 *Name: do_cleanup
 * free all allocated data structures
 */
void do_cleanup(void)
{
    if (wparlist)
        free(wparlist);
}

/*
 *Name: display_global_sysinfo_stat
 * Function used when called from global.
 * Gets all the system metrics using perfstat APIs and displays them
 */
void display_global_sysinfo_stat(void)
{
    perfstat_cpu_total_t *cpustat,*cpustat_last;
    perfstat_id_t first;

    /* allocate memory for data structures and check for any error */
    cpustat = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(cpustat);

    cpustat_last = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(cpustat_last);

    /* get the system wide statistics */
```

```

if (perfstat_cpu_total(NULL , cpustat_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
    perror("perfstat_cpu_total ");
    exit(1);
}

printf ("%10s %10s %10s %10s %10s %10s %10s %10s %10s %10s %10s %10s\n", "cswch", "scalls", "sread", "swrite", "fork", "exec",
        "rchar", "wchar", "deviceint", "bwrite", "bread", "phread");
printf ("%10s %10s %10s %10s %10s %10s %10s %10s %10s %10s %10s %10s\n", "====", "====", "====", "====", "====",
        "====", "====", "====", "====", "====", "====");
while (count > 0){
    sleep(interval);
    if (perfstat_cpu_total(NULL ,cpustat , sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total ");
        exit(1);
    }
    /* print the difference between the old structure and new structure */
    printf("%10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu\n", (cpustat->pswitch - cpustat_last-
>pswitch),
        (cpustat->syscall - cpustat_last->syscall), (cpustat->sysread - cpustat_last-
>sysread ),
        (cpustat->syswrite - cpustat_last->syswrite), (cpustat->sysfork - cpustat_last-
>sysfork),
        (cpustat->sysexec - cpustat_last->sysexec ), (cpustat->readch - cpustat_last->readch),
        (cpustat->writetech - cpustat_last->writetech), (cpustat->devintrs - cpustat_last->devintrs),
        (cpustat->bwrite - cpustat_last->bwrite), (cpustat->bread - cpustat_last->bread ),
        (cpustat->phread - cpustat_last->phread ));

    count--;

    /*copy the present structure to the old structure */
    memcpy(cpustat_last , cpustat , sizeof(perfstat_cpu_total_t));
}
/* free the memory allocated for the data structures */
free(cpustat);
free(cpustat_last);
}

/*
 *Name: display_wpar_sysinfo_stat
 *   Displays both wpar and global metrics
 */

void display_wpar_sysinfo_stat(void)
{
    perfstat_wpar_total_t wparinfo;
    perfstat_cpu_total_wpar_t cinfo_wpar, cinfo_wpar_last;
    perfstat_cpu_total_t sysinfo, sysinfo_last;

    /* ste the spec and pass the wparname */
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, NULL);

    /* save the number of wpars which are active */
    activewpar = perfstat_wpar_total( NULL , &wparinfo ,sizeof(perfstat_wpar_total_t), 1);

    /* if the activewpar is less than zero exit with a perror */
    if (activewpar < 0){
        perror("perfstat_wpar_total :");
        exit(1);
    }

    /* if the wpar is not active exit with a message */
    if (activewpar == 0){
        printf("wpar not active \n");
        exit(1);
    }

    /* get the wpar wide cpu information */
    if (perfstat_cpu_total_wpar(NULL, &cinfo_wpar_last, sizeof(perfstat_cpu_total_wpar_t), 1) <=0){
        perror("perfstat_cpu_total_wpar :");
        exit(1);
    }
    if (perfstat_cpu_total(NULL , &sysinfo_last, sizeof(perfstat_cpu_total_t), 1) <=0){
        perror("perfstat_cpu_total_wpar :");
        exit(1);
    }
    printf("%10s %10s %10s %10s %10s %10s %10s %10s %10s %10s\n", wparname , "cswch" , "syscalls", "fork", "runque", "swpqe", "runocc", "swpocc" );
    printf("%10s %10s %10s %10s %10s %10s %10s %10s %10s %10s\n", "====", "====", "====", "====", "====", "====", "====", "====" );

    while (count > 0){
        sleep(interval);
        if (perfstat_cpu_total_wpar( NULL,&cinfo_wpar , sizeof(perfstat_cpu_total_wpar_t), 1) <=0){
            perror("perfstat_cpu_total_wpar :");
            exit(1);
        }
        if (perfstat_cpu_total(NULL, &sysinfo, sizeof(perfstat_cpu_total_t), 1) <=0){
            perror("perfstat_cpu_total :");
            exit(1);
        }

        /* display the difference between the current and old structure for the current wpar and system wide values*/
        printf("%10s %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu\n", wparinfo.name, (cinfo_wpar.pswitch - cinfo_wpar_last.pswitch),
            (cinfo_wpar.syscall - cinfo_wpar_last.syscall), (cinfo_wpar.sysfork - cinfo_wpar_last.sysfork),
            (cinfo_wpar.runque - cinfo_wpar_last.runque), (cinfo_wpar.swpqe - cinfo_wpar_last.swpqe),
            (cinfo_wpar.runocc - cinfo_wpar_last.runocc), (cinfo_wpar.swpocc - cinfo_wpar_last.swpocc));

        printf("%10s %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu %10llu\n", "Global", (sysinfo.pswitch - sysinfo_last.pswitch),
            (sysinfo.syscall - sysinfo_last.syscall), (sysinfo.sysfork - sysinfo_last.sysfork),
            (sysinfo.runque - sysinfo_last.runque), (sysinfo.swpqe - sysinfo_last.swpqe),
            (sysinfo.runocc - sysinfo_last.runocc), (sysinfo.swpocc - sysinfo_last.swpocc));

        count--;

        /* copy the data to the old structure */
        memcpy(&cinfo_wpar_last, &cinfo_wpar, sizeof(perfstat_wpar_total_t));
        memcpy(&sysinfo_last , &sysinfo , sizeof(perfstat_cpu_total_t));
    }
}

```

```

/* Name: display_wpar_total_sysinfo_stat
 * displays statistics of individual wpar
 *
 */
int display_wpar_total_sysinfo_stat(void)
{
    int i, *status;
    perfstat_wpar_total_t *wparinfo;
    perfstat_cpu_total_wpar_t *cinfo_wpar, *cinfo_wpar_last;

    /* allocate memory for the datastructures and check for any error */
    status = (int *) calloc(totalwpar, sizeof(int));
    CHECK_FOR_MALLOC_NULL(status);

    cinfo_wpar = (perfstat_cpu_total_wpar_t *) malloc(sizeof (perfstat_cpu_total_wpar_t) * totalwpar);
    CHECK_FOR_MALLOC_NULL(cinfo_wpar);

    cinfo_wpar_last = (perfstat_cpu_total_wpar_t *) malloc(sizeof (perfstat_cpu_total_wpar_t) * totalwpar);
    CHECK_FOR_MALLOC_NULL(cinfo_wpar_last);

    wparlist = (perfstat_wpar_total_t *) malloc(sizeof(perfstat_wpar_total_t) * totalwpar);
    CHECK_FOR_MALLOC_NULL(wparlist);

    activewpar = perfstat_wpar_total(&wparid, wparlist, sizeof(perfstat_wpar_total_t), totalwpar);

    if (activewpar < 0){
        perror("perfstat_wpar_total :");
        exit(1);
    }

    /* If no active wpars exit with a message */
    if (activewpar == 0){
        printf("no active wpars found \n");
        exit(1);
    }
    for (i = 0; i < activewpar; i++){
        /* copy the wparname into wparid and collect the data for all active wpars */
        strcpy(wparid.u.wparname, wparlist[i].name);
        if (perfstat_cpu_total_wpar(&wparid, &cinfo_wpar_last[i], sizeof(perfstat_cpu_total_wpar_t), 1) <= 0){
            status[i] = NOTACTIVE;
            continue;
        }
    }
    /*print the headers */
    printf("%20s %12s %12s %12s %12s %12s %12s %12s\n", "wparname", "cswitch", "fork", "runque", "swpque", "runocc", "swpocc", "syscalls");
    printf("%20s %12s %12s %12s %12s %12s %12s %12s\n", "=====", "=====", "====", "=====", "=====", "=====", "=====", "=====");

    while (count > 0){
        sleep(interval);
        for (i = 0; i < activewpar; i++){
            strcpy(wparid.u.wparname, wparlist[i].name);
            if (perfstat_cpu_total_wpar(&wparid, &cinfo_wpar[i], sizeof(perfstat_cpu_total_wpar_t), 1) <= 0){
                status[i] = NOTACTIVE;
                continue;
            }
        }
        /* print the data for all active wpars */
        for (i = 0; i < activewpar; i++){
            if(status[i] == ACTIVE)
                printf("%20s %12llu %12llu %12llu %12llu %12llu %12llu %12llu\n", wparlist[i].name,
                    (cinfo_wpar[i].pswitch - cinfo_wpar_last[i].pswitch), (cinfo_wpar[i].sysfork - cinfo_wpar_last[i].sysfork),
                    (cinfo_wpar[i].runque - cinfo_wpar_last[i].runque), (cinfo_wpar[i].swpque - cinfo_wpar_last[i].swpque),
                    (cinfo_wpar[i].runocc - cinfo_wpar_last[i].runocc), (cinfo_wpar[i].swpocc - cinfo_wpar_last[i].swpocc),
                    (cinfo_wpar[i].syscall - cinfo_wpar_last[i].syscall));
            printf("\n");
            count--;
            memcpy(cinfo_wpar_last, cinfo_wpar, (totalwpar * sizeof(perfstat_cpu_total_wpar_t)));
        }
        /* free all the memory structures */
        free(cinfo_wpar);
        free(cinfo_wpar_last);
        free(status);
    }

    /*
    *Name: showusage
    * displays the usage message
    *
    */
    void showusage()
    {
        if (!cid)
            printf("Usage:simplesysinfo [-@ { ALL | WPARNAME }] [interval] [count]\n ");
        else
            printf("Usage:simplesysinfo [interval] [count]\n");
    }
    exit(1);
}

/* NAME: main
 * This function determines the interval, iteration count.
 * Then it calls the corresponding functions to display
 * the corresponding metrics
 */
int main(int argc, char* argv[])
{
    int rc, atflag = 0, c;
    char wpar[MAXCORRALNAMELEN+1];
    strcpy(wpar, NULL);
    cid = corral_getcid();

    while((c = getopt(argc, argv, "@:")) != EOF){
        if (c == '@'){
            if (IS_WPAR(cid))
                showusage();
        }
    }
}

```

```

        atflag = 1;
        strcpy(wpar, optarg);
    }
}
argc -= optind;
argv += optind;

if (argc > 2)
    showusage();

if (argc){
    if ((interval = atoi(argv[0])) <= 0)
        showusage();
    argc--;
}

if (argc){
    if ((count = atoi(argv[1])) <= 0)
        showusage();
}

/* If no -@ flag call display_global_sysinfo_stat function */
if (!atflag){
    if (!cid)
        /*display global values */
        display_global_sysinfo_stat();
    else
        /* display wpar values */
        display_wpar_sysinfo_stat();
}
else{
    /* if the argument to -@ is not ALL set the totalwpars to 1 */
    if (strcmp(wpar, "ALL")) {
        strcpy(wparid.u.wparname, wpar);
        wparid.spec = WPARNAME;
        totalwpar = 1;
    }
    else{
        totalwpar = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);

        if (totalwpar < 0){
            perror("perfstat_wpar_total : ");
            exit(1);
        }
        if (totalwpar == 0){
            printf("No wpars found");
            exit(1);
        }
        wparid.spec = WPARNAME;
        strcpy(wparid.u.wparname, NULL);
    }
    display_wpar_total_sysinfo_stat();
}
do_cleanup();
return(0);
}

```

The program displays an output that is similar to the following example output:

cswch	scalls	sread	swrite	fork	exec	rchar	wchar	deviceint	bwrite	bread
83	525	133	2	0	1	1009462	264	27	0	
0	0									

## perfstat\_memory\_total Interface

The **perfstat\_memory\_total** interface returns a **perfstat\_memory\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_memory\_total\_t** structure include:

Item	Descriptor
<b>bytes_coalesced</b>	Number of bytes of the calling partition's logical real memory coalesced
<b>bytes_coalesced_mempool</b>	Number of bytes of logical real memory coalesced in the calling partition's memory pool if the calling partition is authorized to see pool wide statistics else, set to zero.
<b>virt_total</b>	Amount of virtual memory (in units of 4 KB pages)
<b>real_total</b>	Amount of real memory (in units of 4 KB pages)
<b>real_free</b>	Amount of free real memory (in units of 4 KB pages)
<b>real_pinned</b>	Amount of pinned memory (in units of 4 KB pages)
<b>pgins</b>	Number of pages paged in
<b>pgouts</b>	Number of pages paged out
<b>pgsp_total</b>	Total amount of paging space (in units of 4 KB pages)
<b>pgsp_free</b>	Amount of free paging space (in units of 4 KB pages)

Item	Descriptor
pgsp_rsvd	Amount of reserved paging space (in units of 4 KB pages)

**Note:** Page coalescing is a transparent operation wherein the hypervisor detects duplicate pages, directs all user reads to a single copy, and can reclaim other duplicate physical memory pages.

Several other memory-related metrics (such as amount of paging space paged in and out, and amount of system memory) are also returned. For a complete list, see the **perfstat\_memory\_total\_t** section of the `libperfstat.h` header file in *Files Reference*.

The preceding program emulates **vmstat's** behavior and also shows an example of how the **perfstat\_memory\_total** interface is used:

```
#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    perfstat_memory_total_t minfo;
    int rc;
    rc = perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1);
    if (rc != 1) {
        perror("perfstat_memory_total");
        exit(-1);
    }
    printf("Memory statistics\n");
    printf("-----\n");
    printf("real memory size           : %llu MB\n",
           minfo.real_total*4096/1024/1024);
    printf("reserved paging space      : %llu MB\n",minfo.pgsp_rsvd);
    printf("virtual memory size        : %llu MB\n",
           minfo.virt_total*4096/1024/1024);
    printf("number of free pages       : %llu\n",minfo.real_free);
    printf("number of pinned pages     : %llu\n",minfo.real_pinned);
    printf("number of pages in file cache : %llu\n",minfo.numperm);
    printf("total paging space pages   : %llu\n",minfo.pgsp_total);
    printf("free paging space pages    : %llu\n", minfo.pgsp_free);
    printf("used paging space          : %3.2f%%\n",
           (float)(minfo.pgsp_total-minfo.pgsp_free)*100.0/
           (float)minfo.pgsp_total);
    perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1);
    printf("Memory statistics\n");
    printf("-----\n");
    printf("real memory size           : %llu MB\n",
           minfo.real_total*4096/1024/1024);
    printf("reserved paging space      : %llu MB\n",minfo.pgsp_rsvd);
    printf("virtual memory size        : %llu MB\n",
           minfo.virt_total*4096/1024/1024);
    printf("number of free pages       : %llu\n",minfo.real_free);
    printf("number of pinned pages     : %llu\n",minfo.real_pinned);
    printf("number of pages in file cache : %llu\n",minfo.numperm);
    printf("total paging space pages   : %llu\n",minfo.pgsp_total);
    printf("free paging space pages    : %llu\n", minfo.pgsp_free);
    printf("used paging space          : %3.2f%%\n",
           (float)(minfo.pgsp_total-minfo.pgsp_free)*100.0/
           (float)minfo.pgsp_total);
    printf("number of paging space page ins : %llu\n",minfo.pgspins);
    printf("number of paging space page outs : %llu\n",minfo.pgspouts);
    printf("number of page ins         : %llu\n",minfo.pgins);
    printf("number of page outs        : %llu\n",minfo.pgouts);
}
```

The preceding program produces output such as the following:

```
Memory statistics
-----
real memory size           : 256 MB
reserved paging space      : 512 MB
virtual memory size        : 768 MB
number of free pages       : 32304
number of pinned pages     : 6546
number of pages in file cache : 12881
total paging space pages   : 131072
free paging space pages    : 129932
used paging space          : 0.87%
number of paging space page ins : 0
number of paging space page outs : 0
```

```

number of page ins      : 20574
number of page outs    : 92508

```

The preceding program emulates **vmstat's** behavior and also shows how **perfstat\_memory\_total** is used.

## perfstat\_disk\_total Interface

The **perfstat\_disk\_total** interface returns a **perfstat\_disk\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_disk\_total\_t** structure include:

Item	Descriptor
<b>number</b>	Number of disks
<b>size</b>	Total disk size (in MB)
<b>free</b>	Total free disk space (in MB)
<b>xfers</b>	Total transfers to and from disk (in KB)

Several other disk-related metrics, such as number of blocks read from and written to disk, are also returned. For a complete list, see the **perfstat\_disk\_total\_t** section in the [libperfstat.h](#) header file in *Files Reference*.

The following code shows an example of how **perfstat\_disk\_total** is used:

```

#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    perfstat_disk_total_t dinfo;
    int rc;
    rc = perfstat_disk_total(NULL, &dinfo, sizeof(perfstat_disk_total_t), 1);
    if (rc != 1)
    {
        perror("perfstat_disk_total");
        exit(-1);
    }
    perfstat_disk_total(NULL, &dinfo, sizeof(perfstat_disk_total_t), 1);
    printf("Total disk statistics\n");
    printf("-----\n");
    printf("number of disks      : %d\n",    dinfo.number);
    printf("total disk space     : %llu\n",  dinfo.size);
    printf("total free space     : %llu\n",  dinfo.free);
    printf("number of transfers  : %llu\n",  dinfo.xfers);
    printf("number of blocks written : %llu\n", dinfo.wblks);
    printf("number of blocks read  : %llu\n", dinfo.rblks);
}

```

This program produces output such as the following:

```

Total disk statistics
-----
number of disks      : 3
total disk space     : 4296
total free space     : 2912
number of transfers  : 77759
number of blocks written : 738016
number of blocks read  : 363120

```

The preceding program emulates **iostat's** behavior and also shows how **perfstat\_disk\_total** is used.

## perfstat\_netinterface\_total Interface

The **perfstat\_netinterface\_total** interface returns a **perfstat\_netinterface\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_netinterface\_total\_t** structure include:

Item	Descriptor
<b>number</b>	Number of network interfaces
<b>ipackets</b>	Total number of input packets received on all network interfaces
<b>opackets</b>	Total number of output packets sent on all network interfaces
<b>ierror</b>	Total number of input errors on all network interfaces
<b>oerror</b>	Total number of output errors on all network interfaces

Several other network interface-related metrics (such as number of bytes sent and received). For a complete list, see the **perfstat\_netinterface\_total\_t** section in the [libperfstat.h](#) header file in *Files Reference*.

## perfstat\_partition\_total Interface

The **perfstat\_partition\_total** interface returns a **perfstat\_partition\_total\_t** structure, which is defined in the [libperfstat.h](#) file.

Selected fields from the **perfstat\_partition\_total\_t** structure include:

Item	Descriptor
<b>purrr_coalescing</b>	PURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero
<b>spurr_coalescing</b>	SPURR cycles consumes coalescing data if the calling partition is authorized to see pool wide statistics, else set to zero
<b>type</b>	Partition type
<b>online_cpus</b>	Number of virtual processors currently allocated to the partition
<b>online_memory</b>	Amount of memory currently allocated to the partition

**Note:** Page coalescing is a transparent operation wherein the hypervisor detects duplicate pages, directs all user reads to a single copy, and reclaims duplicate physical memory pages

For a complete list, see the **perfstat\_partition\_total\_t** section in the [libperfstat.h](#) header file.

The following code shows examples of how to use the **perfstat\_partition\_total** function.

The following example demonstrates how to emulate the **lpartstat -i** command:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[])
{
    perfstat_partition_total_t pinfo;
    int rc;

    rc = perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1);
    if (rc != 1) {
        perror("Error in perfstat_partition_total");
        exit(-1);
    }
    printf("Partition Name           : %s\n", pinfo.name);
    printf("Partition Number           : %u\n", pinfo.lpar_id);
    printf("Type                       : %s\n", pinfo.type.b.shared_enabled ? "Shared" :
"Dedicated");
    printf("Mode                        : %s\n", pinfo.type.b.donate_enabled ? "Donating" :
    pinfo.type.b.capped ? "Capped" : "Uncapped");
    printf("Entitled Capacity          : %u\n", pinfo.entitled_proc_capacity);
    printf("Partition Group-ID         : %u\n", pinfo.group_id);
    printf("Shared Pool ID             : %u\n", pinfo.pool_id);
    printf("Online Virtual CPUs        : %u\n", pinfo.online_cpus);
    printf("Maximum Virtual CPUs       : %u\n", pinfo.max_cpus);
    printf("Minimum Virtual CPUs       : %u\n", pinfo.min_cpus);
}
```

```

printf("Online Memory           : %llu MB\n", pinfo.online_memory);
printf("Maximum Memory          : %llu MB\n", pinfo.max_memory);
printf("Minimum Memory           : %llu MB\n", pinfo.min_memory);
printf("Variable Capacity Weight  : %u\n", pinfo.var_proc_capacity_weight);
printf("Minimum Capacity         : %u\n", pinfo.min_proc_capacity);
printf("Maximum Capacity         : %u\n", pinfo.max_proc_capacity);
printf("Capacity Increment        : %u\n", pinfo.proc_capacity_increment);
printf("Maximum Physical CPUs in system: %u\n", pinfo.max_phys_cpus_sys);
printf("Active Physical CPUs in system: %u\n", pinfo.online_phys_cpus_sys);
printf("Active CPUs in Pool        : %u\n", pinfo.phys_cpus_pool);
printf("Unallocated Capacity       : %u\n", pinfo.unalloc_proc_capacity);
printf("Physical CPU Percentage    : %4.2f%\n",
      (double)pinfo.entitled_proc_capacity / (double)pinfo.online_cpus);
printf("Unallocated Weight       : %u\n", pinfo.unalloc_var_proc_capacity_weight);
}

```

The program displays an output that is similar to the following example output:

```

Partition Name           : perfdev10
Partition Number        : 23
Type                    : Shared
Mode                    : Capped
Entitled Capacity       : 100
Partition Group-ID      : 32791
Shared Pool ID         : 0
Online Virtual CPUs     : 2
Maximum Virtual CPUs   : 4
Minimum Virtual CPUs   : 1
Online Memory           : 4096 MB
Maximum Memory         : 8192 MB
Minimum Memory         : 2048 MB
Variable Capacity Weight : 0
Minimum Capacity       : 100
Maximum Capacity       : 400
Capacity Increment     : 1
Maximum Physical CPUs in system: 64
Active Physical CPUs in system: 64
Active CPUs in Pool    : 59
Unallocated Capacity   : 0
Physical CPU Percentage : 50.00%
Unallocated Weight     : 0

```

The following example demonstrates emulating the **lparstat** command in default mode:

```

#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <libperfstat.h>
#include <sys/systemcfg.h>

#define XINTFRAC ((double)(_system_configuration.Xint))/(double)(_system_configuration.Xfrac)
/* convert physical processor tics to seconds */
#define HTIC2SEC(x) ((double)x * XINTFRAC)/(double)100000000.0

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

/*simplelparstat.c file can be used in two modes:-
1) Auto Mode:It makes use of perfstat_cpu_util API to calculate utilization values,enable 'UTIL_AUTO' macro for execution in auto mode.
2) Manual Mode: Calculations are done in the current code.
*/

/*#define UTIL_AUTO 1*/

#ifdef UTIL_AUTO
#define UTIL_MS 1
#define UTIL_PCT 0
#define UTIL_CORE 2
#define UTIL_PURR 0
#define UTIL_SPURR 1
void display_lpar_util_auto(int mode,int cpumode,int count,int interval);
#endif

static int disp_util_header = 1;
static u_longlong_t last_time_base;
static u_longlong_t last_pcpu_user, last_pcpu_sys, last_pcpu_idle, last_pcpu_wait;
static u_longlong_t last_lcpu_user, last_lcpu_sys, last_lcpu_idle, last_lcpu_wait;
static u_longlong_t last_busy_donated, last_idle_donated;
static u_longlong_t last_busy_stolen, last_idle_stolen;
static u_longlong_t last_phint = 0, last_vcsw = 0, last_pit = 0;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

void display_lpar_util(void);

int main(int argc, char* argv[])
{
    int interval = INTERVAL_DEFAULT;

```

```

int count = COUNT_DEFAULT;
int i, rc;
char *optlist = "i:c:n:";
int mode=0, cpumode=0;

/* Process the arguments */
while ((i = getopt(argc, argv, optlist)) != EOF)
{
    switch(i)
    {
        case 'i':
            /* Interval */
            interval = atoi(optarg);
            if( interval <= 0 )
                interval = INTERVAL_DEFAULT;
            break;
        case 'c':
            /* Number of iterations */
            count = atoi(optarg);
            if( count <= 0 )
                count = COUNT_DEFAULT;
            break;
        case 'n':
            /* Node name in a cluster environment */
            strncpy(nodename, optarg, MAXHOSTNAMELEN);
            nodename[MAXHOSTNAMELEN-1] = '\0';
            collect_remote_node_stats = 1;
            break;
        default:
            /* Invalid arguments. Print the usage and terminate */
            fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ]
\n", argv[0]);
            return(-1);
    }
}

if(collect_remote_node_stats)
{
    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}

#ifdef UTIL_AUTO
printf("Enter CPU mode.\n");
printf(" 0 PURR \n 1 SPURR \n");
scanf("%d",&cpumode);
printf("Enter print mode.\n");
printf(" 0 PERCENTAGE\n 1 MILLISECONDS\n 2 CORES \n");
scanf("%d",&mode);

if((mode>2)&& (cpumode>1))
{
    printf("Error: Invalid Input\n");
    exit(0);
}
display_lpar_util_auto(mode, cpumode, count, interval);
#else
/* Iterate "count" times */
while (count > 0)
{
    display_lpar_util();
    sleep(interval);
    count--;
}
#endif

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}

return(0);
}

/* Save the current values for the next iteration */
void save_last_values(perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    last_vcswh = lparstats->vol_virt_cswitch + lparstats->invol_virt_cswitch;
    last_time_base = lparstats->timebase_last;
    last_phint = lparstats->phantintrs;
    last_pit = lparstats->pool_idle_time;

    last_pcpu_user = lparstats->puser;
    last_pcpu_sys = lparstats->psys;
    last_pcpu_idle = lparstats->pidle;
    last_pcpu_wait = lparstats->pwait;

    last_lcpu_user = cpustats->user;
    last_lcpu_sys = cpustats->sys;
    last_lcpu_idle = cpustats->idle;
    last_lcpu_wait = cpustats->wait;

    last_busy_donated = lparstats->busy_donated_purr;
    last_idle_donated = lparstats->idle_donated_purr;

    last_busy_stolen = lparstats->busy_stolen_purr;
    last_idle_stolen = lparstats->idle_stolen_purr;
}

/* retrieve metrics using perfstat API */
void collect_metrics (perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    if (collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
    }
}

```

```

nodeid.spec = NODENAME;

if (perfstat_partition_total_node(&nodeid, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
    perror("perfstat_partition_total_node");
    exit(-1);
}
if (perfstat_cpu_total_node(&nodeid, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
    perror("perfstat_cpu_total_node");
    exit(-1);
}
}
else
{
    if (perfstat_partition_total(NULL, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
        perror("perfstat_partition_total");
        exit(-1);
    }

    if (perfstat_cpu_total(NULL, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
        perror("perfstat_cpu_total");
        exit(-1);
    }
}
}

/* print header informations */
void print_header(perfstat_partition_total_t *lparstats)
{
    if (lparstats->type.b.shared_enabled) { /* partition is a SPLPAR */
        if (lparstats->type.b.pool_util_authority) { /* partition has PUA access */
            printf("\n%5s %5s %6s %6s %5s %5s %5s %5s %4s %5s",
                "user", "sys", "%wait", "idle", "phyc", "%entc", "lbusy", "app", "vcsw", "phint");

            printf("\n%5s %5s %6s %6s %5s %5s %5s %5s %4s %5s",
                "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----");
        } else {
            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "user", "sys", "%wait", "idle", "phyc", "%entc", "lbusy", "vcsw", "phint");

            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----");
        }
    } else { /* partition is a DLPAR */
        printf("\n%5s %5s %6s %6s", "%user", "%sys", "%wait", "%idle");
        printf("\n%5s %5s %6s %6s", "-----", "-----", "-----", "-----");
        if (lparstats->type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
            printf(" %6s %6s", "%phyc", "%vcsw");
            printf(" %6s %6s", "-----", "-----");
        }
    }
}
fprintf(stdout, "\n");
}

/* Gather and display lpar utilization metrics */
void display_lpar_util(void)
{
    u_longlong_t delta_pcpu_user, delta_pcpu_sys, delta_pcpu_idle, delta_pcpu_wait;
    u_longlong_t delta_lcpu_user, delta_lcpu_sys, delta_lcpu_idle, delta_lcpu_wait;
    u_longlong_t delta_busy_stolen, delta_busy_donated, delta_idle_stolen, delta_idle_donated;
    u_longlong_t vcsw, lcputime, pcputime;
    u_longlong_t entitled_purr, unused_purr;
    u_longlong_t delta_purr, delta_time_base;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    perfstat_cpu_total_t cpustats;

    /* retrieve the metrics */
    collect_metrics (&cpustats, &lparstats);

    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
        print_header (&lparstats);

        disp_util_header = 0;

        /* first iteration, we only read the data, print the header and save the data */
        save_last_values(&cpustats, &lparstats);
        return;
    }

    /* calculate physical processor tics during the last interval in user, system, idle and wait mode */
    delta_pcpu_user = lparstats.puser - last_pcpu_user;
    delta_pcpu_sys = lparstats.psys - last_pcpu_sys;
    delta_pcpu_idle = lparstats.pidle - last_pcpu_idle;
    delta_pcpu_wait = lparstats.pwait - last_pcpu_wait;

    /* calculate total physical processor tics during the last interval */
    delta_purr = pcputime = delta_pcpu_user + delta_pcpu_sys + delta_pcpu_idle + delta_pcpu_wait;

    /* calculate clock tics during the last interval in user, system, idle and wait mode */
    delta_lcpu_user = cpustats.user - last_lcpu_user;
    delta_lcpu_sys = cpustats.sys - last_lcpu_sys;
    delta_lcpu_idle = cpustats.idle - last_lcpu_idle;
    delta_lcpu_wait = cpustats.wait - last_lcpu_wait;

    /* calculate total clock tics during the last interval */
    lcputime = delta_lcpu_user + delta_lcpu_sys + delta_lcpu_idle + delta_lcpu_wait;

    /* calculate entitlement for this partition - entitled physical processors for this partition */
    entitlement = (double)lparstats.entitled_proc_capacity / 100.0 ;

    /* calculate delta time in terms of physical processor tics */
    delta_time_base = lparstats.timebase_last - last_time_base;

    if (lparstats.type.b.shared_enabled) { /* partition is a SPLPAR */
        /* calculate entitled physical processor tics for this partitions */
        entitled_purr = delta_time_base * entitlement;
        if (entitled_purr < delta_purr) { /* for uncapped SPLPAR */
            /* in case of uncapped SPLPAR, consider entitled physical processor tics or

```

```

        * consumed physical processor tics, which ever is greater */
        entitled_purr = delta_purr;
    }
    /* calculate unused physical processor tics out of the entitled physical processor tics */
    unused_purr = entitled_purr - delta_purr;

    /* distributed unused physical processor tics among wait and idle proportionally to wait and idle in clock tics */
    delta_pcpu_wait += unused_purr * ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
    delta_pcpu_idle += unused_purr * ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

    /* for SPLPAR, consider the entitled physical processor tics as the actual delta physical processor tics */
    pcpptime = entitled_purr;
}
else if (lparstats.type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
    /* calculate busy stolen and idle stolen physical processor tics during the last interval */
    /* these physical processor tics are stolen from this partition by the hypervisor
    * which will be used by wanting partitions */
    delta_busy_stolen = lparstats.busy_stolen_purr - last_busy_stolen;
    delta_idle_stolen = lparstats.idle_stolen_purr - last_idle_stolen;

    /* calculate busy donated and idle donated physical processor tics during the last interval */
    /* these physical processor tics are voluntarily donated by this partition to the hypervisor
    * which will be used by wanting partitions */
    delta_busy_donated = lparstats.busy_donated_purr - last_busy_donated;
    delta_idle_donated = lparstats.idle_donated_purr - last_idle_donated;

    /* add busy donated and busy stolen to the kernel bucket, as cpu
    * cycles were donated / stolen when this partition is busy */
    delta_pcpu_sys += delta_busy_donated;
    delta_pcpu_sys += delta_busy_stolen;

    /* distribute idle stolen to wait and idle proportionally to the logical wait and idle in clock tics, as
    * cpu cycles were stolen when this partition is idle or in wait */
    delta_pcpu_wait += delta_idle_stolen *
        ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
    delta_pcpu_idle += delta_idle_stolen *
        ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

    /* distribute idle donated to wait and idle proportionally to the logical wait and idle in clock tics, as
    * cpu cycles were donated when this partition is idle or in wait */
    delta_pcpu_wait += delta_idle_donated *
        ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
    delta_pcpu_idle += delta_idle_donated *
        ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

    /* add donated to the total physical processor tics for CPU usage calculation, as they were
    * distributed to respective buckets accordingly */
    pcpptime += (delta_idle_donated + delta_busy_donated);

    /* add stolen to the total physical processor tics for CPU usage calculation, as they were
    * distributed to respective buckets accordingly */
    pcpptime += (delta_idle_stolen + delta_busy_stolen);
}

/* Processor Utilization - Applies for both SPLPAR and DLPAR*/
printf("%5.1f ", (double)delta_pcpu_user * 100.0 / (double)pcpptime);
printf("%5.1f ", (double)delta_pcpu_sys * 100.0 / (double)pcpptime);
printf("%6.1f ", (double)delta_pcpu_wait * 100.0 / (double)pcpptime);
printf("%6.1f ", (double)delta_pcpu_idle * 100.0 / (double)pcpptime);

if (lparstats.type.b.shared_enabled) { /* print SPLPAR specific stats */
    /* Physical Processor Consumed by this partition */
    phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
    printf("%5.2f ", (double)phys_proc_consumed);

    /* Percentage of Entitlement Consumed - percentage of entitled physical processor tics consumed */
    percent_ent = (double)((phys_proc_consumed / entitlement) * 100);
    printf("%5.1f ", percent_ent);

    /* Logical Processor Utilization of this partition */
    printf("%5.1f ", (double)(delta_lcpu_user+delta_lcpu_sys) * 100.0 / (double)lcpptime);

    if (lparstats.type.b.pool_util_authority) {
        /* Available physical Processor units available in the shared pool (app) */
        printf("%5.2f ", (double)(lparstats.pool_idle_time - last_pit) /
            XINTFRAC*(double)delta_time_base);
    }

    /* Virtual CPU Context Switches per second */
    vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
    delta_sec = HTIC2SEC(delta_time_base);
    printf("%4.0f ", (double)(vcsw - last_vcsw) / delta_sec);

    /* Phantom Interrupts per second */
    printf("%5.0f", (double)(lparstats.phantintrs - last_phint) / delta_sec);
}
else if (lparstats.type.b.donate_enabled) { /* print donation-enabled DLPAR specific stats */
    /* Physical Processor Consumed by this partition
    * (excluding donated and stolen physical processor tics). */
    phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
    printf("%5.2f ", (double)phys_proc_consumed);

    /* Virtual CPU Context Switches per second */
    vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
    delta_sec = HTIC2SEC(delta_time_base);
    printf("%5.0f ", (double)(vcsw - last_vcsw) / delta_sec);
}
printf("\n");

save_last_values(&cpustats, &lparstats);
}

#ifdef UTIL_AUTO
void display_lpar_util_auto(int mode,int cpumode,int count,int interval)
{
    float user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr;
    float user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,sum_core_spurr;
}
#endif

```

```

u_longlong_t user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,sum_ms;
u_longlong_t user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr;
perfstat_rawdata_t data;
u_longlong_t delta_time_purr, delta_time_base;
double phys_proc_consumed, entitlement, percent_ent, delta_sec;
perfstat_partition_total_t lparstats;
static perfstat_cpu_total_t oldt,newt;
perfstat_cpu_util_t util;
int rc;

/* retrieve the metrics */

/* Print the header for utilization metrics (only once) */
if (disp_util_header) {
if(mode==UTIL_PCT)
printf("\n%5s %5s %6s %6s %5s \n",
"user", "sys", "wait", "idle", "physc");
else if(mode==UTIL_MS)
printf("\n%5s %5s %6s %6s %5s \n",
"user(ms)", "sys(ms)", "wait(ms)", "idle(ms)", "physc");
else if(mode==UTIL_CORE)
printf("\n%5s %5s %6s %6s %5s \n",
"user", "sys", "wait", "idle", "physc");

disp_util_header = 0;
}

/* first iteration, we only read the data, print the header and save the data */
}

while(count)
{
collect_metrics (&oldt, &lparstats);
sleep(interval);
collect_metrics (&newt, &lparstats);

data.type = UTIL_CPU_TOTAL;
data.curstat = &newt; data.prevstat= &oldt;
data.sizeof_data = sizeof(perfstat_cpu_total_t);
data.cur_elems = 1;
data.prev_elems = 1;
rc = perfstat_cpu_util(&data, &util,sizeof(perfstat_cpu_util_t), 1);
if(rc <= 0)
{
perror("Error in perfstat_cpu_util");
exit(-1);
}
delta_time_base = util.delta_time;

switch(mode)
{
case UTIL_PCT:
printf(" %5.1f %5.1f %5.1f %5.1f %5.4f \n",util.user_pct,util.kern_pct,util.wait_pct,util.idle_pct,util.physical_consumed);
break;

case UTIL_MS:
user_ms_purr=((util.user_pct*delta_time_base)/100.0);
kern_ms_purr=((util.kern_pct*delta_time_base)/100.0);
wait_ms_purr=((util.wait_pct*delta_time_base)/100.0);
idle_ms_purr=((util.idle_pct*delta_time_base)/100.0);

if(cpumode==UTIL_PURR)
{
printf(" %11u %11u %11u %11u %5.4f\n",user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,util.physical_consumed);
}
else if(cpumode==UTIL_SPURR)
{
user_ms_spurr=(user_ms_purr*util.freq_pct)/100.0;
kern_ms_spurr=(kern_ms_purr*util.freq_pct)/100.0;
wait_ms_spurr=(wait_ms_purr*util.freq_pct)/100.0;
sum_ms=user_ms_spurr+kern_ms_spurr+wait_ms_spurr;
idle_ms_spurr=delta_time_base-sum_ms;

printf(" %11u %11u %11u %11u %5.4f\n",user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr,util.physical_consumed);
}
break;

case UTIL_CORE:

user_core_purr=((util.user_pct*util.physical_consumed)/100.0);
kern_core_purr=((util.kern_pct*util.physical_consumed)/100.0);
wait_core_purr=((util.wait_pct*util.physical_consumed)/100.0);
idle_core_purr=((util.idle_pct*util.physical_consumed)/100.0);

user_core_spurr=((user_core_purr*util.freq_pct)/100.0);
kern_core_spurr=((kern_core_purr*util.freq_pct)/100.0);
wait_core_spurr=((wait_core_purr*util.freq_pct)/100.0);

if(cpumode==UTIL_PURR)
{
printf("%5.4f %5.4f %5.4f %5.4f\n",user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr,util.physical_consumed);
}
else if(cpumode==UTIL_SPURR)
{
sum_core_spurr=user_core_spurr+kern_core_spurr+wait_core_spurr;
idle_core_spurr=util.physical_consumed-sum_core_spurr;

printf("%5.4f %5.4f %5.4f %5.4f %5.4f\n",user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,util.physical_consumed);
}
break;

default:
printf("In correct usage\n");
}
}

```

```

return;
}
count--;
}
#endif

```

The program displays an output that is similar to the following example output:

```

%user  %sys  %wait  %idle  physc  %entc  lbusy  vcsw  phint
-----
 0.1   0.4   0.0   99.5   0.01   1.2   0.2   278   0
 0.0   0.3   0.0   99.7   0.01   0.8   0.2   271   0
 0.0   0.2   0.0   99.8   0.01   0.5   0.1   180   0
 0.0   0.2   0.0   99.8   0.01   0.6   0.1   184   0
 0.0   0.2   0.0   99.7   0.01   0.6   0.1   181   0
 0.0   0.2   0.0   99.8   0.01   0.6   0.1   198   0
 0.0   0.2   0.0   99.8   0.01   0.7   0.2   189   0
 2.1   3.3   0.0   94.6   0.09   8.7   2.1   216   0
 0.0   0.2   0.0   99.8   0.01   0.7   0.1   265   0

```

## perfstat\_tape\_total Interface

The **perfstat\_tape\_total** interface returns a **perfstat\_tape\_total\_t** structure, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_tape\_total\_t** structure include:

Item	Descriptor
<b>number</b>	Total number of tapes
<b>size</b>	Total size of all tapes(in MB)
<b>free</b>	Total free portion of all tapes (in MB)
<b>rxfers</b>	Total number of read transfers from/to tape
<b>xfers</b>	Total number of transfers from/to tape

Several other tape-related metrics (such as number of bytes sent and received). For a complete list, see the **perfstat\_tape\_total** section in the [libperfstat.h](#) header file.

The following code shows examples of how to use the **perfstat\_tape\_total** function.

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_tape_total_t *tinfo;
    int rc,i;

    rc = perfstat_tape_total(NULL, NULL, sizeof(perfstat_tape_total_t), 0);
    if(rc<=0){
        perror("perfstat_tape_total");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    tinfo = calloc(rc, sizeof(perfstat_tape_t));
    if(tinfo==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    rc = perfstat_tape_total(NULL, tinfo, sizeof(perfstat_tape_total_t), rc);
    if (rc < 0)
    {
        perror("perfstat_tape_total");
        exit(-1);
    }

    if(rc==0){
        printf("No tape found on the system\n");
        exit(-1);
    }
}

```

```

for(i=0;i<rc;i++){
    printf("Total number of tapes=%d\n",tinfo[i].number);
    printf("Total size of all tapes (in MB)=%lld\n",tinfo[i].size);
    printf("Free portion of all tapes(in MB)=%lld\n",tinfo[i].free);
    printf("Number of read transfers to/from tape=%lld\n",tinfo[i].xfers);
    printf("Total number of transfers to/from tape=%lld\n",tinfo[i].xfers);
    printf("Blocks written to all tapes=%lld\n",tinfo[i].wblks);
    printf("Blocks read from all tapes=%lld\n",tinfo[i].rblks);
    printf("Amount of time tapes are active=%lld\n",tinfo[i].time);
}
return(0);
}

```

The preceding program emulates **diskstat** behavior and also shows how **perfstat\_tape\_total** is used.

## perfstat\_partition\_config interface

The `perfstat_partition_config` interface returns a `perfstat_partition_config_t` structure, which is defined in the `libperfstat.h` file.

The selected fields from the `perfstat_partition_config_t` structure include:

Item	Descriptor
<b>partitionname</b>	Partition name
<b>processorFamily</b>	Processor type
<b>processorModel</b>	Processor model
<b>machineID</b>	Machine ID
<b>processorMHz</b>	Processor clock speed in megahertz
<b>numProcessors</b>	Number of configured physical processors in frame
<b>OSName</b>	Name of operating system
<b>OSVersion</b>	Version of operating system
<b>OSBuild</b>	Build of operating system
<b>lcpus</b>	Number of logical CPUs
<b>smtthreads</b>	Number of SMT threads
<b>drives</b>	Total number of drives
<b>nw_adapters</b>	Total number of network adapters
<b>vcpus</b>	Minimum, maximum, and online virtual CPUs
<b>cpucap</b>	Minimum, maximum, and online CPU capacity
<b>entitled_proc_capacity</b>	Number of processor units that this partition is entitled to receive
<b>cpucap_weightage</b>	Variable processor capacity weightage
<b>mem_weightage</b>	Variable memory capacity weightage
<b>cpupool_weightage</b>	Pool weightage
<b>activecpusinpool</b>	Count of physical CPUs in the shared processor pool to which the partition belongs
<b>sharedpcpu</b>	Number of physical processors allocated for the use of the shared processor
<b>maxpoolcap</b>	Maximum processor capacity of partition's pool
<b>entpoolcap</b>	Entitled processor capacity of partition's pool

Item	Descriptor
<b>mem</b>	Minimum, maximum, and online memory
<b>totiomement</b>	I/O memory entitlement of the partition in bytes
<b>mempoolid</b>	AMS pool ID of the pool to which the logical partition (LPAR) belongs
<b>hyperpgsize</b>	Hypervisor page size in kilobytes
<b>exp_mem</b>	Minimum, maximum, and online expanded memory
<b>targetmemexpfactor</b>	Target memory expansion factor scaled by 100
<b>targetmemexpsize</b>	Expanded memory size in megabytes
<b>Subprocessormode</b>	Subprocessor mode for the partition

For a complete list, see the `perfstat_partition_config_t` section in the `libperfstat.h` header file.

The usage of the code for the `perfstat_partition_config` API is as follows:

```
#include <libperfstat.h>

int main(int argc, char *argv[])
{
    perfstat_partition_config_t pinfo;
    int rc;

    rc = perfstat_partition_config(NULL, &pinfo, sizeof(perfstat_partition_config_t), 1);
    if(rc != 1)
    {
        perror("Error in perfstat_partition_config");
        exit(-1);
    }
    printf("====Configuration Information of Partition====\n");
    printf("Partition Name = %s\n", pinfo.partitionname);
    printf("Node Name = %s\n", pinfo.nodename);
    printf("Partition Number = %u\n", pinfo.partitionnum);
    printf("Group ID = %u\n", pinfo.groupid);
    printf("\n\n====General Partition Properties(1=YES, 0=NO)====\n");
    printf("SMT Capable = %u\n", pinfo.conf.b.smt_capable);
    /* 1, if OS supports SMT mode */
    printf("SMT Enabled = %u\n", pinfo.conf.b.smt_enabled);
    /* 1, if SMT mode is on */
    printf("LPAR Capable = %u\n", pinfo.conf.b.lpar_capable);
    /* 1, if OS supports logical partitioning */
    printf("LPAR Enabled = %u\n", pinfo.conf.b.lpar_enabled);
    /* 1, if logical partitioning is on */
    printf("Shared Capable = %u\n", pinfo.conf.b.shared_capable);
    /* 1, if OS supports shared processor LPAR */
    printf("Shared Enabled = %u\n", pinfo.conf.b.shared_enabled);
    /* 1, if partition runs in shared mode */
    printf("DLPAR Capable = %u\n", pinfo.conf.b.dlpar_capable);
    /* 1, if OS supports dynamic LPAR */
    printf("Capped = %u\n", pinfo.conf.b.capped);
    /* 1, if partition is capped */
    printf("64-Bit Kernel = %u\n", pinfo.conf.b.kernel_is_64);
    /* 1, if kernel is 64 bit */
    printf("Pool Util Authority = %u\n", pinfo.conf.b.pool_util_authority);
    /* 1, if pool utilization available */
    printf("Donate Capable = %u\n", pinfo.conf.b.donate_capable);
    /* 1, if capable of donating cycles */
    printf("Donate Enabled = %u\n", pinfo.conf.b.donate_enabled);
    /* 1, if capable of donating cycles */
    printf("AMS Capable = %u\n", pinfo.conf.b.ams_capable);
    /* 1, if AMS(Active Memory Sharing) capable */
    printf("AMS Enabled = %u\n", pinfo.conf.b.ams_enabled);
    /* 1, if AMS(Active Memory Sharing) enabled */
    printf("Power Saving Mode = %u\n", pinfo.conf.b.power_save);
    /* 1, if Power saving mode is enabled */
    printf("AME Enabled = %u\n", pinfo.conf.b.ame_enabled);
    /* 1, if Active Memory Expansion is enabled */
    printf("Shared Extended = %u\n", pinfo.conf.b.shared_extended);
    /* 1, if Shared Extended */
    printf("\n\n====Hardware Configuration====\n");
    printf("Processor Type = %s\n", pinfo.processorFamily);
    printf("Processor Model = %s\n", pinfo.processorModel);
}
```

```

printf("Machine ID = %s\n",pinfo.machineID);
printf("Processor Clock Speed = %lf MHz\n",pinfo.processorMHz);
printf("Online Configured Processors = %lld\n",pinfo.numProcessors.online);
printf("Max Configured Processors = %lld\n",pinfo.numProcessors.max);
printf("\n\n=====Software Configuration=====\n");
printf("OS Name = %s\n",pinfo.OSName);
printf("OS Version = %s\n",pinfo.OSVersion);
printf("OS Build = %s\n",pinfo.OSBuild);
printf("\n\n=====LPAR Configuration=====\n");
printf("Number of Logical CPUs = %u\n",pinfo.lcpus);
printf("Number of SMT Threads = %u\n",pinfo.smtthreads);
printf("Number of Drives = %u\n",pinfo.drives);
printf("Number of NW Adapters = %u\n",pinfo.nw_adapters);
printf("\n\n=====Physical CPU Related Configuration=====\n");
printf("Minimum CPU Capacity = %.2f\n", (float)pinfo.cpuscap.min/100.0);
printf("Maximum CPU Capacity = %.2f\n", (float)pinfo.cpuscap.max/100.0);
printf("CPU Capacity Weightage = %u\n",pinfo.cpuscap_weightage);
printf("Entitled Proc Capacity = %.2f\n",pinfo.entitled_proc_capacity/100.0);
printf("\n\n=====Virtual CPU Related Configuration=====\n");
printf("Minimum Virtual CPUs = %lld\n",pinfo.vcpus.min);
printf("Maximum Virtual CPUs = %lld\n",pinfo.vcpus.max);
printf("Online Virtual CPUs = %lld\n",pinfo.vcpus.online);
printf("\n\n=====Processor Pool Related Configuration=====\n");
printf("Processor Pool Id = %u\n",pinfo.processor_poolid);
printf("Active CPUs in pool = %u\n",pinfo.activecpusinpool);
printf("Pool Weightage = %u\n",pinfo.cpuspool_weightage);
printf("Shared processors Count = %u\n",pinfo.sharedpcpu);
printf("Max pool Capacity = %u\n",pinfo.maxpoolcap);
printf("Entitled pool Capacity = %u\n",pinfo.entpoolcap);
printf("\n\n=====Memory Related Configuration=====\n");
printf("Minimum Memory = %lld\n",pinfo.mem.min);
printf("Maximum memory = %lld\n",pinfo.mem.max);
printf("Online memory = %lld\n",pinfo.mem.online);
printf("Memory capacity Weightage = %u\n",pinfo.mem_weightage);
printf("\n\n=====AMS Related Configuration=====\n");
printf("I/O memory Entitlement = %lld\n",pinfo.totiomement);
printf("AMS Pool ID = %d\n",pinfo.mempoolid);
printf("Hypervisor Page Size = %f\n",pinfo.hyperpgsize);
printf("\n\n=====AME Related Configuration=====\n");
printf("Minimum Expanded memory = %lld\n",pinfo.exp_mem.min);
printf("Maximum Expanded Memory = %lld\n",pinfo.exp_mem.max);
printf("Online Expanded memory = %lld\n",pinfo.exp_mem.online);
printf("Target memory Expansion factor = %lld\n",pinfo.targetmemexpfactor);
printf("Target Memory Expansion Size = %lld\n",pinfo.targetmemexpsize);
printf("\n\n=====");
}

```

The output of the program is as follows:

```

=====Configuration Information of Partition=====
Partition Name = clock15
Node Name = clock15
Partition Number = 9
Group ID = 0

=====General Partition Properties(1=YES, 0=NO)=====
SMT Capable = 1
SMT Enabled = 1
LPAR Capable = 1
LPAR Enabled = 1
Shared Capable = 1
Shared Enabled = 1
DLPAR Capable = 1
Capped = 0
64-Bit Kernel = 1
Pool Util Authority = 0
Donate Capable = 0
Donate Enabled = 0
AMS Capable = 0
AMS Enabled = 0
Power Saving Mode = 1
AME Enabled = 0
Shared Extended = 0

=====Hardware Configuration=====
Processor Type = POWER_5
Processor Model = IBM,9133-55A
Machine ID = 061500H

```

```
Processor Clock Speed = 1648.350000 MHz
Online Configured Processors = 8
Max Configured Processors = 8
```

```
=====Software Configuration=====
```

```
OS Name = AIX
OS Version = 7.1
OS Build = Feb 17 2011 15:57:15 1107A_71D
```

```
=====LPAR Configuration=====
```

```
Number of Logical CPUs = 2
Number of SMT Threads = 2
Number of Drives = 2
Number of NW Adapters = 2
```

```
=====Physical CPU Related Configuration=====
```

```
Minimum CPU Capacity = 0.10
Maximum CPU Capacity = 8.00
CPU Capacity Weightage = 128
Entitled Proc Capacity = 0.75
```

```
=====Virtual CPU Related Configuration=====
```

```
Minimum Virtual CPUs = 1
Maximum Virtual CPUs = 8
Online Virtual CPUs = 1
```

```
=====Processor Pool Related Configuration=====
```

```
Processor Pool Id = 0
Active CPUs in pool = 3
Pool Weightage = 128
Shared processors Count = 0
Max pool Capacity = 0
Entitled pool Capacity = 0
```

```
=====Memory Related Configuration=====
```

```
Minimum Memory = 256
Maximum memory = 4096
Online memory = 2048
Memory capacity Weightage = 0
```

```
=====AMS Related Configuration=====
```

```
I/O memory Entitlement = 0
AMS Pool ID = 0
Hypervisor Page Size = 0.000000
```

```
=====AME Related Configuration=====
```

```
Minimum Expanded memory = 0
Maximum Expanded Memory = 0
Online Expanded memory = 0
Target memory Expansion factor = 0
Target Memory Expansion Size = 0
=====
```

## bindid\_to\_lcpuid Subroutine

### Purpose

Returns the logical CPU ID.

### Library

```
perfstat library (libperfstat.a)
```

## Syntax

```
#include <libperfstat.h>
cpu_t bindid_to_lcpuid (id)
cpu_t id;
```

## Description

The **bindid\_to\_lcpuid** subroutine returns the logical CPU identifier of the bind CPU identifier. This subroutine is defined in the `libperfstat.h` file.

## Parameters

Item	Description
<b>id</b>	Specifies the bind CPU identifier that needs to be converted into the logical CPU ID.

## Return values

Upon successful completion, the logical CPU ID is returned. If unsuccessful, a value of -1 is returned and the **errno** parameter is set to the appropriate error code.

## Error codes

Error	Description
<b>EINVAL</b>	One of the parameters is not valid.

## lcpuid\_to\_bindid Subroutine

### Purpose

Returns the bind CPU ID.

### Library

```
perfstat library (libperfstat.a)
```

## Syntax

```
#include <libperfstat.h>
cpu_t lcpuid_to_bindid (id)
cpu_t id;
```

## Description

The **lcpuid\_to\_bindid** subroutine returns the bind CPU identifier of the logical CPU identifier. This subroutine is defined in the `libperfstat.h` file.

## Parameters

Item	Description
<b>id</b>	Specifies the logical CPU identifier that needs to be converted into the bind CPU identifier.

## Return values

Upon successful completion, the bind CPU ID is returned. If unsuccessful, a value of -1 is returned and the `errno` parameter is set to the appropriate error code.

## Error codes

Error	Description
<b>EINVAL</b>	One of the parameters is not valid.

## Component-Specific interfaces

Component-specific interfaces report metrics related to individual components on a system (such as a processor, disk, network interface, or paging space).

All of the following AIX interfaces use the naming convention **perfstat\_subsystem**, and use a common signature:

Item	Descriptor
<b>perfstat_cpu</b>	Retrieves individual processor usage metrics <b>Note:</b> This interface returns global values when called by an application running inside WPAR.
<b>perfstat_disk</b>	Retrieves individual disk usage metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR
<b>perfstat_diskpath</b>	Retrieves individual disk path metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR
<b>perfstat_diskadapter</b>	Retrieves individual disk adapter metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR.
<b>perfstat_netinterface</b>	Retrieves individual network interfaces metrics <b>Note:</b> This interface returns WPAR-specific data when called by an application running inside WPAR.
<b>perfstat_protocol</b>	Retrieves individual network protocol-related metrics <b>Note:</b> This interface returns WPAR-specific data when called by an application running inside WPAR.
<b>perfstat_netbuffer</b>	Retrieves individual network buffer allocation metrics <b>Note:</b> This interface returns WPAR-specific data when called by an application running inside WPAR.
<b>perfstat_pagingpace</b>	Retrieves individual paging space metrics <b>Note:</b> This interface does not return any data when called by an application running inside WPAR.
<b>perfstat_memory_page</b>	Retrieves multiple page size usage metrics <b>Note:</b> This interface returns global values when it is called by an application running inside a WPAR.

Item	Descriptor
<b>perfstat_tape</b>	Retrieves individual tape usage metrics <b>Note:</b> This interface does not return any data when it is called by an application running inside a WPAR.
<b>perfstat_logicalvolume</b>	Retrieves individual logical volume usage metrics <b>Note:</b> This interface does not return any data when called it is by an application running inside a WPAR.
<b>perfstat_volume</b>	Retrieves individual volume group usage metrics <b>Note:</b> This interface does not return any data when it is called by an application running inside a WPAR.
<b>perfstat_hfistat</b>	Retrieves individual host fabric interface (HFI) statistics.
<b>perfstat_hfistat_window</b>	Retrieves individual window-based HFI statistics.
<b>perfstat_cpu_util</b>	Calculates CPU utilization
<b>perfstat_process</b>	Retrieves process utilization metrics
<b>perfstat_process_util</b>	Calculates process utilization metrics
<b>perfstat_thread</b>	Retrieves kernel thread utilization metrics
<b>perfstat_thread_util</b>	Calculates kernel thread utilization metrics

The common signature used by all the component interfaces except `perfstat_memory_page` and `perfstat_hfistat_window` is as follows:

```
int perfstat_subsystem(perfstat_id *name,
                     perfstat_subsystem_t * userbuff,
                     int sizeof_struct,
                     int desired_number);
```

The `perfstat_memory_page` uses the following signature:

```
int perfstat_memory_page(perfstat_psize_t *psize ,
                        perfstat_subsystem_t * userbuff,
                        int sizeof_struct,
                        int desired_number);
```

The `perfstat_hfistat_window` uses the following signature:

```
int perfstat_hfistat_window(perfstat_id_window_t *name,
                           perfstat_hfistat_window_t *userbuff,
                           int sizeof_struct,
                           int desired_number);
```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<b>perfstat_id_t *name</b>	Enter the name of the first component (for example <b>hdisk2</b> for <b>perfstat_disk()</b> ) to obtain the statistics. A structure containing a <code>char *</code> field is used instead of directly passing a <code>char *</code> argument to the function to avoid allocation errors and to prevent the user from giving a constant string as parameter. To start from the first component of a subsystem, set the <code>char*</code> field of the name parameter to "" (empty string). You can use macros such as <b>FIRST_SUBSYSTEM</b> (for example, <b>FIRST_CPU</b> ) defined in the <b>libperfstat.h</b> file.

Item	Descriptor
<b>perfstat_id_window_t *name</b>	Enter the Host Fabric Interface name (for example, hfi0 or hfi1 or FIRST_HFI) in the "name->name" field, and the HFI window number in "name->windowid" field.
<b>perfstat_subsystem_t *userbuff</b>	Specifies a pointer to a memory area with enough space for the returned structures.
<b>int sizeof_struct</b>	Set the parameter to <b>sizeof(perfstat_subsystem_t)</b> .
<b>int desired_number</b>	Specifies the number of structures of type <b>perfstat_subsystem_t</b> to return in userbuff.

The return value is -1 in case of error. Otherwise, the number of structures copied is returned. The field name is either set to NULL or to the name of the next structure available.

An exception to this scheme is when **name=NULL**, **userbuff=NULL** and **desired\_number=0**, the total number of structures available is returned.

To retrieve all structures of a given type, find the number of structures and allocate the required memory to hold the structures. You must then call the appropriate API to retrieve all structures in one call. Another method is to allocate a fixed set of structures and repeatedly call the API to get the next set of structures, each time passing the name returned by the previous call. Start the process with the name set to "" or **FIRST\_SUBSYSTEM**, and repeat the process.

Minimizing the number of API calls, and the number of system calls, leads to more efficient code, so the two-call approach is preferred. Some of the examples shown in the following sections illustrate the API usage using the two-call approach. The two-call approach causes large amount of memory allocation, the multiple-call approach is sometimes used, and is illustrated in the following examples.

The following sections provide examples of the type of data returned and the code used for each of the interfaces.

## perfstat\_bio\_stats interface

The **perfstat\_bio\_stats** interface returns a set of structures of type **perfstat\_bio\_dev\_t**, which is defined in the **libperfstat.h** file. The API is successful only if the **biostat** tunable is set to 1. To set the **biostat** tunable to 1, you must input the following command, `raso -o biostat=1`.

Selected fields from the **perfstat\_bio\_dev\_t** structure include:

Item	Descriptor
<b>name</b>	Device name
<b>devid</b>	64-bit device ID
<b>rbytes</b>	Number of bytes read
<b>wbytes</b>	Number of bytes written
<b>rerrs</b>	Number of read errors
<b>werrs</b>	Number of write errors
<b>rtime</b>	Aggregate time for reads
<b>wtime</b>	Aggregate time for writes
<b>nread</b>	Number of reads
<b>nwrite</b>	Number of writes

Item	Descriptor
<b>dev_status</b>	Status of the device
	1 - Available
	0 - Unavailable
	0xFFFFFFFF0ERRORNO - Otherwise

The following program emulates **blockio** stats behavior and shows an example of how the **perfstat\_bio\_stats** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
# define STDEV_UPPERWORD(__x) (int)((__x & 0xFFFFFFFF00000000LL)>>32)
# define STDEV_LOWERWORD(__x) (int)(__x & 0xFFFFFFFF)

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_bio_dev_t *biop;

    /* check how many perfstat_bio_dev_t structures are available */
    tot = perfstat_bio_stats(NULL, NULL, sizeof(perfstat_bio_dev_t), 0);

    /* check for error */
    if (tot < 0)
    {
        perror("perfstat_bio_stats");
        exit(-1);
    }
    if (tot == 0)
    {
        printf("No disks found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    biop = calloc(tot, sizeof(perfstat_bio_dev_t));

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_bio_stats(NULL, biop,
        sizeof(perfstat_bio_dev_t), tot);

    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_bio_stats");
        exit(-1);
    }

    /* print statistics for each of the disks */
    for (i = 0; i < ret; i++) {
        printf("\nStatistics for disk      : %s\n", biop[i].name);
        printf("-----\n");
        printf("Device Status          : %llu\n", biop[i].dev_status);
        printf("DEV (Major,Minor)     : (%d,%d)\n", STDEV_UPPERWORD(biop[i].devid),STDEV_LOWERWORD(biop[i].devid));
        printf("Bytes Read             : %llu\n", biop[i].rbytes);
        printf("Bytes Written          : %llu\n", biop[i].wbytes);
        printf("Number of Reads        : %llu\n", biop[i].nread);
        printf("Number of Writes       : %llu\n", biop[i].nwrite);
        printf("Number of Read Errors  : %llu\n", biop[i].rerrs);
        printf("Number of Write Errors : %llu\n", biop[i].werrs);
        printf("Aggregate Time for Reads : %llu\n", biop[i].rtime);
        printf("Aggregate Time for writes : %llu\n", biop[i].wtime);
    }
}
```

The program displays an output that is similar to the following example output:

```
Statistics for disk : hdisk0
-----
Device Status          : 1
DEV (Major,Minor)     : (18,8)
Bytes Read             : 1089536
Bytes Written          : 72331264
Number of Reads        : 96
Number of Writes       : 15216
Number of Read Errors  : 0
Number of Write Errors : 0
Aggregate Time for Reads : 294
Aggregate Time for writes : 574260
```

## perfstat\_cpu interface

The **perfstat\_cpu** interface returns a set of structures of type **perfstat\_cpu\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_t** structure include:

Item	Descriptor
<b>name</b>	Logical processor name (cpu0, cpu1, ...)
<b>user</b>	Number of clock ticks spent in user mode
<b>sys</b>	Number of clock ticks spent in system (kernel) mode
<b>idle</b>	Number of clock ticks spent idle with no I/O pending
<b>wait</b>	Number of clock ticks spent idle with I/O pending
<b>syscall</b>	Number of system call executed

Several other CPU-related metrics (such as number of forks, read, write, and execs) are also returned. For a complete list, see the **perfstat\_cpu\_t** section in the **libperfstat.h** header.

The following code shows an example of how the **perfstat\_cpu** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char *argv[]) {
    int i, retcode, cputotal;
    perfstat_id_t firstcpu;
    perfstat_cpu_t *statp;

    /* check how many perfstat_cpu_t structures are available */
    cputotal = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);

    /* check for error */
    if (cputotal <= 0)
    {
        perror("perfstat_cpu");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(cputotal, sizeof(perfstat_cpu_t));
    if (statp == NULL) {
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* set name to first cpu */
    strcpy(firstcpu.name, FIRST_CPU);

    /* ask to get all the structures available in one call */
    retcode = perfstat_cpu(&firstcpu, statp, sizeof(perfstat_cpu_t), cputotal);

    /* check for error */
    if (retcode <= 0)
    {
        perror("perfstat_cpu");
        exit(-1);
    }

    /* return code is number of structures returned */

    for (i = 0; i < retcode; i++) {
        printf("\nStatistics for CPU : %s\n", statp[i].name);
        printf("-----\n");
        printf("CPU user time (raw ticks) : %llu\n", statp[i].user);
        printf("CPU sys time (raw ticks) : %llu\n", statp[i].sys);
        printf("CPU idle time (raw ticks) : %llu\n", statp[i].idle);
        printf("CPU wait time (raw ticks) : %llu\n", statp[i].wait);
        printf("number of syscalls : %llu\n", statp[i].syscall);
        printf("number of readings : %llu\n", statp[i].sysread);
        printf("number of writings : %llu\n", statp[i].syswrite);
    }
}
```

```

printf("number of forks          : %llu\n", statp[i].sysfork);
printf("number of execs         : %llu\n", statp[i].sysexec);
printf("number of char read     : %llu\n", statp[i].readch);
printf("number of char written  : %llu\n", statp[i].writech);
}
}

```

The program displays an output that is similar to the following example output:

```

Statistics for CPU : cpu0
-----
CPU user time (raw ticks) : 2585
CPU sys time (raw ticks) : 25994
CPU idle time (raw ticks) : 7688458
CPU wait time (raw ticks) : 3207
number of syscalls       : 6051122
number of readings       : 436595
number of writings       : 1284469
number of forks          : 4804
number of execs          : 5420
number of char read      : 1014077004
number of char written   : 56464273

Statistics for CPU : cpu1
-----
CPU user time (raw ticks) : 23
CPU sys time (raw ticks) : 794
CPU idle time (raw ticks) : 7703901
CPU wait time (raw ticks) : 42
number of syscalls       : 66064
number of readings       : 3432
number of writings       : 20620
number of forks          : 412
number of execs          : 51
number of char read      : 7068025
number of char written   : 217425

Statistics for CPU : cpu2
-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 720
CPU idle time (raw ticks) : 7704041
CPU wait time (raw ticks) : 0
number of syscalls       : 0
number of readings       : 0
number of writings       : 0
number of forks          : 0
number of execs          : 0
number of char read      : 0
number of char written   : 0

Statistics for CPU : cpu3
-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 810
CPU idle time (raw ticks) : 7703950
CPU wait time (raw ticks) : 0
number of syscalls       : 0
number of readings       : 0
number of writings       : 0
number of forks          : 0
number of execs          : 0
number of char read      : 0
number of char written   : 0

Statistics for CPU : cpu4
-----
CPU user time (raw ticks) : 243
CPU sys time (raw ticks) : 1799
CPU idle time (raw ticks) : 7702802
CPU wait time (raw ticks) : 62
number of syscalls       : 722482
number of readings       : 34416
number of writings       : 2994
number of forks          : 597
number of execs          : 453
number of char read      : 128511349
number of char written   : 2352602

Statistics for CPU : cpu5
-----

```

```

CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 209834
CPU idle time (raw ticks) : 7676489
CPU wait time (raw ticks) : 0
number of syscalls      : 729
number of readings      : 42
number of writings      : 0
number of forks         : 16
number of execs         : 1
number of char read     : 14607
number of char written  : 0

```

Statistics for CPU : cpu6

```

-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 210391
CPU idle time (raw ticks) : 7677505
CPU wait time (raw ticks) : 0
number of syscalls      : 0
number of readings      : 0
number of writings      : 0
number of forks         : 0
number of execs         : 0
number of char read     : 0
number of char written  : 0

```

Statistics for CPU : cpu7

```

-----
CPU user time (raw ticks) : 0
CPU sys time (raw ticks) : 209884
CPU idle time (raw ticks) : 7675736
CPU wait time (raw ticks) : 0
number of syscalls      : 0
number of readings      : 0
number of writings      : 0
number of forks         : 0
number of execs         : 0
number of char read     : 0
number of char written  : 0

```

In an environment where dynamic logical partitioning is used, the number of **perfstat\_cpu\_t** structures available is equal to the **ncpus\_high** field in the **perfstat\_cpu\_total\_t**. This number represents the highest index of any active processor since the last reboot. Kernel data structures holding performance metrics for processors are not deallocated when processors are turned offline or moved to a different partition and it stops updating the information. The **CPUs** field of the **perfstat\_cpu\_total\_t** structure represents the number of active processors, but the **perfstat\_cpu** interface returns **ncpus\_high** structures.

Applications can detect offline or moved processors by checking clock-tick increments. If the sum of the user, sys, idle, and wait fields is identical for a given processor between two **perfstat\_cpu** calls, that processor has been offline for the complete interval. If the sum multiplied by 10 ms (the value of a clock tick) does not match the time interval, the processor has not been online for the complete interval.

The preceding program emulates **mpstat** behavior and also shows how **perfstat\_cpu** is used.

## perfstat\_bridgedadapters Interface

The **perfstat\_bridgedadapters** interface returns a set of structures of type **perfstat\_seachildren\_t**, which is defined in the **libperfstat.h** file.

The following program shows an example of how the **perfstat\_bridgedadapters** interface is used:

```

/* The sample program display the metrics *
 * related to each and every Individual *
 * physical and virtual/trunk adapters which are under SEA in the VIOS */
#include<stdio.h>
#include<stdlib.h>
#include<libperfstat.h>
#include<net/if_types.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1
/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror ("malloc");\
    exit(2);\
}

```

```

        }
    }

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
int returncode;
/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

/* store the data structures */

static perfstat_netadapter_t *statp ,*statq;

/*
 * NAME: showusage
 *      to display the usage
 *
 */

void showusage(char *cmd)
{
    fprintf(stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>] [-n
<node name in the cluster>]/n; ", cmd);
    exit(1);
}

/*
 * NAME: do_initialization
 *      This function initializes the data structures.
 *      It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */

int do_initialization(void)
{
    perfstat_id_t first;

    /* check how many perfstat_netadapter_t structures are available */
    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        /* SEA Adapter Name must be filled */
        strcpy(nodeid.name , FIRST_SEA);
        /*nodeid.spec = NODENAME; */
        tot = perfstat_bridgedadapters_node(&nodeid, NULL, sizeof(perfstat_netadapter_t), 0);
    } else
    {
        /* SEA Adapter Name must be filled */
        strcpy(first.name , FIRST_SEA);
        tot = perfstat_bridgedadapters(&first, NULL, sizeof(perfstat_netadapter_t), 0);
    }
    if (tot == 0)
    {
        printf("There is no SEA Children\n");
        exit(0);
    }
    if (tot < 0) {
        if (collect_remote_node_stats)
            perror("perfstat_bridgedadapters_node: ");
        else
            perror("perfstat_bridgedadapters: ");

        exit(1);
    }
    /* allocate enough memory for all the structures */
    statp = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
    CHECK_FOR_MALLOC_NULL(statp);
    statq = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
    CHECK_FOR_MALLOC_NULL(statq);
    return(0);
}

/*
 *Name: display_metrics
 *      collect the metrics and display them
 *
 */
void display_metrics()
{

```

```

perfstat_id_t first;
int ret, i;

if(collect_remote_node_stats) {
    strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
    nodeid.spec = NODENAME;

    /* Valid SEA Adapter Name Must be passed */
    strcpy(nodeid.name, FIRST_SEA);
    ret = perfstat_bridgedadapters_node(&nodeid, statq, sizeof(perfstat_netadapter_t), tot);
} else
{
    /* Valid SEA Adapter Name Must be passed */
    strcpy(first.name, FIRST_SEA);
    ret = perfstat_bridgedadapters(&first, statq, sizeof(perfstat_netadapter_t), tot);
}
if (ret < 0) {
    free(statp);
    free(statq);
    if (collect_remote_node_stats)
        perror("perfstat_bridgedadapters_node: ");
    else
        perror("perfstat_bridgedadapters: ");
    exit(1);
}
while (count)
{
    sleep (interval);
    if(collect_remote_node_stats)
    {
        ret = perfstat_bridgedadapters_node(&nodeid, statp, sizeof(perfstat_netadapter_t),
tot);
    } else
    {
        ret = perfstat_bridgedadapters(&first, statp, sizeof(perfstat_netadapter_t), tot);
    }
    /* print statistics for each of the interfaces */
    for (i = 0; i < ret; i++)
    {
        printf(" Adapter name: %s \n", statp[i].name);
        printf(" ===== Transmit Statistics
===== \n");
        printf(" Transmit Packets: %lld \n", statp[i].tx_packets - statq[i].tx_packets);
        printf(" Transmit Bytes: %lld \n", statp[i].tx_bytes - statq[i].tx_bytes);
        printf(" Transfer Interrupts : %lld \n", statp[i].tx_interrupts -
statq[i].tx_interrupts);
        printf(" Transmit Errors : %lld \n", statp[i].tx_errors - statq[i].tx_errors);
        printf(" Packets Dropped at the time of Data Transmission : %lld \n",
statp[i].tx_packets_dropped - statq[i].tx_packets_dropped);
        printf(" Transmit Queue Size: %lld \n", statp[i].tx_queue_size -
statq[i].tx_queue_size);
        printf(" Transmit Queue Length : %lld \n", statp[i].tx_queue_len -
statq[i].tx_queue_len);
        printf(" Transmit Queue Overflow : %lld \n", statp[i].tx_queue_overflow -
statq[i].tx_queue_overflow);
        printf(" Broadcast Packets Transmitted: %lld \n", statp[i].tx_broadcast_packets -
statq[i].tx_broadcast_packets);
        printf(" Multicast packets Transmitted: %lld \n", statp[i].tx_multicast_packets -
statq[i].tx_multicast_packets);
        printf(" Lost Carrier Sense signal count : %lld \n", statp[i].tx_carrier_sense -
statq[i].tx_carrier_sense);
        printf(" Count of DMA Under-runs for Transmission: %lld
\n", statp[i].tx_DMA_underrun - statq[i].tx_DMA_underrun);
        printf(" Number of unsuccessful transmissions : %lld
\n", statp[i].tx_lost_CTS_errors - statq[i].tx_lost_CTS_errors);
        printf(" Maximum Collision Errors at Transmission: %lld
\n", statp[i].tx_max_collision_errors - statq[i].tx_max_collision_errors);
        printf(" Late Collision Errors at Transmission : %lld
\n", statp[i].tx_late_collision_errors - statq[i].tx_late_collision_errors);
        printf(" Number of packets deferred for Transmission : %lld
\n", statp[i].tx_deferred - statq[i].tx_deferred);
        printf(" Time Out Errors for Transmission : %lld \n", statp[i].tx_timeout_errors -
statq[i].tx_timeout_errors);
        printf(" Count of Single Collision error at Transmission: %lld
\n", statp[i].tx_single_collision_count - statq[i].tx_single_collision_count);
        printf(" Count of Multiple Collision error at Transmission : %lld
\n", statp[i].tx_multiple_collision_count - statq[i].tx_multiple_collision_count);

        printf(" ===== Receive Statistics
===== \n");
        printf(" Receive Packets : %lld \n", statp[i].rx_packets - statq[i].rx_packets);

```

```

        printf(" Receive Bytes :%lld \n", statp[i].rx_bytes - statq[i].rx_bytes);
        printf(" Receive Interrupts : %lld \n", statp[i].rx_interrupts -
statq[i].rx_interrupts);
        printf(" Input errors on interface :%lld \n", statp[i].rx_errors -
statq[i].rx_errors);
        printf(" Number of Packets Dropped : %lld \n", statp[i].rx_packets_dropped -
statq[i].rx_packets_dropped);
        printf(" Count of Bad Packets Received : %lld \n", statp[i].rx_bad_packets -
statq[i].rx_bad_packets);
        printf(" Number of MultiCast Packets Received : %lld \n",
statp[i].rx_multicast_packets - statq[i].rx_multicast_packets);
        printf(" Number of Broadcast Packets Received : %lld
\n",statp[i].rx_broadcast_packets - statq[i].rx_broadcast_packets);
        printf(" Count of Packets Received with CRC errors: %lld \n",statp[i].rx_CRC_errors
- statq[i].rx_CRC_errors);
        printf(" DMA over-runs : %lld \n", statp[i].rx_DMA_overrun -
statq[i].rx_DMA_overrun);
        printf(" Alignment Errors : %lld \n", statp[i].rx_alignment_errors -
statq[i].rx_alignment_errors);
        printf(" No Resource Errors : %lld \n", statp[i].rx_noresource_errors -
statq[i].rx_noresource_errors);
        printf(" Collision Errors: %lld \n", statp[i].rx_collision_errors -
statq[i].rx_collision_errors);
        printf(" Number of Short Packets Received: %lld
\n",statp[i].rx_packet_tooshort_errors - statq[i].rx_packet_tooshort_errors);
        printf(" Number of Too Long Packets Received : %lld \n",
statp[i].rx_packet_toolong_errors - statq[i].rx_packet_toolong_errors);
        printf(" Number of Received Packets discarded by Adapter: %lld \n",
statp[i].rx_packets_discardedbyadapter -
statq[i].rx_packets_discardedbyadapter);
        printf(" Adapter Type :%d \n",statp[i].adapter_type);
        printf("
===== \n");
    }

    memcpy(statq, statp, (tot * sizeof(perfstat_netadapter_t)));
    count--;
}
}
/*
 *Name: main
 *
 */
int main(int argc, char *argv[])
{
    int i, rc;
    /* get the interval and count values */

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {

```

```

        perror("cluster statistics collection is not available");
        exit(-1);
    }
}

do_initialization();
display_metrics();

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}

free(statp);
free(statq);
return 0;
}

```

## perfstat\_cpu\_util interface

The `perfstat_cpu_util` interface returns a set of structures of type `perfstat_cpu_util_t`, which is defined in the `libperfstat.h` file

The `perfstat_cpu_util` interface includes the following fields:

Item	Descriptor
<b>cpu_id</b>	Holds CPU ID
<b>entitlement</b>	Partition's entitlement
<b>user_pct</b>	Percentage of utilization in user mode
<b>kern_pct</b>	Percentage of utilization in kernel mode
<b>idle_pct</b>	Percentage of utilization in idle mode
<b>wait_pct</b>	Percentage of utilization in wait mode
<b>physical_busy</b>	Physical CPU is busy
<b>physical_consumed</b>	Total CPUs consumed by the partition
<b>freq_pct</b>	Average frequency over the last interval in percentage
<b>entitlement_pct</b>	Percentage of entitlement used
<b>busy_pct</b>	Percentage of entitlement busy
<b>idle_donated_pct</b>	Percentage of idle cycles donated
<b>busy_donated_pct</b>	Percentage of busy cycles donated
<b>idle_stolen_pct</b>	Percentage of idle cycles stolen
<b>busy_stolen_pct</b>	Percentage of busy cycles stolen
<b>float l_user_pct</b>	Percentage of utilization in user mode in terms of the logical processor ticks
<b>float l_kern_pct</b>	Percentage of utilization in kernel mode in terms of the logical processor ticks
<b>float l_idle_pct</b>	Percentage of utilization in idle mode in terms of the logical processor ticks
<b>float l_wait_pct</b>	Percentage of utilization in wait mode in terms of the logical processor ticks
<b>u_longlong_t delta_time</b>	Percentage of the delta time in milliseconds for which the utilization is evaluated

Both system utilization and per CPU utilization can be obtained by using the `perfstat_cpu_util` by mentioning the type field of the `perfstat_rawdata_t` data structure as `UTIL_CPU_TOTAL` or `UTIL_CPU` respectively. `UTIL_CPU_TOTAL` and `UTIL_CPU` are the macros, which can be referred in the definition of the `perfstat_rawdata_t` data structure.

The use of the `perfstat_cpu_util` API for system-level utilization follows:

```
#include <libperfstat.h>
#define PERIOD 5
void main()
{
    perfstat_cpu_total_t *newt, *oldt;
    perfstat_cpu_util_t *util;
    perfstat_rawdata_t data;
    int rc;

    oldt = (perfstat_cpu_total_t*)malloc(sizeof(perfstat_cpu_total_t)*1);
    if(oldt==NULL){
        perror ("malloc");
        exit(-1);
    }

    newt = (perfstat_cpu_total_t*)malloc(sizeof(perfstat_cpu_total_t)*1);
    if(newt==NULL){
        perror ("malloc");
        exit(-1);
    }

    util = (perfstat_cpu_util_t*)malloc(sizeof(perfstat_cpu_util_t)*1);
    if(util==NULL){
        perror ("malloc");
        exit(-1);
    }

    rc = perfstat_cpu_total(NULL, oldt, sizeof(perfstat_cpu_total_t), 1);
    if(rc <= 0)
    {
        perror("Error in perfstat_cpu_total");
        exit(-1);
    }
    sleep(PERIOD);
    rc = perfstat_cpu_total(NULL, newt, sizeof(perfstat_cpu_total_t), 1);
    if(rc <= 0)
    {
        perror("Error in perfstat_cpu_total");
        exit(-1);
    }
    data.type = UTIL_CPU_TOTAL;
    data.curstat = newt; data.prevstat= oldt;
    data.sizeof_data = sizeof(perfstat_cpu_total_t);
    data.cur_elems = 1;
    data.prev_elems = 1;
    rc = perfstat_cpu_util(&data, util, sizeof(perfstat_cpu_util_t), 1);
    if(rc <= 0)
    {
        perror("Error in perfstat_cpu_util");
        exit(-1);
    }
    printf("====Overall CPU Utilization Metrics====\n");
    printf("Utilization Metrics for a period of %d seconds\n",PERIOD);
    printf("User Percentage = %f\n",util->user_pct);
    printf("System Percentage = %f\n",util->kern_pct);
    printf("Idle Percentage = %f\n",util->idle_pct);
    printf("Wait Percentage = %f\n",util->wait_pct);
    printf("Physical Busy = %f\n",util->physical_busy);
    printf("Physical Consumed = %f\n",util->physical_consumed);
    printf("Freq Percentage = %f\n",util->freq_pct);
    printf("Entitlement Used Percentage = %f\n",util->entitlement_pct);
    printf("Entitlement Busy Percentage = %f\n",util->busy_pct);
    printf("Idle Cycles Donated Percentage = %f\n",util->idle_donated_pct);
    printf("Busy Cycles Donated Percentage = %f\n",util->busy_donated_pct);
    printf("Idle Cycles Stolen Percentage = %f\n",util->idle_stolen_pct);
    printf("Busy Cycles Stolen Percentage = %f\n",util->busy_stolen_pct);
    printf("User percentage for logical cpu in ticks = %f\n",util->l_user_pct);
    printf("Sytem percentage for logical cpu in ticks= %f\n",util->l_kern_pct);
    printf("Idle percentage for logical cpu in ticks= %f\n",util->l_idle_pct);
    printf("Wait percentage for logical cpu in ticks= %f\n",util->l_wait_pct);
    printf("delta time in milliseconds = %llu \n",util->delta_time);
}
```

```

    printf("=====\n");
}

```

The program produces the output similar to the following:

```

=====Overall CPU Utilization Metrics=====
Utilization Metrics for a period of 5 seconds
User Percentage =          0.050689
System Percentage =       0.262137
Idle Percentage =        99.687172
Wait Percentage =         0.000000
Physical Busy =           0.003128
Physical Consumed =       0.008690
Freq Percentage =        99.935417
Entitlement Used Percentage = 0.869017
Entitlement Busy Percentage = 0.312826
Idle Cycles Donated Percentage = 0.000000
Busy Cycles Donated Percentage = 0.000000
Idle Cycles Stolen Percentage = 0.000000
Busy Cycles Stolen Percentage = 0.000000
User percentage for logical cpu in ticks = 0.000000
System percentage for logical cpu in ticks= 0.082034
Idle percentage for logical cpu in ticks= 99.917969
Wait percentage for logical cpu in ticks= 0.000000
delta time in milliseconds = 4980

```

The example code to calculate system utilization per CPU, and CPU utilization, by using the `perfstat_cpu_util` interface follows:

```

#include <libperfstat.h>
#define PERIOD 5

void main()
{
    perfstat_rawdata_t data;
    perfstat_cpu_util_t *util;
    perfstat_cpu_t *newt,*oldt;
    perfstat_id_t id;
    int i,cpu_count,rc;

    /* Check how many perfstat_cpu_t structures are available */
    cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

    /* check for error */
    if(cpu_count <= 0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }
    /* allocate enough memory */
    oldt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
    if(oldt == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1);
    }
    /* set name to first cpu */
    strcpy(id.name,FIRST_CPU);
    /* ask to get all the structures available in one call */
    rc = perfstat_cpu(&id, oldt, sizeof(perfstat_cpu_t), cpu_count);
    /* check for error */
    if(rc <=0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }
    data.type = UTIL_CPU;
    data.prevstat= oldt;
    data.sizeof_data = sizeof(perfstat_cpu_t);
    data.prev_elems = cpu_count;
    sleep(PERIOD);
    /* Check how many perfstat_cpu_t structures are available after a defined period */
    cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

    /* Check for error */
    if(cpu_count <= 0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }
}

```

```

}

data.cur_elems = cpu_count;
if(data.prev_elems != data.cur_elems)
{
    perror("The number of CPUs has become different for defined period");
    exit(-1);
}
/* allocate enough memory */
newt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
util = (perfstat_cpu_util_t *)calloc(cpu_count,sizeof(perfstat_cpu_util_t));
if(newt == NULL || util == NULL)
{
    perror("Memory Allocation Error");
    exit(-1);
}
data.curstat = newt;
rc = perfstat_cpu(&id, newt, sizeof(perfstat_cpu_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}
/* Calculate CPU Utilization Metrics*/
rc = perfstat_cpu_util(&data, util, sizeof(perfstat_cpu_util_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu_util");
    exit(-1);
}
printf("==== Per CPU Utilization Metrics =====\n");
printf("Utilization Metrics for a period of %d seconds\n",PERIOD);
printf("=====\n");
for ( i = 0;i<cpu_count;i++)
{
    printf("Utilization metrics for CPU-ID = %s\n",util[i].cpu_id);
    printf("User Percentage = %f\n",util[i].user_pct);
    printf("System Percentage = %f\n",util[i].kern_pct);
    printf("Idle Percentage = %f\n",util[i].idle_pct);
    printf("Wait Percentage = %f\n",util[i].wait_pct);
    printf("Physical Busy = %f\n",util[i].physical_busy);
    printf("Physical Consumed = %f\n",util[i].physical_consumed);
    printf("Freq Percentage = %f\n",util[i].freq_pct);
    printf("Entitlement Used Percentage = %f\n",util[i].entitlement_pct);
    printf("Entitlement Busy Percentage = %f\n",util[i].busy_pct);
    printf("Idle Cycles Donated Percentage = %f\n",util[i].idle_donated_pct);
    printf("Busy Cycles Donated Percentage = %f\n",util[i].busy_donated_pct);
    printf("Idle Cycles Stolen Percentage = %f\n",util[i].idle_stolen_pct);
    printf("Busy Cycles Stolen Percentage = %f\n",util[i].busy_stolen_pct);
    printf("system percentage for logical cpu in ticks = %f\n",util[i].l_kern_pct);
    printf("idle percentage for logical cpu in ticks = %f\n",util[i].l_idle_pct);
    printf("wait percentage for logical cpu in ticks = %f\n",util[i].l_wait_pct);
    printf("delta time in milliseconds = %llu \n",util[i].delta_time);
    printf("\n\n");
}
printf("=====\n");
}
}

```

The program produces the output similar to the following:

```

==== Per CPU Utilization Metrics =====
Utilization Metrics for a period of 5 seconds
=====
Utilization metrics for CPU-ID =      cpu0
User Percentage =                      14.850358
System Percentage =                    63.440376
Idle Percentage =                      21.709267
Wait Percentage =                      0.000000
Physical Busy =                        0.003085
Physical Consumed =                    0.003941
Freq Percentage =                      99.975967
Entitlement Used Percentage =           0.394055
Entitlement Busy Percentage =           0.308508
Idle Cycles Donated Percentage =        0.000000
Busy Cycles Donated Percentage =        0.000000
Idle Cycles Stolen Percentage =         0.000000
Busy Cycles Stolen Percentage =         0.000000
system percentage for logical cpu in ticks = 0.000000
idle percentage for logical cpu in ticks = 100.000000
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 4999

```

```
Utilization metrics for CPU-ID =    cpu1
User Percentage =                   0.000000
System Percentage =                  4.720662
Idle Percentage =                    95.279335
Wait Percentage =                    0.000000
Physical Busy =                      0.000065
Physical Consumed =                  0.001371
Freq Percentage =                    99.938919
Entitlement Used Percentage =         0.137110
Entitlement Busy Percentage =        0.006472
Idle Cycles Donated Percentage =     0.000000
Busy Cycles Donated Percentage =     0.000000
Idle Cycles Stolen Percentage =      0.000000
Busy Cycles Stolen Percentage =      0.000000
system percentage for logical cpu in ticks = 0.000000
idle percentage for logical cpu in ticks = 100.000000
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 5000
```

```
Utilization metrics for CPU-ID =    cpu2
User Percentage =                   0.000000
System Percentage =                  5.848962
Idle Percentage =                    94.151039
Wait Percentage =                    0.000000
Physical Busy =                      0.000079
Physical Consumed =                  0.001348
Freq Percentage =                    99.900566
Entitlement Used Percentage =         0.134820
Entitlement Busy Percentage =        0.007886
Idle Cycles Donated Percentage =     0.000000
Busy Cycles Donated Percentage =     0.000000
Idle Cycles Stolen Percentage =      0.000000
Busy Cycles Stolen Percentage =      0.000000
system percentage for logical cpu in ticks = 0.000000
idle percentage for logical cpu in ticks = 100.000000
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 5000
```

```
Utilization metrics for CPU-ID =    cpu3
User Percentage =                   0.000000
System Percentage =                  4.644570
Idle Percentage =                    95.355431
Wait Percentage =                    0.000000
Physical Busy =                      0.000061
Physical Consumed =                  0.001312
Freq Percentage =                    99.925430
Entitlement Used Percentage =         0.131174
Entitlement Busy Percentage =        0.006092
Idle Cycles Donated Percentage =     0.000000
Busy Cycles Donated Percentage =     0.000000
Idle Cycles Stolen Percentage =      0.000000
Busy Cycles Stolen Percentage =      0.000000
system percentage for logical cpu in ticks = 0.000000
idle percentage for logical cpu in ticks = 100.000000
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 5000
```

```
Utilization metrics for CPU-ID =    cpu4
User Percentage =                   0.000000
System Percentage =                  55.325123
Idle Percentage =                    44.674877
Wait Percentage =                    0.000000
Physical Busy =                      0.000153
Physical Consumed =                  0.000276
Freq Percentage =                    99.927551
Entitlement Used Percentage =         0.027605
Entitlement Busy Percentage =        0.015273
Idle Cycles Donated Percentage =     0.000000
Busy Cycles Donated Percentage =     0.000000
Idle Cycles Stolen Percentage =      0.000000
Busy Cycles Stolen Percentage =      0.000000
system percentage for logical cpu in ticks = 0.000000
idle percentage for logical cpu in ticks = 100.000000
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 4999
```

```
Utilization metrics for CPU-ID =    cpu5
```

```

User Percentage = 0.000000
System Percentage = 1.854463
Idle Percentage = 98.145538
Wait Percentage = 0.000000
Physical Busy = 0.000002
Physical Consumed = 0.000113
Freq Percentage = 99.612183
Entitlement Used Percentage = 0.011326
Entitlement Busy Percentage = 0.000210
Idle Cycles Donated Percentage = 0.000000
Busy Cycles Donated Percentage = 0.000000
Idle Cycles Stolen Percentage = 0.000000
Busy Cycles Stolen Percentage = 0.000000
system percentage for logical cpu in ticks = 0.255102
idle percentage for logical cpu in ticks = 99.744896
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 3913

```

```

Utilization metrics for CPU-ID = cpu6
User Percentage = 0.000000
System Percentage = 1.776852
Idle Percentage = 98.223145
Wait Percentage = 0.000000
Physical Busy = 0.000002
Physical Consumed = 0.000115
Freq Percentage = 99.475967
Entitlement Used Percentage = 0.011506
Entitlement Busy Percentage = 0.000204
Idle Cycles Donated Percentage = 0.000000
Busy Cycles Donated Percentage = 0.000000
Idle Cycles Stolen Percentage = 0.000000
Busy Cycles Stolen Percentage = 0.000000
system percentage for logical cpu in ticks = 0.255102
idle percentage for logical cpu in ticks = 99.744896
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 3912

```

```

Utilization metrics for CPU-ID = cpu7
User Percentage = 0.000000
System Percentage = 2.138275
Idle Percentage = 97.861725
Wait Percentage = 0.000000
Physical Busy = 0.000002
Physical Consumed = 0.000112
Freq Percentage = 99.593727
Entitlement Used Percentage = 0.011205
Entitlement Busy Percentage = 0.000240
Idle Cycles Donated Percentage = 0.000000
Busy Cycles Donated Percentage = 0.000000
Idle Cycles Stolen Percentage = 0.000000
Busy Cycles Stolen Percentage = 0.000000
system percentage for logical cpu in ticks = 0.255102
idle percentage for logical cpu in ticks = 99.744896
wait percentage for logical cpu in ticks = 0.000000
delta time in milliseconds = 3912

```

### Example for simplelparstat.c code

This topic provides an example for using the simplelparstat.c code.

```

#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <libperfstat.h>
#include <sys/systemcfg.h>

#define XINTFRAC ((double)(_system_configuration.Xint)/(double)(_system_configuration.Xfrac))
/* convert physical processor ticks to seconds */
#define HTIC2SEC(x) ((double)x * XINTFRAC)/(double)100000000.0

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

/*simplelparstat.c file can be used in two modes:-
1) Auto Mode:It makes use of perfstat_cpu_util API to calculate utilization values,enable 'UTIL_AUTO' macro for execution in auto mode.
2) Manual Mode: Calculations are done in the current code.
*/

/**#define UTIL_AUTO 1*/

#ifdef UTIL_AUTO
#define UTIL_MS 1
#define UTIL_PCT 0
#define UTIL_CORE 2
#define UTIL_PURR 0
#define UTIL_SPURR 1

```

```

void display_lpar_util_auto(int mode,int cpumode,int count,int interval);
#endif

static int disp_util_header = 1;
static u_longlong_t last_time_base;
static u_longlong_t last_pcpu_user, last_pcpu_sys, last_pcpu_idle, last_pcpu_wait;
static u_longlong_t last_lcpu_user, last_lcpu_sys, last_lcpu_idle, last_lcpu_wait;
static u_longlong_t last_busy_donated, last_idle_donated;
static u_longlong_t last_busy_stolen, last_idle_stolen;
static u_longlong_t last_phint = 0, last_vcswh = 0, last_pit = 0;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

void display_lpar_util(void);

int main(int argc, char* argv[])
{
    int interval = INTERVAL_DEFAULT;
    int count = COUNT_DEFAULT;
    int i, rc;
    char *optlist = "i:c:n:";
    int mode=0,cpumode=0;

    /* Process the arguments */
    while ((i = getopt(argc, argv, optlist)) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default: /* Invalid arguments. Print the usage and terminate */
                fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ]
\n", argv[0]);
                return(-1);
        }
    }

    if(collect_remote_node_stats)
    { /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }

#ifdef UTIL_AUTO
    printf("Enter CPU mode.\n");
    printf(" 0 PURR \n 1 SPURR \n");
    scanf("%d",&cpumode);
    printf("Enter print mode.\n");
    printf(" 0 PERCENTAGE\n 1 MILLISECONDS\n 2 CORES \n");
    scanf("%d",&mode);

    if((mode>2)&& (cpumode>1))
    {
        printf("Error: Invalid Input\n");
        exit(0);
    }
    display_lpar_util_auto(mode,cpumode,count,interval);
#else
    /* Iterate "count" times */
    while (count > 0)
    {
        display_lpar_util();
        sleep(interval);
        count--;
    }
#endif

    if(collect_remote_node_stats)
    { /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }

    return(0);
}

/* Save the current values for the next iteration */
void save_last_values(perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    last_vcswh = lparstats->vol_virt_cswitch + lparstats->invol_virt_cswitch;
    last_time_base = lparstats->timebase_last;
    last_phint = lparstats->phantintirs;
    last_pit = lparstats->pool_idle_time;

    last_pcpu_user = lparstats->puser;

```

```

last_pcpu_sys = lparstats->psys;
last_pcpu_idle = lparstats->pidle;
last_pcpu_wait = lparstats->pwait;

last_lcpu_user = cpustats->user;
last_lcpu_sys = cpustats->sys;
last_lcpu_idle = cpustats->idle;
last_lcpu_wait = cpustats->wait;

last_busy_donated = lparstats->busy_donated_purr;
last_idle_donated = lparstats->idle_donated_purr;

last_busy_stolen = lparstats->busy_stolen_purr;
last_idle_stolen = lparstats->idle_stolen_purr;
}

/* retrieve metrics using perfstat API */
void collect_metrics (perfstat_cpu_total_t *cpustats, perfstat_partition_total_t *lparstats)
{
    if (collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        if (perfstat_partition_total_node(&nodeid, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total_node");
            exit(-1);
        }
        if (perfstat_cpu_total_node(&nodeid, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
            perror("perfstat_cpu_total_node");
            exit(-1);
        }
    }
    else
    {
        if (perfstat_partition_total(NULL, lparstats, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total");
            exit(-1);
        }

        if (perfstat_cpu_total(NULL, cpustats, sizeof(perfstat_cpu_total_t), 1) <= 0) {
            perror("perfstat_cpu_total");
            exit(-1);
        }
    }
}

/* print header informations */
void print_header(perfstat_partition_total_t *lparstats)
{
    if (lparstats->type.b.shared_enabled) { /* partition is a SPLPAR */
        if (lparstats->type.b.pool_util_authority) { /* partition has PUA access */
            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "%user", "%sys", "%wait", "%idle", "phyc", "%entc", "lbusy", "app", "vcsw", "phint");

            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----");
        } else {
            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "%user", "%sys", "%wait", "%idle", "phyc", "phint", "phyc", "lbusy", "vcsw", "phint");

            printf("\n%5s %5s %6s %6s %5s %5s %5s %4s %5s",
                "-----", "-----", "-----", "-----", "-----", "-----", "-----", "-----");
        }
    } else { /* partition is a DLPAR */
        printf("\n%5s %5s %6s %6s", "%user", "%sys", "%wait", "%idle");
        printf("\n%5s %5s %6s %6s", "-----", "-----", "-----", "-----");
        if (lparstats->type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
            printf(" %6s %6s", "%phyc", "%vcsw");
            printf(" %6s %6s", "-----", "-----");
        }
    }
    fprintf(stdout, "\n");
}

/* Gather and display lpar utilization metrics */
void display_lpar_util(void)
{
    u_longlong_t delta_pcpu_user, delta_pcpu_sys, delta_pcpu_idle, delta_pcpu_wait;
    u_longlong_t delta_lcpu_user, delta_lcpu_sys, delta_lcpu_idle, delta_lcpu_wait;
    u_longlong_t delta_busy_stolen, delta_busy_donated, delta_idle_stolen, delta_idle_donated;
    u_longlong_t vcswh, lcpstime, pcputime;
    u_longlong_t entitled_purr, unused_purr;
    u_longlong_t delta_purr, delta_time_base;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    perfstat_cpu_total_t cpustats;

    /* retrieve the metrics */
    collect_metrics (&cpustats, &lparstats);

    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
        print_header (&lparstats);

        disp_util_header = 0;

        /* first iteration, we only read the data, print the header and save the data */
        save_last_values(&cpustats, &lparstats);
        return;
    }

    /* calculate physcial processor tics during the last interval in user, system, idle and wait mode */
    delta_pcpu_user = lparstats.puser - last_pcpu_user;
    delta_pcpu_sys = lparstats.psys - last_pcpu_sys;
    delta_pcpu_idle = lparstats.pidle - last_pcpu_idle;
    delta_pcpu_wait = lparstats.pwait - last_pcpu_wait;

    /* calculate total physcial processor tics during the last interval */

```

```

delta_purr = pcpptime = delta_pcpu_user + delta_pcpu_sys + delta_pcpu_idle + delta_pcpu_wait;

/* calculate clock tics during the last interval in user, system, idle and wait mode */
delta_lcpu_user = cpustats.user - last_lcpu_user;
delta_lcpu_sys = cpustats.sys - last_lcpu_sys;
delta_lcpu_idle = cpustats.idle - last_lcpu_idle;
delta_lcpu_wait = cpustats.wait - last_lcpu_wait;

/* calculate total clock tics during the last interval */
lcpptime = delta_lcpu_user + delta_lcpu_sys + delta_lcpu_idle + delta_lcpu_wait;

/* calculate entitlement for this partition - entitled physical processors for this partition */
entitlement = (double)lparstats.entitled_proc_capacity / 100.0 ;

/* calculate delta time in terms of physical processor tics */
delta_time_base = lparstats.timebase_last - last_time_base;

if (lparstats.type.b.shared_enabled) { /* partition is a SPLPAR */
/* calculate entitled physical processor tics for this partitions */
entitled_purr = delta_time_base * entitlement;
if (entitled_purr < delta_purr) { /* for uncapped SPLPAR */
/* in case of uncapped SPLPAR, consider entitled physical processor tics or
* consumed physical processor tics, which ever is greater */
entitled_purr = delta_purr;
}
/* calculate unused physical processor tics out of the entitled physical processor tics */
unused_purr = entitled_purr - delta_purr;

/* distributed unused physical processor tics among wait and idle proportionally to wait and idle in clock tics */
delta_pcpu_wait += unused_purr * ((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += unused_purr * ((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* far SPLPAR, consider the entitled physical processor tics as the actual delta physical processor tics */
pcpptime = entitled_purr;
}
else if (lparstats.type.b.donate_enabled) { /* if donation is enabled for this DLPAR */
/* calculate busy stolen and idle stolen physical processor tics during the last interval */
/* these physical processor tics are stolen from this partition by the hypervisor
* which will be used by wanting partitions */
delta_busy_stolen = lparstats.busy_stolen_purr - last_busy_stolen;
delta_idle_stolen = lparstats.idle_stolen_purr - last_idle_stolen;

/* calculate busy donated and idle donated physical processor tics during the last interval */
/* these physical processor tics are voluntarily donated by this partition to the hypervisor
* which will be used by wanting partitions */
delta_busy_donated = lparstats.busy_donated_purr - last_busy_donated;
delta_idle_donated = lparstats.idle_donated_purr - last_idle_donated;

/* add busy donated and busy stolen to the kernel bucket, as cpu
* cycles were donated / stolen when this partition is busy */
delta_pcpu_sys += delta_busy_donated;
delta_pcpu_sys += delta_busy_stolen;

/* distribute idle stolen to wait and idle proportionally to the logical wait and idle in clock tics, as
* cpu cycles were stolen when this partition is idle or in wait */
delta_pcpu_wait += delta_idle_stolen *
((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += delta_idle_stolen *
((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* distribute idle donated to wait and idle proportionally to the logical wait and idle in clock tics, as
* cpu cycles were donated when this partition is idle or in wait */
delta_pcpu_wait += delta_idle_donated *
((double)delta_lcpu_wait / (double)(delta_lcpu_wait + delta_lcpu_idle));
delta_pcpu_idle += delta_idle_donated *
((double)delta_lcpu_idle / (double)(delta_lcpu_wait + delta_lcpu_idle));

/* add donated to the total physical processor tics for CPU usage calculation, as they were
* distributed to respective buckets accordingly */
pcpptime += (delta_idle_donated + delta_busy_donated);

/* add stolen to the total physical processor tics for CPU usage calculation, as they were
* distributed to respective buckets accordingly */
pcpptime += (delta_idle_stolen + delta_busy_stolen);
}

/* Processor Utilization - Applies for both SPLPAR and DLPAR*/
printf("%5.1f ", (double)delta_pcpu_user * 100.0 / (double)pcpptime);
printf("%5.1f ", (double)delta_pcpu_sys * 100.0 / (double)pcpptime);
printf("%6.1f ", (double)delta_pcpu_wait * 100.0 / (double)pcpptime);
printf("%6.1f ", (double)delta_pcpu_idle * 100.0 / (double)pcpptime);

if (lparstats.type.b.shared_enabled) { /* print SPLPAR specific stats */
/* Physical Processor Consumed by this partition */
phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
printf("%5.2f ", (double)phys_proc_consumed);

/* Percentage of Entitlement Consumed - percentage of entitled physical processor tics consumed */
percent_ent = (double)((phys_proc_consumed / entitlement) * 100);
printf("%5.1f ", percent_ent);

/* Logical Processor Utilization of this partition */
printf("%5.1f ", (double)(delta_lcpu_user+delta_lcpu_sys) * 100.0 / (double)lcpptime);

if (lparstats.type.b.pool_util_authority) {
/* Available physical Processor units available in the shared pool (app) */
printf("%5.2f ", (double)(lparstats.pool_idle_time - last_pit) /
XINTFRAC*(double)delta_time_base);
}

/* Virtual CPU Context Switches per second */
vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
delta_sec = HTIC2SEC(delta_time_base);
printf("%4.0f ", (double)(vcsw - last_vcsw) / delta_sec);

/* Phantom Interrupts per second */
printf("%5.0f", (double)(lparstats.phantintrs - last_phint) / delta_sec);
}
}

```

```

else if (lparstats.type.b.donate_enabled) { /* print donation-enabled DLPAR specific stats */
    /* Physical Processor Consumed by this partition
    * (excluding donated and stolen physical processor tics). */
    phys_proc_consumed = (double)delta_purr / (double)delta_time_base;
    printf("%5.2f ", (double)phys_proc_consumed);

    /* Virtual CPU Context Switches per second */
    vcsw = lparstats.vol_virt_cswitch + lparstats.invol_virt_cswitch;
    delta_sec = HTIC2SEC(delta_time_base);
    printf("%5.0f ", (double)(vcsw - last_vcsw) / delta_sec);
}
printf("\n");
save_last_values(&cpustats, &lparstats);
}

#ifdef UTIL_AUTO
void display_lpar_util_auto(int mode,int cpumode,int count,int interval)
{
    float user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr;
    float user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,sum_core_spurr;
    u_longlong_t user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,sum_ms;
    u_longlong_t user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr;
    perfstat_rawdata_t data;
    u_longlong_t delta_purr, delta_time_base;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    static perfstat_cpu_total_t oldt,newt;
    perfstat_cpu_util_t util;
    int rc;

    /* retrieve the metrics */

    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
    if(mode==UTIL_PCT)
        printf("\n%5s %5s %6s %6s %5s \n",
            "user", "sys", "%wait", "%idle", "physc");
    else if(mode==UTIL_MS)
        printf("\n%5s %5s %6s %6s %5s \n",
            "user(ms)", "sys(ms)", "wait(ms)", "idle(ms)", "physc");
    else if(mode==UTIL_CORE)
        printf("\n%5s %5s %6s %6s %5s \n",
            "user", "sys", "wait", "idle", "physc");

        disp_util_header = 0;
    }

    /* first iteration, we only read the data, print the header and save the data */
}

while(count)
{
    collect_metrics (&oldt, &lparstats);
    sleep(interval);
    collect_metrics (&newt, &lparstats);

    data.type = UTIL_CPU_TOTAL;
    data.curstat = &newt; data.prevstat= &oldt;
    data.sizeof_data = sizeof(perfstat_cpu_total_t);
    data.cur_elems = 1;
    data.prev_elems = 1;
    rc = perfstat_cpu_util(&data, &util,sizeof(perfstat_cpu_util_t), 1);
    if(rc <= 0)
    {
        perror("Error in perfstat_cpu_util");
        exit(-1);
    }
    delta_time_base = util.delta_time;

switch(mode)
{
case UTIL_PCT:
    printf(" %5.1f %5.1f %5.1f %5.1f %5.4f \n",util.user_pct,util.kern_pct,util.wait_pct,util.idle_pct,util.physical_consumed);
    break;

case UTIL_MS:
    user_ms_purr=((util.user_pct*delta_time_base)/100.0);
    kern_ms_purr=((util.kern_pct*delta_time_base)/100.0);
    wait_ms_purr=((util.wait_pct*delta_time_base)/100.0);
    idle_ms_purr=((util.idle_pct*delta_time_base)/100.0);

    if(cpumode==UTIL_PURR)
    {
        printf(" %11u %11u %11u %11u %5.4f\n",user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,util.physical_consumed);
    }
    else if(cpumode==UTIL_SPURR)
    {
        user_ms_spurr=(user_ms_purr*util.freq_pct)/100.0;
        kern_ms_spurr=(kern_ms_purr*util.freq_pct)/100.0;
        wait_ms_spurr=(wait_ms_purr*util.freq_pct)/100.0;
        sum_ms=user_ms_spurr+kern_ms_spurr+wait_ms_spurr;
        idle_ms_spurr=delta_time_base-sum_ms;

        printf(" %11u %11u %11u %11u %5.4f\n",user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr,util.physical_consumed);
    }
    break;

case UTIL_CORE:
    user_core_purr=((util.user_pct*util.physical_consumed)/100.0);
    kern_core_purr=((util.kern_pct*util.physical_consumed)/100.0);
    wait_core_purr=((util.wait_pct*util.physical_consumed)/100.0);
    idle_core_purr=((util.idle_pct*util.physical_consumed)/100.0);
}
}
}

```

```

user_core_spurr=((user_core_purr*util.freq_pct)/100.0);
kern_core_spurr=((kern_core_purr*util.freq_pct)/100.0);
wait_core_spurr=((wait_core_purr*util.freq_pct)/100.0);

if(cpumode==UTIL_PURR)
{
printf("%5.4f %5.4f %5.4f %5.4f\n",user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr,util.physical_consumed);
}
else if(cpumode==UTIL_SPURR)
{
sum_core_spurr=user_core_spurr+kern_core_spurr+wait_core_spurr;
idle_core_spurr=util.physical_consumed-sum_core_spurr;

printf("%5.4f %5.4f %5.4f %5.4f %5.4f\n",user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,util.physical_consumed);
}
break;

default:
printf("In correct usage\n");
return;
}
count--;
}
}
#endif

```

The program displays an output that is similar to the following example output:

%user	%sys	%wait	%idle	physc	%entc	lbusy	vcs	phint
0.1	0.3	0.0	99.6	0.01	1.1	0.2	285	0
0.0	0.3	0.0	99.7	0.01	0.8	0.0	229	0
0.0	0.2	0.0	99.8	0.01	0.6	0.1	181	0
0.1	0.2	0.0	99.7	0.01	0.8	0.1	189	0
0.0	0.3	0.0	99.7	0.01	0.7	0.0	193	0
0.0	0.2	0.0	99.8	0.01	0.7	0.2	204	0
0.1	0.3	0.0	99.7	0.01	0.9	1.0	272	0
0.0	0.3	0.0	99.7	0.01	0.9	0.1	304	0
0.0	0.3	0.0	99.7	0.01	0.9	0.0	212	0

### Example for *simplempstat.c* code

This topic provides an example for using the `simplempstat.c` code.

```

#include <stdio.h>
#include <stdlib.h>
#include <unistd.h>
#include <libperfstat.h>
#include <errno.h>
#include <wpars/wparcfg.h>
static int disp_util_header = 1;

/*simplempstat.c file can be used in two modes:-
1) Auto Mode:It makes use of perfstat_cpu_util API to calculate utilization values,enable 'UTIL_AUTO' macro for
execution in auto mode.
2) Manual Mode: Calculations are done in the current code.
*/

/* #define UTIL_AUTO */

#ifdef UTIL_AUTO
#define UTIL_MS 1
#define UTIL_PCT 0
#define UTIL_CORE 2
#define UTIL_PURR 0
#define UTIL_SPURR 1
void display_metrics_global_auto(int mode,int cpumode,int count,int interval);
#endif

/* To Check whether malloc is successful or not */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
    perror ("malloc");\
    exit(2);\
} }

/* Convert 4K pages to MB */
#define AS_MB(X) ((X) * 4096/1024/1024)

/* WPAR ID for global will always be zero */
#define IS_GLOBAL(X) (!(X))

/* Non zero WPAR ID indicates WPAR */
#define IS_WPAR(X) ((X))

/* For WPAR, use NULL else use the actual WPAR ID (for global) */

```

```

#define WPAR_ID ((cid)?NULL:&wparid)

/* To store the count of Logical CPUs in the LPAR */
/* Default values for interval and count */

#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

static int ncpu, atflag;
static int returncode, count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT;
unsigned long long last_user, last_sys, last_idle, last_wait, last_timebase;
unsigned long long delta_user, delta_sys, delta_wait, delta_idle, delta_total, delta_timebase;

/* store LPAR level stats */
perfstat_cpu_total_t      *totalcinfo, *totalcinfo_last;
perfstat_memory_total_t  minfo;
perfstat_partition_total_t  pinfo, qinfo;
perfstat_cpu_t          *cinfo, *cinfo_last;

/* stores wpar id for perfstat library */
perfstat_id_wpar_t      wparid;

/* store per WPAR stats */
perfstat_wpar_total_t   winfo;
perfstat_cpu_total_wpar_t  cinfo_wpar;

/* store current WPAR ID */
cid_t cid;
char wpar[MAXCORRALNAMELEN+1];

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
char nodename[MAXHOSTNAMELEN];
int nflag = 0;
/* display the usage */

void showusage(char *cmd)
{
    if (!cid)
        fprintf(stderr, "usage: %s [-@ { ALL | WPARNAME } | -n nodename ] [-i <interval in seconds> ] [-c <number of iterations> ]\n", cmd);
    else
        fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ]\n", cmd);
    exit(1);
}

/* Save the current values for the next iteration */

void save_last_values (void)
{
    memcpy( totalcinfo_last, totalcinfo, sizeof(perfstat_cpu_total_t));
    memcpy( cinfo_last, cinfo, sizeof(perfstat_cpu_t));
}

void initialise(void)
{
    totalcinfo = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(totalcinfo);

    totalcinfo_last = (perfstat_cpu_total_t *)malloc(sizeof(perfstat_cpu_total_t));
    CHECK_FOR_MALLOC_NULL(totalcinfo_last);

    cinfo = (perfstat_cpu_t *)malloc(sizeof(perfstat_cpu_t) * ncpu);
    CHECK_FOR_MALLOC_NULL(cinfo);

    cinfo_last = (perfstat_cpu_t *)malloc(sizeof(perfstat_cpu_t) * ncpu);
    CHECK_FOR_MALLOC_NULL(cinfo_last);
}

void display_configuration (void)
{
    unsigned long long memlimit;
    double cpulimit;
    int i ,totalcpu;

    /* gather LPAR level data */
    if(nflag) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        if (perfstat_partition_total_node(&nodeid, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0) {
            perror("perfstat_partition_total_node:");
            exit(1);
        }

        if (perfstat_memory_total_node(&nodeid, &minfo, sizeof(perfstat_memory_total_t), 1) <= 0) {
            perror("perfstat_memory_total_node:");
            exit(1);
        }
    }

    totalcpu = perfstat_cpu_node(&nodeid, NULL, sizeof(perfstat_cpu_t), 0);
}

```

```

}
else {
    if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0) {
        perror("perfstat_partition_total:");
        exit(1);
    }

    if (perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1) <= 0) {
        perror("perfstat_memory_total:");
        exit(1);
    }

    totalcpu = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);
}

/* print LPAR configuration */
printf("Purr counter value = %lld \n", pinfo.purr_counter);
printf("Spurr counter value = %lld \n", pinfo.spurr_counter);
printf("Free memory = %lld \n", pinfo.real_free);
printf("Available memory = %lld \n", pinfo.real_avail);

printf("\nlpnr configuration : ");
printf("lcpus = %d ", totalcpu); /* number of CPUs online */
printf("mem = %lluMB ", AS_MB(minfo.real_total)); /* real memory */
printf("ent = %5.2f\n", (double)pinfo.entitled_proc_capacity/100.0); /* entitled capacity */
}

/*
 * NAME: display_metrics_global
 *      used to display the metrics when called from global
 */
void display_metrics_global(void)
{
    int i;
    perfstat_id_t first;

    strcpy(first.name, FIRST_CPU);
    if(nflag){
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        if (perfstat_cpu_total_node(&nodeid, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total_node:");
            exit(1);
        }

        if (perfstat_cpu_node(&nodeid, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
            perror("perfstat_cpu_node:");
            exit(1);
        }

        if (perfstat_partition_total_node(&nodeid, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
            perror("perfstat_partition_total_node:");
            exit(1);
        }
    }
    else{
        if (perfstat_cpu_total(NULL, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
            perror("perfstat_cpu_total:");
            exit(1);
        }

        if (perfstat_cpu(&first, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
            perror("perfstat_cpu:");
            exit(1);
        }

        if (perfstat_partition_total(NULL, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
            perror("perfstat_partition_total:");
            exit(1);
        }
    }
    printf("\n cpu\tuser\tsys\twait\tidle\tstate\n\n");
    while(count)
    {
        sleep(interval);

        if(nflag){
            if (perfstat_cpu_total_node(&nodeid, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
                perror("perfstat_cpu_total_node:");
                exit(1);
            }

            if (perfstat_cpu_node(&nodeid, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
                perror("perfstat_cpu_node:");
                exit(1);
            }

            if (perfstat_partition_total_node(&nodeid, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
                perror("perfstat_partition_total_node:");
            }
        }
    }
}

```

```

        exit(1);
    }
}
else{
    if (perfstat_cpu_total(NULL, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total:");
        exit(1);
    }

    if (perfstat_cpu(&first, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
        perror("perfstat_cpu:");
        exit(1);
    }

    if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
        perror("perfstat_partition_total:");
        exit(1);
    }
}

for(i = 0; i < ncpu; i++){
    delta_user = cinfo[i].puser - cinfo_last[i].puser;
    delta_sys = cinfo[i].psys - cinfo_last[i].psys;
    delta_idle = cinfo[i].pidle - cinfo_last[i].pidle;
    delta_wait = cinfo[i].pwait - cinfo_last[i].pwait;
    delta_total= delta_user + delta_sys + delta_idle + delta_wait;
    delta_timebase = pinfo.timebase_last - qinfo.timebase_last;
    if(!delta_total)
        continue;

    printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1d\n", cinfo[i].name,
           ((double)(delta_user)/(double)(delta_total) * 100.0),
           ((double)(delta_sys)/(double)(delta_total) * 100.0),
           ((double)(delta_wait)/(double)(delta_total) * 100.0),
           ((double)(delta_idle)/(double)(delta_total) * 100.0),
           cinfo[i].state);
}
delta_user = totalcinfo->puser - totalcinfo_last->puser;
delta_sys = totalcinfo->psys - totalcinfo_last->psys;
delta_wait = totalcinfo->pwait - totalcinfo_last->pwait;
delta_idle = totalcinfo->pidle - totalcinfo_last->pidle;
delta_total= delta_user + delta_sys + delta_idle + delta_wait;

printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n\n", "ALL", ((double)(delta_user)/(double)(delta_total) * 100.0),
       ((double)(delta_sys)/(double)(delta_total) * 100.0),
       ((double)(delta_wait)/(double)(delta_total) * 100.0),
       ((double)(delta_idle)/(double)(delta_total) * 100.0));

count--;
save_last_values();
}
}

/*
*NAME: display_metrics_wpar
* used to display the metrics when called from wpar
*
*/
void display_metrics_wpar(void)
{
    int i;
    char last[5];
    perfstat_id_wpar_t first;
    /*first.spec = WPARNAME;*/
    strcpy(first.name, NULL);
    if (perfstat_wpar_total( NULL, &winfo, sizeof(perfstat_wpar_total_t), 1) <= 0){
        perror("perfstat_wpar_total:");
        exit(1);
    }

    if (perfstat_cpu_total_rset(NULL, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total_rset:");
        exit(1);
    }

    if (perfstat_cpu_rset(NULL, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
        perror("perfstat_cpu_rset:");
        exit(1);
    }

    if (perfstat_partition_total(NULL, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
        perror("perfstat_partition_total:");
        exit(1);
    }
}
printf("\n cpu\tuser\tsys\twait\tidle\n\n");
while(count)
{
    sleep(interval);

    if (perfstat_cpu_total_rset(NULL, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total_rset:");
    }
}

```

```

    }
    exit(1);
}

if (perfstat_cpu_rset(NULL, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
    perror("perfstat_cpu_rset:");
    exit(1);
}

if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
    perror("perfstat_partition_total:");
    exit(1);
}

for(i=0; i<ncpu; i++){
    delta_user = cinfo[i].puser - cinfo_last[i].puser;
    delta_sys = cinfo[i].psys - cinfo_last[i].psys;
    delta_idle = cinfo[i].pidle - cinfo_last[i].pidle;
    delta_wait = cinfo[i].pwait - cinfo_last[i].pwait;
    delta_total= delta_user + delta_sys + delta_idle + delta_wait;
    delta_timebase = pinfo.timebase_last - qinfo.timebase_last;
    if(!delta_total)
        continue;

    printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n", cinfo[i].name, ((double)(delta_user)/(double)(delta_total) *
100.0),
                                                    ((double)(delta_sys)/(double)(delta_total) * 100.0),
                                                    ((double)(delta_wait)/(double)(delta_total) * 100.0),
                                                    ((double)(delta_idle)/(double)(delta_total) * 100.0));
}

delta_user = totalcinfo->puser - totalcinfo_last->puser;
delta_sys = totalcinfo->psys - totalcinfo_last->psys;
delta_wait = totalcinfo->pwait - totalcinfo_last->pwait;
delta_idle = totalcinfo->pidle - totalcinfo_last->pidle;
delta_total= delta_user + delta_sys + delta_idle + delta_wait;

if (winfo.type.b.cpu_rset)
    strcpy(last, "RST");
else
    strcpy(last, "ALL");

printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n\n", last, ((double)(delta_user)/(double)(delta_total) * 100.0),
                                                    ((double)(delta_sys)/(double)(delta_total) * 100.0),
                                                    ((double)(delta_wait)/(double)(delta_total) * 100.0),
                                                    ((double)(delta_idle)/(double)(delta_total) * 100.0));

count--;
save_last_values();
}

}

/*
 * NAME: display_metrics_wpar_from_global
 *      display metrics of wpar when called from global
 *
 */
void display_metrics_wpar_from_global(void)
{
    char last[5];
    int i;
    if (perfstat_wpar_total( &wparid, &winfo, sizeof(perfstat_wpar_total_t), 1) <= 0){
        perror("perfstat_wpar_total:");
        exit(1);
    }
    if (winfo.type.b.cpu_rset)
        strcpy(last, "RST");
    else
        strcpy(last, "ALL");

    strcpy(wparid.u.wparname, wpar);

    if (perfstat_cpu_total_rset(&wparid, totalcinfo_last, sizeof(perfstat_cpu_total_t), 1) <= 0){
        perror("perfstat_cpu_total_rset:");
        exit(1);
    }

    if (perfstat_cpu_rset(&wparid, cinfo_last, sizeof(perfstat_cpu_t), ncpu) <= 0){
        perror("perfstat_cpu_rset:");
        exit(1);
    }

    if (perfstat_partition_total(NULL, &qinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
        perror("perfstat_partition_total:");
        exit(1);
    }

    printf("\n cpu\tuser\tsys\twait\tidle\n\n");

    while(count)
    {
        sleep(interval);

```

```

if (perfstat_cpu_total_rset(&wparid, totalcinfo, sizeof(perfstat_cpu_total_t), 1) <= 0){
    perror("perfstat_cpu_total_rset:");
    exit(1);
}

if (perfstat_cpu_rset(&wparid, cinfo, sizeof(perfstat_cpu_t), ncpu) <= 0){
    perror("perfstat_cpu_rset:");
    exit(1);
}

if (perfstat_partition_total(NULL, &pinfo, sizeof(perfstat_partition_total_t), 1) <= 0){
    perror("perfstat_partition_total:");
    exit(1);
}

for(i = 0; i < ncpu; i++){
    delta_user = cinfo[i].puser - cinfo_last[i].puser;
    delta_sys = cinfo[i].psys - cinfo_last[i].psys;
    delta_idle = cinfo[i].pidle - cinfo_last[i].pidle;
    delta_wait = cinfo[i].pwait - cinfo_last[i].pwait;
    delta_total= delta_user + delta_sys + delta_idle + delta_wait;
    delta_timebase = pinfo.timebase_last - qinfo.timebase_last;
    if(!delta_total)
        continue;

    printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n",cinfo[i].name,((double)(delta_user)/(double)(delta_total) * 100.0),
        ((double)(delta_sys)/(double)(delta_total) * 100.0),
        ((double)(delta_wait)/(double)(delta_total) * 100.0),
        ((double)(delta_idle)/(double)(delta_total) * 100.0));
}

delta_user = totalcinfo->puser - totalcinfo_last->puser;
delta_sys = totalcinfo->psys - totalcinfo_last->psys;
delta_wait = totalcinfo->pwait - totalcinfo_last->pwait;
delta_idle = totalcinfo->pidle - totalcinfo_last->pidle;
delta_total= delta_user + delta_sys + delta_idle + delta_wait;

printf("%s\t%#4.1f\t%#4.1f\t%#4.1f\t%#4.1f\n",last, ((double)(delta_user)/(double)(delta_total) * 100.0),
        ((double)(delta_sys)/(double)(delta_total) * 100.0),
        ((double)(delta_wait)/(double)(delta_total) * 100.0),
        ((double)(delta_idle)/(double)(delta_total) * 100.0));

count--;
save_last_values();
}
}

#ifdef UTIL_AUTO
void display_metrics_global_auto(int mode,int cpumode,int count,int interval)
{
    float user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr;
    float user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,sum_core_spurr;
    u_longlong_t user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,sum_ms;
    u_longlong_t user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr;
    perfstat_rawdata_t data;
    u_longlong_t delta_purr;
    double phys_proc_consumed, entitlement, percent_ent, delta_sec;
    perfstat_partition_total_t lparstats;
    static perfstat_cpu_t *oldt,*newt;
    perfstat_cpu_util_t *util;
    int rc,cpu_count,i;
    perfstat_id_t id;

    /* retrieve the metrics */
while(count) {
    /* Print the header for utilization metrics (only once) */
    if (disp_util_header) {
        if(mode==UTIL_PCT)
            printf("\nCPU %5s %5s %6s %6s %5s \n",
                "%user", "%sys", "%wait", "%idle", "physc");
        else if(mode==UTIL_MS)
            printf("\nCPU %5s %5s %6s %6s %5s \n",
                "user(ms)", "sys(ms)", "wait(ms)", "idle(ms)", "physc");
        else if(mode==UTIL_CORE)
            printf("\nCPU %5s %5s %6s %6s %5s %5s \n",
                "user", "sys", "wait", "idle", "physc", "state");

        /* first iteration, we only read the data, print the header and save the data */
    }
    cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

    /* check for error */
    if(cpu_count <= 0)
    {
        perror("Error in perfstat_cpu");
        exit(-1);
    }
}
}

```

```

/* allocate enough memory */
oldt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
if(oldt == NULL)
{
    perror("Memory Allocation Error");
    exit(-1);
}
/* set name to first cpu */
strcpy(id.name,FIRST_CPU);

/* ask to get all the structures available in one call */
rc = perfstat_cpu(&id, oldt, sizeof(perfstat_cpu_t), cpu_count);

/* check for error */
if(rc <=0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}

data.type = UTIL_CPU;
data.prevstat= oldt;
data.sizeof_data = sizeof(perfstat_cpu_t);
data.prev_elems = cpu_count;

sleep(interval);

/* Check how many perfstat_cpu_t structures are available after a defined period */
cpu_count = perfstat_cpu(NULL, NULL,sizeof(perfstat_cpu_t),0);

/* Check for error */
if(cpu_count <= 0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}

data.cur_elems = cpu_count;

if(data.prev_elems != data.cur_elems)
{
    perror("The number of CPUs has become different for defined period");
    exit(-1);
}

/* allocate enough memory */
newt = (perfstat_cpu_t *)calloc(cpu_count,sizeof(perfstat_cpu_t));
util = (perfstat_cpu_util_t *)calloc(cpu_count,sizeof(perfstat_cpu_util_t));

if(newt == NULL || util == NULL)
{
    perror("Memory Allocation Error");
    exit(-1);
}
data.curstat = newt;
rc = perfstat_cpu(&id, newt, sizeof(perfstat_cpu_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu");
    exit(-1);
}

/* Calculate CPU Utilization Metrics*/
rc = perfstat_cpu_util(&data, util, sizeof(perfstat_cpu_util_t), cpu_count);
if(rc <= 0)
{
    perror("Error in perfstat_cpu_util");
    exit(-1);
}

```

```

switch(mode)
{
    case UTIL_PCT:
        for(i=0;i<cpu_count;i++)
            printf("%d %5.1f %5.1f %5.1f %5.1f %5.7f\n",i,util[i].user_pct,util[i].kern_pct,util[i].wait_pct,util[i].idle_pct,util[i].physical_consumed);
        break;

    case UTIL_MS:
        for(i=0;i<cpu_count;i++)
        {
            user_ms_purr=((util[i].user_pct*util[i].delta_time)/100.0);
            kern_ms_purr=((util[i].kern_pct*util[i].delta_time)/100.0);
            wait_ms_purr=((util[i].wait_pct*util[i].delta_time)/100.0);
            idle_ms_purr=((util[i].idle_pct*util[i].delta_time)/100.0);
            if(cpumode==UTIL_PURR)
            {
                printf("%d\t %llu\t %llu\t %llu\t %llu\t\n",i,user_ms_purr,kern_ms_purr,wait_ms_purr,idle_ms_purr,util[i].physical_consumed);
            }
            else if(cpumode==UTIL_SPURR)

```

```

    {
        user_ms_spurr=(user_ms_purr*util[i].freq_pct)/100.0;
        kern_ms_spurr=(kern_ms_purr*util[i].freq_pct)/100.0;
        wait_ms_spurr=(wait_ms_purr*util[i].freq_pct)/100.0;
        sum_ms=user_ms_spurr+kern_ms_spurr+wait_ms_spurr;
        idle_ms_spurr=util[i].delta_time-sum_ms;

        printf("%d\t %llu\t %llu\t %llu\t %llu\t %5.4f\n",i,user_ms_spurr,kern_ms_spurr,wait_ms_spurr,idle_ms_spurr,util[i].physical_consumed);
    }
    break;
case UTIL_CORE:
    for(i=0;i<cpu_count;i++)
    {
        user_core_purr=((util[i].user_pct*util[i].physical_consumed)/100.0);
        kern_core_purr=((util[i].kern_pct*util[i].physical_consumed)/100.0);
        wait_core_purr=((util[i].wait_pct*util[i].physical_consumed)/100.0);
        idle_core_purr=((util[i].idle_pct*util[i].physical_consumed)/100.0);

        user_core_spurr=((user_core_purr*util[i].freq_pct)/100.0);
        kern_core_spurr=((kern_core_purr*util[i].freq_pct)/100.0);
        wait_core_spurr=((wait_core_purr*util[i].freq_pct)/100.0);

        if(cpumode==UTIL_PURR)
        {
            printf("%d %5.4f %5.4f %5.4f %5.4f\n",i,user_core_purr,kern_core_purr,wait_core_purr,idle_core_purr,util[i].physical_consumed);
        }

        else if(cpumode==UTIL_SPURR)
        {
            sum_core_spurr=user_core_spurr+kern_core_spurr+wait_core_spurr;
            idle_core_spurr=util[i].physical_consumed-sum_core_spurr;

            printf("%d %5.4f %5.4f %5.4f %5.4f %5.4f\n",i,user_core_spurr,kern_core_spurr,wait_core_spurr,idle_core_spurr,util[i].physical_consumed);
        }
    }
    break;
default:
    printf("In correct usage\n");
    return;
}
count--;
}
#endif

```

```

/*
 *NAME: main
 */
int main(int argc,char* argv[])
{
    int c, rc;
    int mode,cpumode;

    cid = corral_getcid();

    while((c = getopt(argc, argv, "@:n:i:c:")!= EOF){
        switch(c)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of interations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                nflag = 1;
                break;
            case '@': /* Per-WPAR stats */
                if (IS_WPAR(cid))
                    showusage(argv[0]);
                atflag = 1;
                strcpy(wpar, optarg);
                break;
            default: /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }
    if (nflag && atflag){
        showusage(argv[0]);
    }
    if(nflag)
    { /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
}

```

```

    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}
if (atflag){
    wparid.spec = WPARNAME;
    strncpy(wparid.u.wparname,wpar);
    ncpu = perfstat_cpu_rset (&wparid, NULL, sizeof(perfstat_cpu_t), 0);
}
else if (nflag){
    nodeid.spec = NODENAME;
    strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
    ncpu = perfstat_cpu_node(&nodeid, NULL, sizeof(perfstat_cpu_t), 0);
}
else if (IS_GLOBAL(cid)){
    ncpu = perfstat_cpu(NULL, NULL, sizeof(perfstat_cpu_t), 0);
}
else{
    ncpu = perfstat_cpu_rset(NULL, NULL, sizeof(perfstat_cpu_t), 0);
}

initialise();
display_configuration();

if(atflag)
    display_metrics_wpar_from_global();
else if (cid)
    display_metrics_wpar();
else
    #ifndef UTIL_AUTO
        printf("Enter CPU mode.\n");
        printf(" 0 PURR \n 1 SPURR \n");
        scanf("%d",&cpumode);
        printf("Enter print mode.\n");
        printf(" 0 PERCENTAGE\n 1 MILLISECONDS\n 2 CORES \n");
        scanf("%d",&mode);

        if((mode>2)&& (cpumode>1))
        {
            printf("Error: Invalid Input\n");
            exit(0);
        }
        display_metrics_global_auto(mode,cpumode,count,interval);
        #else
        display_metrics_global();
        #endif
    if(nflag)
    { /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
return(0);
}

```

The program displays an output that is similar to the following example output:

```

Purr counter value = 54500189780
Spurr counter value = 54501115744
Free memory = 760099
Available memory = 758179

lpar configuration : lcpus = 8 mem = 4096MB ent = 1.00

  cpu   user   sys   wait   idle   state
cpu0    26.8   54.9   0.0    18.3    1
cpu1     0.0    2.3    0.0    97.7    1
cpu2     0.0    4.7    0.0    95.3    1
cpu3     0.0    2.5    0.0    97.5    1
cpu4     0.0   49.6    0.0    50.4    1
cpu5     0.0   12.7    0.0    87.3    1
cpu6     0.0   10.5    0.0    89.5    1
cpu7     0.0   10.7    0.0    89.3    1
ALL     10.7   24.9    0.0    64.4

```

## perfstat\_diskadapter Interface

The **perfstat\_diskadapter** interface returns a set of structures of type **perfstat\_diskadapter\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_diskadapter\_t** structure include:

Item	Descriptor
<b>name</b>	Adapter name (from ODM)
<b>description</b>	Adapter description (from ODM)
<b>size</b>	Total disk size connected to this adapter (in MB)
<b>free</b>	Total free space on disks connected to this adapter (in MB)
<b>xfers</b>	Total transfers to/from this adapter (in KB)

Several other disk adapter-related metrics (such as the number of blocks read from and written to the adapter) are also returned. For a complete list, see the **perfstat\_diskadapter\_t** section in the [libperfstat.h](#) header file.

The following program emulates the **diskadapterstat** behavior and also shows an example of how the **perfstat\_diskadapter** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <string.h>
#include <errno.h>
#include <libperfstat.h>
#include <errno.h>
#include <wpar/wparcfg.h>

/* Non zero WPAR ID indicates WPAR */
#define IS_WPAR(X) ((X))

/* To Check whether malloc is successful or not */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
                                }

/* Default values for interval and count */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* Function prototypes */

static int do_initialization(void);
static void do_cleanup(void);
static void collect_disk_metrics(void);
static void print_disk_header(void);
static void showusage(Char *);

/* variables and data structures declaration */

static perfstat_diskadapter_t *statp, *statq;
static int num_adapt;
static int interval = INTERVAL_DEFAULT;
static int count = COUNT_DEFAULT;
static int rc;

/* support for remote node statistics collection in a cluster environment */
static perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

cid_t cid;          /* store the WPAR cid */

/*
 * NAME: do_initialization
 *      This function initializes the data structures.
 *      It also collects initial set of values.
 *
 * RETURNS:
 * On successful completion:
 * - returns 0.
 * In case of error
 * - exit with code 1.
 */

static int do_initialization(void)
{
    if (collect_remote_node_stats){
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        /* Get the total number of disk adapters available in the current system */
        num_adapt = perfstat_diskadapter_node(&nodeid, NULL, sizeof(perfstat_diskadapter_t), 0);
    }
}
```

```

}
else{
    /* Get the total number of disk adapters available in the current system */
    num_adapt = perfstat_diskadapter(NULL, NULL, sizeof(perfstat_diskadapter_t), 0);
}

if (num_adapt == 0) {
    printf("There are no disk adapters.\n");
    exit(0);
}

if (num_adapt < 0) {
    perror("perfstat_diskadapter: ");
    exit(1);
}

/* Allocate sufficient memory for perfstat structures */

statp = (perfstat_diskadapter_t *)malloc(sizeof(perfstat_diskadapter_t) * num_adapt);
CHECK_FOR_MALLOC_NULL(statp);

statq = (perfstat_diskadapter_t *)malloc(sizeof(perfstat_diskadapter_t) * num_adapt);
CHECK_FOR_MALLOC_NULL(statq);

/* Make the structures as 0 */
memset(statq, 0, (sizeof(perfstat_diskadapter_t) * num_adapt));

memset(statp, 0, (sizeof(perfstat_diskadapter_t) * num_adapt));

return (0);
}

/*
 *NAME: Showusage
 *      This function displays the usage
 */

void showusage (char *cmd)
{
    fprintf (stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ]\n", cmd);
    exit(1);
}

/*
 * NAME: do_cleanup
 *      This function frees the memory allocated for the perfstat structures.
 */

static void do_cleanup(void)
{
    if (statp) {
        free(statp);
    }

    if (statq) {
        free(statq);
    }
}

/*
 * NAME: collect_diskadapter_metrics
 *      This function collects the raw values in to
 *      the specified structures and derive the metrics from the
 *      raw values
 */

void collect_diskadapter_metrics(void)
{
    perfstat_id_t first;
    unsigned long long delta_read, delta_write, delta_xfers, delta_xrate;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        strncpy(nodeid.name, FIRST_DISKADAPTER);
        rc = perfstat_diskadapter_node(&nodeid ,statq, sizeof(perfstat_diskadapter_t), num_adapt);
    }
    else {
        strncpy(first.name, FIRST_DISKADAPTER);
        rc = perfstat_diskadapter(&first ,statq, sizeof(perfstat_diskadapter_t), num_adapt);
    }

    if (rc < num_adapt){
        perror("perfstat_diskadapter: ");
        exit(1);
    }
}

```

```

/* Name - name of the diskadapter
 * Disks- number of disks connected
 * Size - total size of all the disks
 * Free - free space on disk
 * ARS - average read per second
 * AWS - average write per second
 */

printf("\n%-8s %7s %8s %8s %8s %8s\n", " Name ", " Disks ", " Size ", " Free ", " ARS ", " AWS ");
printf("%-8s %7s %8s %8s %8s %8s\n", "=====", "=====", "=====", "=====", "=====", "=====");

while (count > 0) {
    sleep(interval);

    if(collect_remote_node_stats) {
        rc = perfstat_diskadapter_node(&nodeid, statp, sizeof(perfstat_diskadapter_t), num_adapt);
    }
    else {
        rc = perfstat_diskadapter(&first, statp, sizeof(perfstat_diskadapter_t), num_adapt);
    }

    if (rc < num_adapt ) {
        perror("perfstat_diskadapter:");
        exit(-1);
    }

    /* print statistics for each of the diskadapter */
    for (int i = 0; i < rc; i++) {
        delta_write = statp[i].wblks - statq[i].wblks;
        delta_read = statp[i].rblks - statq[i].rblks;
        delta_xfers = statp[i].xfers - statq[i].xfers;
        delta_xrate = statp[i].xrate - statq[i].xrate;

        printf("%-8s %7d %8llu %8llu %8llu %8llu\n", statp[i].name, statp[i].number,
            statp[i].size, statp[i].free, (u_longlong_t)(delta_read / (statp[i].xrate - statq[i].xrate)),
            (u_longlong_t)(delta_write / (delta_xfers - delta_xrate)));
    }

    /* copy to the old data structures */
    memcpy(statq, statp, sizeof(perfstat_diskadapter_t) * num_adapt);
    count--;
    printf("\n");
}
/* Free all the memory allocated for all the data structures */
do_cleanup();
}

/*
 *NAME: main
 *
 */

int main(int argc, char* argv[])
{
    int i;
    cid = corral_getcid();

    /* Check Whether running Inside WPAR or on Global*/
    if(IS_WPAR(cid)) {
        printf("The metrics requested for WPAR cannot be retrieved.\n");
        exit(1);
    }

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i':
                /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c':
                /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n':
                /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
}

```

```

if (rc == -1)
{
    perror("cluster statistics collection is not available");
    exit(-1);
}
}
do_initialization();
/* call the functions to collect the metrics and display them */
collect_diskadapter_metrics();

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
return (0);
}

```

The program displays an output that is similar to the following example output:

Name	Disks	Size	Free	ARS	AWS
=====	=====	=====	=====	=====	=====
vscsi0	1	25568	19616	1	9

## perfstat\_disk Interface

The **perfstat\_disk** interface returns a set of structures of type **perfstat\_disk\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_disk\_t** structure include:

Item	Descriptor
<b>name</b>	Disk name (from ODM)
<b>description</b>	Disk description (from ODM)
<b>vgname</b>	Volume group name (from ODM)
<b>size</b>	Disk size (in MB)
<b>free</b>	Free space (in MB)
<b>xfers</b>	Transfers to/from disk (in KB)

Several other disk-related metrics (such as number of blocks read from and written to disk, and adapter names) are also returned. For a complete list, see the **perfstat\_disk\_t** section in the [libperfstat.h](#) header file in *Files Reference*.

The following program emulates **diskstat** behavior and also shows an example of how the **perfstat\_disk** interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_disk_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_disk_t structures are available */
    tot = perfstat_disk(NULL, NULL, sizeof(perfstat_disk_t), 0);

    /* check for error */
    if (tot < 0)
    {
        perror("perfstat_disk");
        exit(-1);
    }
    if (tot == 0)
    {
        printf("No disks found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */

```

```

statp = calloc(tot, sizeof(perfstat_disk_t));

/* set name to first interface */
strcpy(first.name, FIRST_DISK);

/* ask to get all the structures available in one call */
/* return code is number of structures returned */
ret = perfstat_disk(&first, statp,
                  sizeof(perfstat_disk_t), tot);

/* check for error */
if (ret <= 0)
{
    perror("perfstat_disk");
    exit(-1);
}

/* print statistics for each of the disks */
for (i = 0; i < ret; i++) {
    printf("\nStatistics for disk : %s\n", statp[i].name);
    printf("-----\n");
    printf("description           : %s\n", statp[i].description);
    printf("volume group name        : %s\n", statp[i].vgname);
    printf("adapter name             : %s\n", statp[i].adapter);
    printf("size                     : %llu MB\n", statp[i].size);
    printf("free space               : %llu MB\n", statp[i].free);
    printf("number of blocks read    : %llu blocks of %llu bytes\n", statp[i].rblks,
statp[i].bsize);
    printf("number of blocks written : %llu blocks of %llu bytes\n", statp[i].wblks,
statp[i].bsize);
}
}

```

The preceding program produces the following output:

```

Statistics for disk : hdisk1
-----
description           : 16 Bit SCSI Disk Drive
volume group name    : rootvg
adapter name         : scsi0
size                 : 4296 MB
free space           : 2912 MB
number of blocks read : 403946 blocks of 512 bytes
number of blocks written : 768176 blocks of 512 bytes

Statistics for disk : hdisk0
-----
description           : 16 Bit SCSI Disk Drive
volume group name    : None
adapter name         : scsi0
size                 : 0 MB
free space           : 0 MB
number of blocks read : 0 blocks of 512 bytes
number of blocks written : 0 blocks of 512 bytes

Statistics for disk : cd0
-----
description           : SCSI Multimedia CD-ROM Drive
volume group name    : not available
adapter name         : scsi0
size                 : 0 MB
free space           : 0 MB
number of blocks read : 3128 blocks of 2048 bytes
number of blocks written : 0 blocks of 2048 bytes

```

## perfstat\_diskpath Interface

The **perfstat\_diskpath** interface returns a set of structures of type **perfstat\_diskpath\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_diskpath\_t** structure include:

Item	Descriptor
<b>name</b>	Path name (<disk_name>_Path<path_id>)
<b>xfers</b>	Total transfers through this path (in KB)

Item	Descriptor
<b>adapter</b>	Name of the adapter linked to the path

Several other disk path-related metrics (such as the number of blocks read from and written through the path) are also returned. For a complete list, see the **perfstat\_diskpath\_t** section in the [libperfstat.h](#) header file.

The following code shows an example of how the **perfstat\_diskpath** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int ret, tot, i;
    perfstat_diskpath_t *statp;
    perfstat_id_t first;
    char *substring;
    perfstat_disk_t dstat;

    /* check how many perfstat_diskpath_t structures are available */
    tot = perfstat_diskpath(NULL, NULL, sizeof(perfstat_diskpath_t), 0);

    /* check for error */
    if (tot < 0)
    {
        perror("perfstat_diskpath");
        exit(-1);
    }

    if (tot == 0)
    {
        printf("No Paths found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_diskpath_t));
    if(statp==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* set name to first interface */
    strcpy(first.name, FIRST_DISKPATH);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_diskpath(&first, statp, sizeof(perfstat_diskpath_t), tot);

    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_diskpath");
        exit(-1);
    }

    /* print statistics for each of the disk paths */
    for (i = 0; i < ret; i++) {
        printf("\nStatistics for disk path : %s\n", statp[i].name);
        printf("-----\n");
        printf("number of blocks read      : %llu\n", statp[i].rblks);
        printf("number of blocks written   : %llu\n", statp[i].wblks);
        printf("adapter name                : %s\n", statp[i].adapter);
    }

    /* retrieve paths for last disk if any */
    if (ret > 0) {
        /* extract the disk name from the last disk path name */
        substring = strstr(statp[ret-1].name, "_Path");
        if (substring == NULL) {
            return (-1);
        }
        substring[0] = '\0';
    }
}
```

```

/* set name to the disk name */
strcpy(first.name, substring);
/* retrieve info about disk */
ret = perfstat_disk(&first, &dstat, sizeof(perfstat_disk_t),1);

if (ret <= 0)
{
    perror("perfstat_diskpath");
    exit(-1);
}

printf("\nPaths for disk path : %s (%d)\n", dstat.name, dstat.paths_count);
printf("-----\n");

/* retrieve all paths for this disk */
ret = perfstat_diskpath(&first, statp, sizeof(perfstat_diskpath_t), dstat.paths_count);
if (ret <= 0)
{
    perror("perfstat_diskpath");
    exit(-1);
}

/* print statistics for each of the paths */
for (i = 0; i < ret; i++) {
    printf("\nStatistics for disk path : %s\n", statp[i].name);
    printf("-----\n");
    printf("number of blocks read      : %llu\n", statp[i].rblks);
    printf("number of blocks written   : %llu\n", statp[i].wblks);
    printf("adapter name                : %s\n", statp[i].adapter);
}
}
}

```

The program displays an output that is similar to the following example output:

```

Statistics for disk path : hdisk0_Path0
-----
number of blocks read      : 335354
number of blocks written   : 291416
adapter name                : vscsi0

Paths for disk path : hdisk0 (1)
-----

Statistics for disk path : hdisk0_Path0
-----
number of blocks read      : 335354
number of blocks written   : 291416
adapter name                : vscsi0

```

## perfstat\_fcstat Interface

The **perfstat\_fcstat** interface returns a set of structures of type **perfstat\_fcstat\_t**, which is defined in the **libperfstat.h** file.

The following program is an example of how the **perfstat\_fcstat** interface is used:

```

/* The sample program displays the metrics *
 * related to every individual *
 * Fiber Channel adapter in the LPAR */
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
}

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot=0;
int returncode=0;

/* store the data structures */
static perfstat_fcstat_t *statp=NULL, *statq=NULL;

/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

```

```

unsigned long long wwpn_id=0;
int fc_flag=0, wwpn_flag=0;
char fcadapter_name[MAXHOSTNAMELEN];
/*
 * NAME: showusage
 *       to display the usage
 *
 */
void showusage(char *cmd)
{
    fprintf(stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the cluster> ] [-a FC adapter name] [-w worldwide port
name]] \n", cmd);
    exit(1);
}
/*

```

```

* NAME: do_initialization
*       This function initializes the data structures.
*       It also collects the initial set of values.
*
* RETURNS:
* On successful completion:
* - returns 0.
* In case of error
* - exits with code 1.
*/

int do_initialization(void)
{
    /* check how many perfstat_fcstat_t structures are available */
    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_fcstat_node(&nodeid, NULL, sizeof(perfstat_fcstat_t), 0)
;
    }
    else if(fc_flag == 1 && wwpn_flag == 1)
    {
        tot = perfstat_fcstat_wwpn(NULL, NULL, sizeof(perfstat_fcstat_t), 0);
        if(tot >= 1)
        {
            tot = 1;
        }
    }
    else
    {
        printf("There is no FC adapter \n");
        exit(-1);
    }
}
else
{
    tot = perfstat_fcstat(NULL, NULL, sizeof(perfstat_fcstat_t), 0);
}
if (tot <= 0) {
    printf("There is no FC adapter\n");
    exit(0);
}

/* allocate enough memory for all the structures */

statp = (perfstat_fcstat_t *)malloc(tot * sizeof(perfstat_fcstat_t));
CHECK_FOR_MALLOC_NULL(statp);

statq = (perfstat_fcstat_t *)malloc(tot * sizeof(perfstat_fcstat_t));
CHECK_FOR_MALLOC_NULL(statq);
return(0);
}

/*
 *Name: display_metrics
 *       collect the metrics and display them
 *
 */
void display_metrics()
{
    perfstat_id_t first;
    perfstat_wwpn_id_t wwpn;
    int ret=0, i=0;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strncpy(nodeid.name , FIRST_NETINTERFACE);
        ret = perfstat_fcstat_node(&nodeid, statq, sizeof(perfstat_fcstat_t), tot);
    } else if((fc_flag == 1) && (wwpn_flag == 1)) {

```

```

        strcpy(wwpn.name , fcadapter_name);
        wwpn.initiator_wwpn_name = wwpn_id;
        ret = perfstat_fcstat_wwpn( &wwpn, statq, sizeof(perfstat_fcstat_t), tot);
    }
else
{
    strcpy(first.name , FIRST_NETINTERFACE);
    ret = perfstat_fcstat( &first, statq, sizeof(perfstat_fcstat_t), tot);
}
if (ret < 0)
{
    free(statp);
    free(statq);
    perror("perfstat_fcstat: ");
    exit(1);
}
while (count)
{
    sleep (interval);
if(collect_remote_node_stats) {
    ret = perfstat_fcstat_node(&nodeid, statp, sizeof(perfstat_fcstat_t), tot);
}
if((fc_flag == 1) && (wwpn_flag == 1))
{
    strcpy(wwpn.name , fcadapter_name);
    wwpn.initiator_wwpn_name = wwpn_id;
    ret = perfstat_fcstat_wwpn(&wwpn, statp, sizeof(perfstat_fcstat_t), tot);
}
else
{
    ret = perfstat_fcstat(&first, statp, sizeof(perfstat_fcstat_t), tot);
}
/* print statistics for the Fiber channel */
for (i = 0; i < ret; i++) {
    printf(" FC Adapter name: %s \n", statp[i].name);
    printf(" ===== Traffic Statistics =====\n");
    printf(" Number of Input Requests: %lld \n",
    statp[i].InputRequests - statq[i].InputRequests);
    printf(" Number of Output Requests: %lld \n",
    statp[i].OutputRequests - statq[i].OutputRequests);
    printf(" Number of Input Bytes : %lld \n",
    statp[i].InputBytes - statq[i].InputBytes);
    printf(" Number of Output Bytes : %lld \n",
    statp[i].OutputBytes - statq[i].OutputBytes);
    printf(" ===== Transfer Statistics =====\n");
    printf(" Adapter's Effective Maximum Transfer Value : %lld \n",
    statp[i].EffMaxTransfer - statq[i].EffMaxTransfer);
    printf(" ===== Driver Statistics
=====
\n");
    printf(" Count of DMA failures: %lld \n",
    statp[i].NoDMAResourceCnt - statq[i].NoDMAResourceCnt);
    printf(" No command resource available :%lld \n",
    statp[i].NoCmdResourceCnt - statq[i].NoCmdResourceCnt);
    printf(" Link Indicator : %d \n", statp[i].AttentionType);
    printf(" ===== CHBA Statistics
=====
\n");
    printf(" Seconds since last reset of the statistics on the adapter: %lld \n",
    statp[i].SecondsSinceLastReset - statq[i].SecondsSinceLastReset);
    printf(" Number of frames transmitted: %lld \n",
    statp[i].TxFrames - statq[i].TxFrames);
    printf(" Fiber Channel Kbytes transmitted : %lld \n",
    statp[i].TxWords - statq[i].TxWords);
    printf(" Number of Frames Received.: %lld \n",
    statp[i].RxFrames - statq[i].RxFrames);
    printf(" Fiber Channel Kbytes Received : %lld \n",
    statp[i].RxWords - statq[i].RxWords);
    printf(" Loop Initialization Protocol(LIP) Count: %lld \n",
    statp[i].LIPCount - statq[i].LIPCount);
    printf(" NOS(Not_Operational) Count : %lld \n",
    statp[i].NOSCount - statq[i].NOSCount);
    printf(" Number of frames received with the CRC Error : %lld \n",
    statp[i].ErrorFrames - statq[i].ErrorFrames);
    printf(" Number of lost frames : %lld \n",
    statp[i].DumpedFrames - statq[i].DumpedFrames);
    printf(" Count of Link failures: %lld \n",
    statp[i].LinkFailureCount - statq[i].LinkFailureCount);
    printf(" Count of loss of sync : %lld \n",
    statp[i].LossOfSyncCount - statq[i].LossOfSyncCount);
    printf(" Count of loss of Signal:%lld \n",
    statp[i].LossOfSignal - statq[i].LossOfSignal);
    printf(" Number of times a primitive sequence was in error :%lld \n",
    statp[i].PrimitiveSeqProtocolErrCount - statq[i].PrimitiveSeqProtocolErrCount);
}
}

```

```

        printf(" Count of Invalid Transmission words received : %lld \n",
        statp[i].InvalidTxWordCount - statq[i].InvalidTxWordCount);
        printf(" Count of CRC Errors in a Received Frame :%lld \n",
        statp[i].InvalidCRCCount - statq[i].InvalidCRCCount);
        printf(" SCSI Id of the adapter : %lld \n",
        statp[i].PortFcId);
        printf(" Speed of Adapter in GBIT : %lld \n",
        statp[i].PortSpeed);
        printf(" Connection Type: %s \n",
        statp[i].PortType);
        printf(" worldwide port name : %lld \n",
        statp[i].PortWWN);
        printf(" Supported Port Speed in GBIT: %lld \n",
        statp[i].PortSupportedSpeed);

        printf(" ===== End =====\n");
    }
    memcpy(statq, statp, (tot * sizeof(perfstat_fcstat_t)));
    count--;
}
}
/*
 *Name: main
 *
 */
int main(int argc, char *argv[])
{
    int i=0, rc=0;
    /* get the interval and count values */

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:a:w")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of interations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            case 'a': /* Fiber Channel Adapter Name */
                strncpy(fcadapter_name, optarg, MAXHOSTNAMELEN);
                fcadapter_name[MAXHOSTNAMELEN-1] = '\0';
                fc_flag = 1;
                break;
            case 'w': /* Worldwide port name(WWPN) */
                wwpn_id = (unsigned long long) (atoll(optarg));
                wwpn_flag = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                showusage(argv[0]);
        }
    }

    if((fc_flag == 1))
    {
        if(fcadapter_name == NULL )
        {
            fprintf(stderr, "FC adapter Name should not be NULL");
            exit(-1);
        }
    }

    if(wwpn_flag == 1)
    {
        if(wwpn_id < 0 )
        {
            fprintf(stderr, "WWPN id should not be negavite ");

```

```

        exit(-1);
    }
}

if(collect_remote_node_stats)
{
    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
    }
}

exit(-1);
}

do_initialization();
display_metrics();

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
free(statp);
free(statq);
return 0;
}
}

```

## perfstat\_hfistat\_window Interface

The **perfstat\_hfistat\_window** interface returns a set of structures of type **perfstat\_hfistat\_window\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_hfistat\_window\_t** structure include:

Item	Descriptor
<b>pkts_sent</b>	The number of packets sent (56 bit counter).
<b>pkts_dropped_sending</b>	The number of packets that were dropped from sending (40 bit counter).
<b>pkts_received</b>	The number of the packets that were received (56 bit counter).

## perfstat\_hfistat Interface

The **perfstat\_hfistat** interface returns a set of structures of type **perfstat\_hfistat\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_hfistat\_t** structure include:

Item	Descriptor
<b>cycles_blocked_sending</b>	The cycles that are blocked from sending.
<b>link_retries</b>	The number of retries at the Link Level.
<b>pkts_sent</b>	The aggregate number of the packet sent.
<b>pkts_dropped_sending</b>	The number of packets that were at the sent first in first out (FIFO), but dropped (not sent), regardless of window.
<b>mmu_cache_hits</b>	The memory hits from the Nest Memory Management Unit Cache.
<b>mmu_cache_misses</b>	The hits that were missed from the Nest Memory Management Unit Cache.
<b>cycles_waiting_on_a_credit</b>	The cycles that are waiting on credit.

## perfstat\_logicalvolume Interface

The **perfstat\_logicalvolume** interface returns a set of structures of type **perfstat\_logicalvolume\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_logicalvolume\_t** structure include:

Item	Descriptor
<b>Ppsize</b>	Physical partition size (in MB)
<b>Iocnt</b>	Number of read and write requests
<b>Kbreads</b>	Number of kilobytes read
<b>Kbwrites</b>	Number of kilobytes written

Several other paging-space-related metrics (such as name, type, and active) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_logicalvolume\_t** section in the **libperfstat.h** header file in *Files Reference*.

**Note:** The **perfstat\_config (PERFSTAT\_ENABLE | PERFSTAT\_LV, NULL)** must be used to enable the logical volume statistical collection.

The following code shows an example of how the **perfstat\_logicalvolume** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
int lv_count,i, rc;
perfstat_id_t first;
perfstat_logicalvolume_t *lv;

strcpy(first.name,NULL);

/* enable the logical volume statistical collection */
perfstat_config(PERFSTAT_ENABLE | PERFSTAT_LV,NULL);

/* get the number of logical volumes */
lv_count = perfstat_logicalvolume (NULL, NULL, sizeof(perfstat_logicalvolume_t), 0);

/* check the subroutine return code for any error */
if (lv_count == -1){
    perror("perfstat_logicalvolume");
    exit(-1);
}

/* Allocate enough memory to hold all the structures */
lv = (perfstat_logicalvolume_t *)calloc(lv_count, sizeof(perfstat_logicalvolume_t));
if (lv == NULL){
    perror(".malloc");
    exit(-1);
}

/* Call the API to get the data */
rc = perfstat_logicalvolume(&first,(perfstat_logicalvolume_t*)lv,
sizeof(perfstat_logicalvolume_t),lv_count);

/* check the return code for any error */
if (rc == -1){
    perror("perfstat_logical volume ");
    exit(-1);
}

for(i=0;i<lv_count;i++){
    printf("\n");
    printf("Logical volume name=%s\n",lv[i].name);
    printf("Volume group name=%s\n",lv[i].vgname);
    printf("Physical partition size in MB=%lld\n",lv[i].ppsize);
    printf("total number of logical partitions configured for this logical
volume=%lld\n",lv[i].logical_partitions);
    printf("number of physical mirrors for each logical partition=%lu\n",lv[i].mirrors);
    printf("Number of read and write requests=%lu\n",lv[i].iocnt);
```

```

printf("Number of Kilobytes read=%lld\n",lv[i].kbreads);
printf("Number of Kilobytes written=%lld\n",lv[i].kbwrites);
}

/* disable logical volume statistical collection */
perfstat_config(PERFSTAT_DISABLE | PERFSTAT_LV , NULL);
}

```

The program displays an output that is similar to the following example output:

```

Logical volume name=hd5
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd6
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=16
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd8
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd4
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=2
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd2
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=31
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd9var
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd10opt
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd3
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=4
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

```

```

Logical volume name=hd1
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=74
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=hd11admin
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=4
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=lg_dumplv
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=32
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=livedump
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=8
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=fslv00
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=3
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

Logical volume name=fslv01
Volume group name=rootvg
Physical partition size in MB=32
total number of logical partitions configured for this logical volume=1
number of physical mirrors for each logical partition=1
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

```

The preceding program emulates **vmstat** behavior and also shows how **perfstat\_logicalvolume** is used.

## perfstat\_memory\_page Interface

The **perfstat\_memory\_page** interface returns a set of structures of type **perfstat\_memory\_page\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_memory\_page\_t** structure include:

Item	Descriptor
<b>psize</b>	Page size in bytes
<b>real_total</b>	Amount of real memory (in units of psize)
<b>real_freesize</b>	Amount of free real memory (in units of psize)
<b>real_pinned</b>	Amount of pinned memory (in units of psize multiplied by 4)
<b>Pgins</b>	Number of pages paged in

Item	Descriptor
<b>Pgouts</b>	Number of pages paged out

Several other disk-adapter related metrics (such as the number of blocks read from and written to the adapter) are also returned. For a complete list of other disk-adapter-related metrics, see the **perfstat\_memory\_page\_t** section in the [libperfstat.h](#) header file.

The following program shows an example of how the **perfstat\_memory\_page** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main (){
    int total_psize, avail_psize;
    perfstat_memory_page_t *psize_mem_values;
    perfstat_psize_t pagesize;
    int i;
    /*get the total number of page sizez */

    total_psize = perfstat_memory_page(NULL, NULL, sizeof(perfstat_memory_page_t), 0);

    /*check for any error*/
    if(total_psize < 1)
    {
        perror("do_initialization:"
            " Unable to retrieve the number of available pagesizes.");
        exit(-1);
    }

    /* allocate sufficient memory to store the structures */
    psize_mem_values = (perfstat_memory_page_t *)malloc(sizeof(perfstat_memory_page_t) * total_psize);

    /*check for bad malloc */
    if(psize_mem_values == NULL)
    {
        perror("do_initialization: Unable to allocate sufficient"
            " memory for psize_mem_values buffer.");
        exit(-1);
    }

    pagesize.psize = FIRST_PSIZE;
    avail_psize = perfstat_memory_page(&pagesize, psize_mem_values, sizeof(perfstat_memory_page_t),
        total_psize);

    /*check the return value for any error */

    if(avail_psize < 1)
    {
        perror("display_psize_memory_stats: Unable to retrieve memory "
            "statistics for the available page sizes.");
        exit(-1);
    }

    for(i=0;i<avail_psize;i++){
        printf("Page size in bytes=%llu\n",psize_mem_values[i].psize);
        printf("Number of real memory frames of this page size=%lld\n",psize_mem_values[i].real_total);
        printf("Number of pages on free list=%lld\n",psize_mem_values[i].real_free);
        printf("Number of pages pinned=%lld\n",psize_mem_values[i].real_pinned);
        printf("Number of pages in use=%lld\n",psize_mem_values[i].real_inuse);
        printf("Number of page faults =%lld\n",psize_mem_values[i].pgexct);
        printf("Number of pages paged in=%lld\n",psize_mem_values[i].pgins);
        printf("Number of pages paged out=%lld\n",psize_mem_values[i].pgouts);
        printf("\n");
    }
    return 0;
}
```

The program displays an output that is similar to the following example output:

```
Page size in bytes=4096
Number of real memory frames of this page size=572640
Number of pages on free list=364101
Number of pages pinned=171770
Number of pages in use=208539
Number of page faults =1901334
Number of pages paged in=40569
```

```
Number of pages paged out=10381
Page size in bytes=65536
Number of real memory frames of this page size=29746
Number of pages on free list=24741
Number of pages pinned=4333
Number of pages in use=5005
Number of page faults =28495
Number of pages paged in=0
Number of pages paged out=0
```

## perfstat\_netbuffer Interface

The **perfstat\_netbuffer** interface returns a set of structures of type **perfstat\_netbuffer\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_netbuffer\_t** structure include:

Item	Descriptor
<b>size</b>	Size of the allocation (string expressing size in bytes)
<b>inuse</b>	Current allocation of this size
<b>failed</b>	Failed allocation of this size
<b>free</b>	Free list for this size

Several other allocation-related metrics (such as high-water mark and freed) are also returned. For a complete list of other allocation-related metrics, see the **perfstat\_netbuffer\_t** section in the [libperfstat.h](#) header file.

The following code shows an example of how the **perfstat\_netbuffer** interface is used: The preceding program produces the following output:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_netbuffer_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_netbuffer_t structures are available */
    tot = perfstat_netbuffer(NULL, NULL, sizeof(perfstat_netbuffer_t), 0);

    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_netbuffer");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_netbuffer_t));
    if(statp==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* set name to first interface */
    strcpy(first.name, FIRST_NETBUFFER);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_netbuffer(&first, statp,
        sizeof(perfstat_netbuffer_t), tot);

    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_netbuffer");
        exit(-1);
    }

    /* print info in netstat -m format */
```

```

printf("%-12s %10s %9s %6s %9s %7s %7s %7s\n",
      "By size", "inuse", "calls", "failed",
      "delayed", "free", "hiwat", "freed");
for (i = 0; i < ret; i++) {
    printf("%-12s %10llu %9llu %6llu %9llu %7llu %7llu %7llu\n",
          statp[i].name,
          statp[i].inuse,
          statp[i].calls,
          statp[i].delayed,
          statp[i].free,
          statp[i].failed,
          statp[i].highwatermark,
          statp[i].freed);
}
}

```

The program displays an output that is similar to the following example output:

```

By size          inuse      calls  failed   delayed    free   hiwat   freed
64                598      12310   14      682        0   10480    0
128               577       8457   16      287        0    7860    0
256              1476     287157  88     716        0   15720    0
512              2016     1993915 242    808        0   32750    0
1024              218       8417   81     158        0    7860    0
2048              563       2077   277    307        0   19650    0
4096               39        127   15     143        0    1310    0
8192                4         16    4         0        0     327     0
16384              128        257   19         4        0     163     0
32768               25         55    9         4        0      81     0
65536               59         121   35         5        0      81     0
131072              3          7    0        217       0     204     0

```

## perfstat\_netinterface Interface

The `perfstat_netinterface` interface returns a set of structures of type `perfstat_netinterface_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_netinterface_t` structure include:

Table 6. Fields from the `perfstat_netinterface_t` structure

Item	Description
<code>name</code>	Interface name (from ODM)
<code>description</code>	Interface description (from ODM)
<code>ipackets</code>	Total number of input packets received on this network interface
<code>opackets</code>	Total number of output packets sent on this network interface
<code>ierror</code>	Total number of input errors on this network interface
<code>oerror</code>	Total number of output errors on this network interface

Several other network-interface related metrics (such as number of bytes sent and received, type, and bitrate) are also returned. For a complete list of other network-interfaced related metrics, see the `perfstat_netinterface_t` section in the `libperfstat.h` header file in *Files Reference*.

The following code shows an example of how `perfstat_netinterface` is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
#include <net/if_types.h>

char *
decode(uchar type) {
    switch(type) {
        case IFT_LOOP:
            return("loopback");
    }
}

```

```

    case IFT_IS088025:
        return("token-ring");

    case IFT_ETHER:
        return("ethernet");
    }

    return("other");
}

int main(int argc, char* argv[]) {
    int i, ret, tot;
    perfstat_netinterface_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_netinterface_t structures are available */
    tot = perfstat_netinterface(NULL, NULL, sizeof(perfstat_netinterface_t), 0);

    /* check for error */
    if (tot < 0)
    {

    /* check for error */
    if (tot == 0)
    {
        printf("No network interfaces found\n");
        exit(-1);
    }

    perror("perfstat_netinterface");
    exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_netinterface_t));

    /* set name to first interface */
    strcpy(first.name, FIRST_NETINTERFACE);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_netinterface(&first, statp, sizeof(perfstat_netinterface_t), tot);

    /* check for error */
    if (ret <= 0)
    {

    perror("perfstat_netinterface");
    exit(-1);
    }

    /* print statistics for each of the interfaces */
    for (i = 0; i < ret; i++) {
        printf("\nStatistics for interface : %s\n", statp[i].name);
        printf("-----\n");
        printf("type : %s\n", decode(statp[i].type));
        printf("\ninput statistics:\n");
        printf("number of packets : %llu\n", statp[i].ipackets);
        printf("number of errors : %llu\n", statp[i].ierrors);
        printf("number of bytes : %llu\n", statp[i].ibytes);
        printf("\noutput statistics:\n");
        printf("number of packets : %llu\n", statp[i].opackets);
        printf("number of bytes : %llu\n", statp[i].obytes);
        printf("number of errors : %llu\n", statp[i].oerrors);
    }
}

```

The preceding program produces the following output:

```

Statistics for interface : tr0
-----
type : token-ring

input statistics:
number of packets : 306352
number of errors : 0
number of bytes : 24831776

output statistics:
number of packets : 62669

```

```

number of bytes   : 11497679
number of errors  : 0

Statistics for interface : lo0
-----
type : loopback

input statistics:
number of packets : 336
number of errors  : 0
number of bytes   : 20912

output statistics:
number of packets : 336
number of bytes   : 20912
number of errors  : 0

```

The preceding program emulates diskadapterstat behavior and also shows how perfstat\_netinterface is used.

## perfstat\_netadapter Interface

The **perfstat\_netadapter** interface returns a set of structures of type **perfstat\_netadapter\_t**, which is defined in the **libperfstat.h** file.

**Note:** The **perfstat\_netadapter** interface returns only the network Ethernet adapter statistics similar to the **entstat** command.

The following program shows an example of how the **perfstat\_netadapter** interface is used:

```

/* The sample program displays the metrics *
 * related to every Individual *
 * network adapter in the LPAR*/
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
#include <net/if_types.h>
/* define default interval and count values */
#define INTERVAL_DEFAULT 1
#define COUNT_DEFAULT 1

/* Check value returned by malloc for NULL */
#define CHECK_FOR_MALLOC_NULL(X) { if ((X) == NULL) {\
                                perror ("malloc");\
                                exit(2);\
                                }\
                                }

int count = COUNT_DEFAULT, interval = INTERVAL_DEFAULT, tot;
int returncode;

/* store the data structures */

static perfstat_netadapter_t *statp ,*statq;
/* support for remote node statistics collection in a cluster environment */
perfstat_id_node_t nodeid;
static char nodename[MAXHOSTNAMELEN] = "";
static int collect_remote_node_stats = 0;

/*
 * NAME: showusage
 *       to display the usage
 */

void showusage(char *cmd)
{
    fprintf (stderr, "usage: %s [-i <interval in seconds> ] [-c <number of iterations> ] [-n <node name in the
cluster> ]\n", cmd);
    exit(1);
};

/*
 * NAME: do_initialization
 *       This function initializes the data structures.
 *       It also collects the initial set of values.
 *
 * RETURNS:
 * 0n successful completion:
 * - returns 0.
 * In case of error
 * - exits with code 1.
 */

```

```

int do_initialization(void)
{
    /* check how many perfstat_netadapter_t structures are available */
    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        tot = perfstat_netadapter_node(&nodeid, NULL, sizeof(perfstat_netadapter_t), 0);
    }
    else
    {
        tot = perfstat_netadapter(NULL, NULL, sizeof(perfstat_netadapter_t), 0);
    }
    if (tot == 0)
    {
        printf("There is no net adapter\n");
        exit(0);
    }
    if (tot < 0)
    {
        perror("perfstat_netadapter: ");
        exit(1);
    }
    /* allocate enough memory for all the structures */

    statp = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
    CHECK_FOR_MALLOC_NULL(statp);

    statq = (perfstat_netadapter_t *)malloc(tot * sizeof(perfstat_netadapter_t));
    CHECK_FOR_MALLOC_NULL(statq);

    return(0);
}

/*
 *Name: display_metrics
 *      collect the metrics and display them
 */
void display_metrics()
{
    perfstat_id_t first;
    int ret, i;

    if(collect_remote_node_stats) {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;

        strncpy(nodeid.name, FIRST_NETINTERFACE);
        ret = perfstat_netadapter_node(&nodeid, statq, sizeof(perfstat_netadapter_t), tot);
    }
    else {
        strncpy(first.name, FIRST_NETINTERFACE);
        ret = perfstat_netadapter(&first, statq, sizeof(perfstat_netadapter_t), tot);
    }
    if (ret < 0) {
        free(statp);
        free(statq);
        perror("perfstat_netadapter: ");
        exit(1);
    }
    while (count)
    {
        sleep (interval);
        if(collect_remote_node_stats)
        {
            ret = perfstat_netadapter_node(&nodeid, statp, sizeof(perfstat_netadapter_t), tot);
        }
        else {
            ret = perfstat_netadapter(&first, statp, sizeof(perfstat_netadapter_t), tot);
        }
        /* print statistics for each of the interfaces */
        for (i = 0; i < ret; i++)
        {
            printf(" Adapter name: %s \n", statp[i].name);
            printf(" ===== Transmit Statistics===== \n");
            printf(" Transmit Packets: %lld \n",
statp[i].tx_packets - statq[i].tx_packets);
            printf(" Transmit Bytes: %lld \n",
statp[i].tx_bytes - statq[i].tx_bytes);
            printf(" Transfer Interrupts : %lld \n",
statp[i].tx_interrupts - statq[i].tx_interrupts);
            printf(" Transmit Errors : %lld \n",
statp[i].tx_errors - statq[i].tx_errors);
            printf(" Packets Dropped at the time of Data Transmission : %lld \n",
statp[i].tx_packets_dropped - statq[i].tx_packets_dropped);
            printf(" Transmit Queue Size: %lld \n",
statp[i].tx_queue_size - statq[i].tx_queue_size);
            printf(" Transmit Queue Length : %lld \n",
statp[i].tx_queue_len - statq[i].tx_queue_len);
            printf(" Transmit Queue Overflow : %lld \n",
statp[i].tx_queue_overflow - statq[i].tx_queue_overflow);
            printf(" Broadcast Packets Transmitted: %lld \n",

```

```

    statp[i].tx_broadcast_packets - statq[i].tx_broadcast_packets);
    printf(" Multicast packets Transmitted: %lld \n",
    statp[i].tx_multicast_packets - statq[i].tx_multicast_packets);
    printf(" Lost Carrier Sense signal count : %lld \n",
statp[i].tx_carrier_sense - statq[i].tx_carrier_sense);
    printf(" Count of DMA Under-runs for Transmission: %lld \n",
statp[i].tx_DMA_underrun - statq[i].tx_DMA_underrun);
    printf(" Number of unsuccessful transmissions : %lld \n",
statp[i].tx_lost_CTS_errors - statq[i].tx_lost_CTS_errors);
    printf(" Maximum Collision Errors at Transmission: %lld \n",
statp[i].tx_max_collision_errors - statq[i].tx_max_collision_errors);
    printf(" Late Collision Errors at Transmission : %lld \n",
statp[i].tx_late_collision_errors - statq[i].tx_late_collision_errors);
    printf(" Number of packets deferred for Transmission : %lld \n",
statp[i].tx_deferred - statq[i].tx_deferred);
    printf(" Time Out Errors for Transmission : %lld \n",
statp[i].tx_timeout_errors - statq[i].tx_timeout_errors);
    printf(" Count of Single Collision error at Transmission: %lld \n",
statp[i].tx_single_collision_count - statq[i].tx_single_collision_count);
    printf(" Count of Multiple Collision error at Transmission : %lld \n",
statp[i].tx_multiple_collision_count - statq[i].tx_multiple_collision_count);
    printf(" ===== Receive Statistics =====\n");
    printf(" Receive Packets :%lld \n",
statp[i].rx_packets - statq[i].rx_packets);
    printf(" Receive Bytes :%lld \n",
statp[i].rx_bytes - statq[i].rx_bytes);
    printf(" Receive Interrupts : %lld \n",
statp[i].rx_interrupts - statq[i].rx_interrupts);
    printf(" Input errors on interface :%lld \n",
statp[i].rx_errors - statq[i].rx_errors);
    printf(" Number of Packets Dropped : %lld \n",
statp[i].rx_packets_dropped - statq[i].rx_packets_dropped);
    printf(" Count of Bad Packets Received : %lld \n",
statp[i].rx_bad_packets - statq[i].rx_bad_packets);
    printf(" Number of MultiCast Packets Received : %lld \n",
statp[i].rx_multicast_packets - statq[i].rx_multicast_packets);
    printf(" Number of Broadcast Packets Received : %lld \n",
statp[i].rx_broadcast_packets - statq[i].rx_broadcast_packets);
    printf(" Count of Packets Received with CRC errors: %lld \n",
statp[i].rx_CRC_errors - statq[i].rx_CRC_errors);
    printf(" DMA over-runs : %lld \n",
statp[i].rx_DMA_underrun - statq[i].rx_DMA_underrun);
    printf(" Alignment Errors : %lld \n",
statp[i].rx_alignment_errors - statq[i].rx_alignment_errors);
    printf(" No Resource Errors : %lld \n",
statp[i].rx_noresource_errors - statq[i].rx_noresource_errors);
    printf(" Collision Errors: %lld \n",
statp[i].rx_collision_errors - statq[i].rx_collision_errors);
    printf(" Number of Short Packets Received: %lld \n",
statp[i].rx_packet_tooshort_errors - statq[i].rx_packet_tooshort_errors);
    printf(" Number of Too Long Packets Received : %lld \n",
statp[i].rx_packet_toolong_errors - statq[i].rx_packet_toolong_errors);
    printf(" Number of Received Packets discarded by Adapter: %lld \n",
statp[i].rx_packets_discardedbyadapter - statq[i].rx_packets_discardedbyadapter);
    printf(" =====\n");
}
memcpy(statq, statp, (tot * sizeof(perfstat_netadapter_t)));
count--;
}
}

/*
 *Name: main
 *
 */

int main(int argc, char *argv[])
{
    int i, rc;
    /* get the interval and count values */

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if (interval <= 0)
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if (count <= 0)
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:

```

```

        /* Invalid arguments. Print the usage and terminate */
        showusage(argv[0]);
    }
}

if(collect_remote_node_stats)
{
    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }
}

do_initialization();
display_metrics();

if(collect_remote_node_stats)
{
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
free(statp);
free(statq);
return 0;
}

```

The program produces the output similar to the following:

```

Adapter name: ent0
===== Transmit Statistics=====
Transmit Packets: 0
Transmit Bytes: 0
Transfer Interrupts : 0
Transmit Errors : 0
Packets Dropped at the time of Data Transmission : 0
Transmit Queue Size: 0
Transmit Queue Length :0
Transmit Queue Overflow : 0
Broadcast Packets Transmitted: 0
Multicast packets Transmitted: 0
Lost Carrier Sense signal count : 0
Count of DMA Under-runs for Transmission: 0
Number of unsuccessful transmissions : 0
Maximum Collision Errors at Transmission: 0
Late Collision Errors at Transmission : 0
Number of packets deferred for Transmission : 0
Time Out Errors for Transmission : 0
Count of Single Collision error at Transmission: 0
Count of Multiple Collision error at Transmission : 0
===== Receive Statistics =====
Receive Packets :48
Receive Bytes :2962
Receive Interrupts : 44
Input errors on interface :0
Number of Packets Dropped : 0
Count of Bad Packets Received : 0
Number of MultiCast Packets Received : 0
Number of Broadcast Packets Received : 47
Count of Packets Received with CRC errors: 0
DMA over-runs : 0
Alignment Errors : 0
No Resource Errors : 0
Collision Errors: 0
Number of Short Packets Received: 0
Number of Too Long Packets Received : 0
Number of Received Packets discarded by Adapter: 0

```

## perfstat\_protocol Interface

The **perfstat\_protocol** interface returns a set of structures of type **perfstat\_protocol\_t**, which consists of a set of unions to accommodate the different sets of fields needed for each protocol, as defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_protocol\_t** structure include:

Item	Descriptor
<b>name</b>	Protocol name, which can be any of the following values: <b>ip</b> , <b>ip6</b> , <b>icmp</b> , <b>icmp6</b> , <b>udp</b> , <b>tcp</b> , <b>rpc</b> , <b>nfs</b> , <b>nfsv2</b> , or <b>nfsv3</b> .
<b>ipackets</b>	Number of input packets received using this protocol. This field exists only for protocols <b>ip</b> , <b>ipv6</b> , <b>udp</b> , and <b>tcp</b> .

Item	Descriptor
<b>opackets</b>	Number of output packets sent using this protocol. This field exists only for protocols <b>ip</b> , <b>ipv6</b> , <b>udp</b> , and <b>tcp</b> .
<b>received</b>	Number of packets received using this protocol. This field exists only for protocols <b>icmp</b> and <b>icmpv6</b> .
<b>calls</b>	Number of calls made to this protocol. This field exists only for protocols <b>rpc</b> , <b>nfs</b> , <b>nfsv2</b> , and <b>nfsv3</b> .

Many other network-protocol related metrics are also returned. For a complete list of network-protocol related metrics, see the **perfstat\_protocol\_t** section in the [libperfstat.h](#) header file.

The following code shows an example of how the **perfstat\_protocol** interface is used:

```
#include <stdio.h>
#include <string.h>
#include <libperfstat.h>

int main(int argc, char* argv[]) {
    int ret, tot, retrieved = 0;
    perfstat_protocol_t pinfo;
    perfstat_id_t protid;

    /* check how many perfstat_protocol_t structures are available */
    tot = perfstat_protocol(NULL, NULL, sizeof(perfstat_protocol_t), 0);

    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_protocol");
        exit(-1);
    }

    printf("number of protocol usage structures available : %d\n", tot);

    /* set name to first protocol */
    strcpy(protid.name, FIRST_PROTOCOL);

    /* retrieve first protocol usage information */
    ret = perfstat_protocol(&protid, &pinfo, sizeof(perfstat_protocol_t), 1);

    if (ret < 0)
    {
        perror("perfstat_protocol");
        exit(-1);
    }
    retrieved += ret;
    do {
        printf("\nStatistics for protocol : %s\n", pinfo.name);
        printf("-----\n");

        if (!strcmp(pinfo.name, "ip")) {
            printf("number of input packets : %llu\n", pinfo.u.ip.ipackets);
            printf("number of input errors : %llu\n", pinfo.u.ip.ierrors);
            printf("number of output packets : %llu\n", pinfo.u.ip.opackets);
            printf("number of output errors : %llu\n", pinfo.u.ip.oerrors);
        } else if (!strcmp(pinfo.name, "ipv6")) {
            printf("number of input packets : %llu\n", pinfo.u.ipv6.ipackets);
            printf("number of input errors : %llu\n", pinfo.u.ipv6.ierrors);
            printf("number of output packets : %llu\n", pinfo.u.ipv6.opackets);
            printf("number of output errors : %llu\n", pinfo.u.ipv6.oerrors);
        } else if (!strcmp(pinfo.name, "icmp")) {
            printf("number of packets received : %llu\n", pinfo.u.icmp.received);
            printf("number of packets sent : %llu\n", pinfo.u.icmp.sent);
            printf("number of errors : %llu\n", pinfo.u.icmp.errors);
        } else if (!strcmp(pinfo.name, "icmpv6")) {
            printf("number of packets received : %llu\n", pinfo.u.icmpv6.received);
            printf("number of packets sent : %llu\n", pinfo.u.icmpv6.sent);
            printf("number of errors : %llu\n", pinfo.u.icmpv6.errors);
        } else if (!strcmp(pinfo.name, "udp")) {
            printf("number of input packets : %llu\n", pinfo.u.udp.ipackets);
            printf("number of input errors : %llu\n", pinfo.u.udp.ierrors);
            printf("number of output packets : %llu\n", pinfo.u.udp.opackets);
        } else if (!strcmp(pinfo.name, "tcp")) {
            printf("number of input packets : %llu\n", pinfo.u.tcp.ipackets);
        }
    } while (ret > 0);
}
```

```

        printf("number of input errors   : %llu\n", pinfo.u.tcp.ierrors);
        printf("number of output packets : %llu\n", pinfo.u.tcp.opackets);
    } else if (!strcmp(pinfo.name, "rpc")) {
        printf("client statistics:\n");
        printf("number of connection-oriented RPC requests : %llu\n",
            pinfo.u.rpc.client.stream.calls);
        printf("number of rejected connection-oriented RPCs : %llu\n",
            pinfo.u.rpc.client.stream.badcalls);
        printf("number of connectionless RPC requests   : %llu\n",
            pinfo.u.rpc.client.dgram.calls);
        printf("number of rejected connectionless RPCs   : %llu\n",
            pinfo.u.rpc.client.dgram.badcalls);
        printf("\nserver statistics:\n");
        printf("number of connection-oriented RPC requests : %llu\n",
            pinfo.u.rpc.server.stream.calls);
        printf("number of rejected connection-oriented RPCs : %llu\n",
            pinfo.u.rpc.server.stream.badcalls);
        printf("number of connectionless RPC requests   : %llu\n",
            pinfo.u.rpc.server.dgram.calls);
        printf("number of rejected connectionless RPCs   : %llu\n",
            pinfo.u.rpc.server.dgram.badcalls);
    } else if (!strcmp(pinfo.name, "nfs")) {
        printf("total number of NFS client requests      : %llu\n",
            pinfo.u.nfs.client.calls);
        printf("total number of NFS client failed calls   : %llu\n",
            pinfo.u.nfs.client.badcalls);
        printf("total number of NFS server requests      : %llu\n",
            pinfo.u.nfs.server.calls);
        printf("total number of NFS server failed calls   : %llu\n",
            pinfo.u.nfs.server.badcalls);
        printf("total number of NFS version 2 server calls : %llu\n",
            pinfo.u.nfs.server.public_v2);
        printf("total number of NFS version 3 server calls : %llu\n",
            pinfo.u.nfs.server.public_v3);
    } else if (!strcmp(pinfo.name, "nfsv2")) {
        printf("number of NFS V2 client requests : %llu\n",
            pinfo.u.nfsv2.client.calls);
        printf("number of NFS V2 server requests : %llu\n",
            pinfo.u.nfsv2.server.calls);
    } else if (!strcmp(pinfo.name, "nfsv3")) {
        printf("number of NFS V3 client requests : %llu\n",
            pinfo.u.nfsv3.client.calls);
        printf("number of NFS V3 server requests : %llu\n",
            pinfo.u.nfsv3.server.calls);
    }

    /* make sure we stop after the last protocol */
    if (ret = strcmp(protid.name, "")) {
        printf("\nnext protocol name : %s\n", protid.name);

        /* retrieve information for next protocol */
        ret = perfstat_protocol(&protid, &pinfo, sizeof(perfstat_protocol_t), 1);
        if (ret < 0)
        {
            perror("perfstat_protocol");
            exit(-1);
        }
        retrieved += ret;
    }
} while (ret == 1);

printf("\nnumber of protocol usage structures retrieved : %d\n", retrieved);
}

```

The program displays an output that is similar to the following example output:

```

number of protocol usage structures available : 11

Statistics for protocol : ip
-----
number of input packets   : 155855
number of input errors    : 32911
number of output packets  : 25635
number of output errors   : 32909

next protocol name : ipv6

Statistics for protocol : ipv6
-----
number of input packets   : 0
number of input errors    : 0

```

```

number of output packets : 0
number of output errors  : 0

next protocol name : icmp

Statistics for protocol : icmp
-----
number of packets received : 2
number of packets sent    : 1
number of errors          : 1

next protocol name : icmpv6

Statistics for protocol : icmpv6
-----
number of packets received : 0
number of packets sent    : 0
number of errors          : 0

next protocol name : udp

Statistics for protocol : udp
-----
number of input packets  : 106630
number of input errors   : 91625
number of output packets : 14435

next protocol name : tcp

Statistics for protocol : tcp
-----
number of input packets  : 16313
number of input errors   : 0
number of output packets : 11196

next protocol name : rpc

Statistics for protocol : rpc
-----
client statistics:
number of connection-oriented RPC requests : 41
number of rejected connection-oriented RPCs : 0
number of connectionless RPC requests      : 24
number of rejected connectionless RPCs     : 0

server statistics:
number of connection-oriented RPC requests : 0
number of rejected connection-oriented RPCs : 0
number of connectionless RPC requests      : 0
number of rejected connectionless RPCs     : 0

next protocol name : nfs

Statistics for protocol : nfs
-----
total number of NFS client requests      : 41
total number of NFS client failed calls  : 0
total number of NFS server requests      : 0
total number of NFS server failed calls  : 0
total number of NFS version 2 server calls : 0
total number of NFS version 3 server calls : 0

next protocol name : nfsv2

Statistics for protocol : nfsv2
-----
number of NFS V2 client requests : 0
number of NFS V2 server requests : 0

next protocol name : nfsv3

Statistics for protocol : nfsv3
-----
number of NFS V3 client requests : 41
number of NFS V3 server requests : 0

next protocol name : nfsv4

Statistics for protocol : nfsv4
-----

```

```
number of protocol usage structures retrieved : 11
```

The preceding program emulates **protocolstat** behavior and also shows how **perfstat\_protocol** is used.

## perfstat\_pagingspace Interface

The **perfstat\_pagingspace** interface returns a set of structures of type **perfstat\_pagingspace\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_pagingspace\_t** structure include:

Item	Descriptor
<b>mb_size</b>	Size of the paging space in MB
<b>lp_size</b>	Size of the paging space in logical partitions
<b>mb_used</b>	Portion of the paging space used in MB

Several other paging-space-related metrics (such as name, type, and active) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_pagingspace\_t** section in the [libperfstat.h](#) header file in *Files Reference*.

The following code shows an example of how **perfstat\_pagingspace** is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char agrv[]) {
    int i, ret, tot;
    perfstat_id_t first;
    perfstat_pagingspace_t *pinfo;

    tot = perfstat_pagingspace(NULL, NULL, sizeof(perfstat_pagingspace_t), 0);
    /* check for error */
    if (tot <= 0)
    {
        perror("perfstat_pagingspace");
        exit(-1);
    }

    pinfo = calloc(tot, sizeof(perfstat_pagingspace_t));

    strcpy(first.name, FIRST_PAGINGSPACE);

    ret = perfstat_pagingspace(&first, pinfo, sizeof(perfstat_pagingspace_t), tot);
    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_pagingspace");
        exit(-1);
    }
    for (i = 0; i < ret; i++) {
        printf("\nStatistics for paging space : %s\n", pinfo[i].name);
        printf("-----\n");
        printf("type          : %s\n",
            pinfo[i].type == LV_PAGING ? "logical volume" : "NFS file");
        if (pinfo[i].type == LV_PAGING) {
            printf("volume group : %s\n", pinfo[i].u.lv_paging.vgname);
        }
        else {
            printf("hostname : %s\n", pinfo[i].u.nfs_paging.hostname);
            printf("filename : %s\n", pinfo[i].u.nfs_paging.filename);
        }
        printf("size (in LP) : %llu\n", pinfo[i].lp_size);
        printf("size (in MB) : %llu\n", pinfo[i].mb_size);
        printf("used (in MB) : %llu\n", pinfo[i].mb_used);
    }
}
```

The preceding program produces the following output:

```

Statistics for paging space : hd6
-----
type       : logical volume
volume_group : rootvg
size (in LP) : 64
size (in MB) : 512
used (in MB) : 4

```

## perfstat\_process interfaces

The `perfstat_process` interface returns a set of structures of type `perfstat_process_t`, which is defined in the `libperfstat.h` file.

The field of the `perfstat_process_t` structure includes:

Item	Descriptor
<b>pid</b>	Process ID
<b>proc_name</b>	Name of the process
<b>proc_priority</b>	Priority of the process
<b>num_threads</b>	Thread count
<b>proc_uid</b>	Information of the owner
<b>proc_classid</b>	WLM class name
<b>proc_size</b>	Virtual size of the process
<b>proc_real_mem_data</b>	Real memory used for the data in kilobytes
<b>proc_real_mem_text</b>	Real memory used for text in kilobytes
<b>proc_virt_mem_data</b>	Virtual memory used for data in kilobytes
<b>proc_virt_mem_text</b>	Virtual memory used for text in kilobytes
<b>shared_lib_data_size</b>	Data size from shared library in kilobytes
<b>heap_size</b>	Heap size in kilobytes
<b>real_inuse</b>	The real memory in kilobytes used by the process including the segments
<b>virt_inuse</b>	The virtual memory in kilobytes used by the process including the segments
<b>pinned</b>	Pinned memory in kilobytes used for the process that is inclusive of all segments
<b>pgsp_inuse</b>	Paging space in kilobytes uses inclusive of all segments
<b>filepages</b>	File pages in kilobytes used including shared pages
<b>real_inuse_map</b>	Real memory in kilobytes used for shared memory and memory mapped regions
<b>virt_inuse_map</b>	Virtual memory in kilobytes used for shared memory and memory mapped regions
<b>pinned_inuse_map</b>	Pinned memory in kilobytes for shared memory and memory mapped regions
<b>ucpu_time</b>	User mode CPU time in milliseconds
<b>scpu_time</b>	System mode CPU time in milliseconds
<b>last_timebase</b>	Timebase counter
<b>inBytes</b>	Bytes read from the disk

Item	Descriptor
<b>outBytes</b>	Bytes written to the disk
<b>inOps</b>	In operations from disk
<b>outOps</b>	Out operations from disk

The following is an example of code for the perfstat\_process API:

```
#include <libperfstat.h>

void main()
{
    perfstat_process_t *proct;
    perfstat_id_t id;
    int i,rc,proc_count;

    /* Get the count of processes */
    proc_count = perfstat_process(NULL, NULL,sizeof(perfstat_process_t),0);

    /* check for error */
    if(proc_count <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1) ;
    }
    printf("Number of Processes = %d\n",proc_count);

    /* Allocate enough memory */
    proct = (perfstat_process_t *)calloc(proc_count,sizeof(perfstat_process_t));
    if(proct == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1) ;
    }

    strcpy(id.name,"");
    rc = perfstat_process(&id,proct,sizeof(perfstat_process_t),proc_count);
    if(rc <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1) ;
    }

    printf("\n =====Process Related metrics =====\n");
    for(i=0 ; i<proc_count ;i++)
    {
        printf("Process Name = %s\n",proct[i].proc_name);
        printf("Process ID = %lld\n",proct[i].pid);
        printf("Process priority = %d\n",proct[i].proc_priority);
        printf("Thread Count = %lld\n",proct[i].num_threads);
        printf("\nCredential Information\n");
        printf("Owner Info = %lld\n",proct[i].proc_uid);
        printf("WLM Class Name = %lld\n",proct[i].proc_classid);
        printf("\nMemory Related Statistics \n");
        printf("Process Virtual Size = %lld KB \n",proct[i].proc_size);
        printf("Real Memory used for Data = %lld KB \n",proct[i].proc_real_mem_data);
        printf("Real Memory used for Text = %lld KB \n",proct[i].proc_real_mem_text);
        printf("Virtual Memory used for Data = %lld KB \n",proct[i].proc_virt_mem_data);
        printf("Virtual Memory used for Text = %lld KB \n",proct[i].proc_virt_mem_text);
        printf("Data Size from Shared Library = %lld KB \n",proct[i].shared_lib_data_size);
        printf("Heap Size = %lld KB \n",proct[i].heap_size);
        printf("Real memory in use by process = %lld KB \n",proct[i].real_inuse);
        printf("Virtual memory in use by process= %lld KB \n",proct[i].virt_inuse);
        printf("Pinned Memory for this process = %lld KB \n",proct[i].pinned);
        printf("Paging Space in use = %lld KB \n",proct[i].pgsp_inuse);
        printf("File Pages used = %lld KB \n",proct[i].filepages);
        printf("Real memory used for Shared Memory and Memory Mapped regions =%lld KB \n",
        proct[i].real_inuse_map);
        printf("Virtual Memory used for Shared Memory and Memory Mapped regions =%lld KB \n",
        proct[i].virt_inuse_map);
        printf("Pinned memory for Shared Memory and Memory Mapped regions =%lld KB \n",
        proct[i].pinned_inuse_map);
        printf("\nCPU Related Statistics \n");
        printf("User Mode CPU time = %lf ms\n",proct[i].ucpu_time);
        printf("System Mode CPU time = %lf ms\n",proct[i].scpu_time);
        printf("Timebase Counter = %lld\n", proct[i].last_timebase);
        printf("\nDisk Related Statistics \n");
    }
}
```

```

printf("Bytes Written to Disk =          %lld\n",proct[i].inBytes);
printf("Bytes Read from Disk =          %lld\n",proct[i].outBytes);
printf("In Operations from Disk =       %lld\n",proct[i].inOps);
printf("Out Operations from Disk =       %lld\n",proct[i].outOps);
printf("=====\n");
printf("\n\n");
}
}

```

The program produces the output similar to the following:

Number of Processes = 77

```

=====Process Related metrics =====
Process Name =                swapper
Process ID =                   0
Process priority =             16
Thread Count =                 0

Credential Information
Owner Info =                   0
WLM Class Name =               257

Memory Related Statistics
Process Virtual Size =         384 KB
Real Memory used for Data =    384 KB
Real Memory used for Text =    0 KB
Virtual Memory used for Data = 384 KB
Virtual Memory used for Text = 0 KB
Data Size from Shared Library = 0 KB
Heap Size =                    0 KB
Real memory in use by process = 384 KB
Virtual memory in use by process= 384 KB
Pinned Memory for this process = 320 KB
Paging Space in use =         0 KB
File Pages used =              0 KB
Real memory used for Shared Memory and Memory Mapped regions =0 KB
Virtual Memory used for Shared Memory and Memory Mapped regions =0 KB
Pinned memory for Shared Memory and Memory Mapped regions =0 KB

CPU Related Statistics
User Mode CPU time =           0.000000 ms
System Mode CPU time =         9262.345828 ms
Timebase Counter =             7290723200327369

Disk Related Statistics
Bytes Written to Disk =        0
Bytes Read from Disk =         32768
In Operations from Disk =      0
Out Operations from Disk =     8
=====

```

The program displays an output that is similar to the following example output:

Number of Processes = 77

```

=====Process Related metrics =====
Process Name =                swapper
Process ID =                   0
Process priority =             16
Thread Count =                 0

Credential Information
Owner Info =                   0
WLM Class Name =               257

Memory Related Statistics
Process Virtual Size =         384 KB
Real Memory used for Data =    384 KB
Real Memory used for Text =    0 KB
Virtual Memory used for Data = 384 KB
Virtual Memory used for Text = 0 KB
Data Size from Shared Library = 0 KB
Heap Size =                    0 KB
Real memory in use by process = 384 KB
Virtual memory in use by process= 384 KB
Pinned Memory for this process = 320 KB
Paging Space in use =         0 KB
File Pages used =              0 KB
Real memory used for Shared Memory and Memory Mapped regions =0 KB
Virtual Memory used for Shared Memory and Memory Mapped regions =0 KB

```

Pinned memory for Shared Memory and Memory Mapped regions =0 KB

```
CPU Related Statistics
User Mode CPU time =          0.000000 ms
System Mode CPU time =       9262.345828 ms
Timebase Counter =          7290723200327369
```

```
Disk Related Statistics
Bytes Written to Disk =      0
Bytes Read from Disk =     32768
In Operations from Disk =   0
Out Operations from Disk =   8
=====
```

## perfstat\_process\_util interface

The `perfstat_process_util` interface returns a set of structures of type `perfstat_process_t`, which is defined in the `libperfstat.h` file.

The following is an example of code that uses the `perfstat_process_util` API:

```
#include <libperfstat.h>
#include <stdio.h>
#include <stdlib.h>
#define PERIOD 5

void main()
{
    perfstat_process_t *cur, *prev;
    perfstat_rawdata_t buf;
    perfstat_process_t *proc_util;
    perfstat_id_t id;
    int cur_proc_count, prev_proc_count;
    int i, rc;
    prev_proc_count = perfstat_process(NULL, NULL, sizeof(perfstat_process_t), 0);
    if (prev_proc_count <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1);
    }
    prev = (perfstat_process_t *)calloc(prev_proc_count, sizeof(perfstat_process_t));
    if (prev == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1);
    }
    strcpy(id.name, "");
    rc = perfstat_process(&id, prev, sizeof(perfstat_process_t), prev_proc_count);
    if (rc <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1);
    }
    sleep(PERIOD);

    cur_proc_count = perfstat_process(NULL, NULL, sizeof(perfstat_process_t), 0);
    if (cur_proc_count <= 0)
    {
        perror("Error in perfstat_process");
        exit(-1);
    }
    cur = (perfstat_process_t *)calloc(cur_proc_count, sizeof(perfstat_process_t));
    proc_util = (perfstat_process_t *)calloc(cur_proc_count, sizeof(perfstat_process_t));
    if (cur == NULL || proc_util == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1);
    }
    rc = perfstat_process(&id, cur, sizeof(perfstat_process_t), cur_proc_count);
    if (rc < 0)
    {
        perror("Error in perfstat_process");
        exit(-1);
    }

    bzero(&buf, sizeof(perfstat_rawdata_t));
    buf.type = UTIL_PROCESS;
    buf.curstat = cur;
    buf.prevstat = prev;
}
```

```

buf.sizeof_data = sizeof(perfstat_process_t);
buf.cur_elems = cur_proc_count;
buf.prev_elems = prev_proc_count;

/* Calculate Process Utilization */
rc = perfstat_process_util(&buf,proc_util,sizeof(perfstat_process_t),cur_proc_count);
if(rc <= 0)
{
    perror("Error in perfstat_process_util");
    exit(-1);
}

printf("\n =====Process Related Utilization Metrics =====\n");
for(i=0 ; i<cur_proc_count ; i++)
{
    printf("Process ID =                %lld\n",proc_util[i].pid);
    printf("User Mode CPU time =          %lf \n",proc_util[i].ucpu_time);
    printf("System Mode CPU time =          %lf \n",proc_util[i].scpu_time);
    printf("Bytes Written to Disk =         %lld\n",proc_util[i].inBytes);
    printf("Bytes Read from Disk =         %lld\n",proc_util[i].outBytes);
    printf("In Operations from Disk =      %lld\n",proc_util[i].inOps);
    printf("Out Operations from Disk =     %lld\n",proc_util[i].outOps);
    printf("=====\n");
    printf("\n\n");
}
}

```

The program displays an output that is similar to the following example output:

```

=====Process Related Utilization Metrics =====
Process ID =                0
User Mode CPU time =          0.000000
System Mode CPU time =          0.013752
Bytes Written to Disk =         0
Bytes Read from Disk =         0
In Operations from Disk =      0
Out Operations from Disk =     0
=====

Process ID =                1
User Mode CPU time =          0.000000
System Mode CPU time =          0.000000
Bytes Written to Disk =         0
Bytes Read from Disk =         0
In Operations from Disk =      0
Out Operations from Disk =     0
=====

Process ID =                196614
User Mode CPU time =          0.000000
System Mode CPU time =          0.000000
Bytes Written to Disk =         0
Bytes Read from Disk =         0
In Operations from Disk =      0
Out Operations from Disk =     0
=====

Process ID =                262152
User Mode CPU time =          0.000000
System Mode CPU time =          0.000000
Bytes Written to Disk =         0
Bytes Read from Disk =         0
In Operations from Disk =      0
Out Operations from Disk =     0
=====

```

## perfstat\_processor\_pool\_util interface

The `perfstat_processor_pool_util` interface returns a set of structures of type `perfstat_processor_pool_util_t`, which is defined in the `libperfstat.h` file

Item	Descriptor
<b>max_capacity</b>	Maximum pool processor capacity of the partition.
<b>entitled_capacity</b>	Entitled pool processor capacity of the partition.
<b>phys_cpus_pool</b>	Physical processors that are available in the Shared processor Pool to which the partition is associated.
<b>idle_cores</b>	Physical processors that are available in the Shared processor Pool from the last interval.
<b>max_cores</b>	Maximum cores used by the Shared processor Pool for the last interval, which is associated with the partition.
<b>busy_cores</b>	Maximum busy (non-idle) cores that are accumulated for the last interval across all partitions in the Shared processor Pool, which is associated with the partition.
<b>sbusy_cores</b>	Normalized summation of busy (non-idle) cores that are accumulated across all partitions in the Shared processor Pool, which is associated with the partition. This option applies if the cores run at nominal or rated frequency.
<b>gpool_tot_cores</b>	Total number of cores across all physical processors that are allocated for shared processor use (across all pools).
<b>gpool_busy_cores</b>	Summation of the busy (non-idle) cores that are accumulated across all shared processor partitions (across all pools) for the last interval.
<b>gpool_sbusy_cores</b>	Normalized summation of the busy cores that are accumulated across all shared processor partitions (across all pools) for the last interval. This option applies if the cores run at nominal or rated frequency.
<b>tb_last_delta</b>	Elapsed number of clock ticks.
<b>version</b>	Version number of the data structure.

The use of the `perfstat_processor_pool_util` API for the system-level utilization follows:

```
#include <libperfstat.h>
#include <sys/dr.h>
#include <sys/types.h>
#include <stdio.h>
#include <errno.h>
#include <unistd.h>
#define COUNT 2
#define INTERVAL 2
void main(int argc, char **argv)
{
    perfstat_rawdata_t data;
    perfstat_partition_total_t oldt,newt;
    perfstat_processor_pool_util_t util,*uti;
    static int once=0;
    int rc;
    u_longlong_t x=0;
    int iInter=0,iCount=0;
```



Item	Descriptor
<b>bsize</b>	Tape block size (in bytes)
<b>paths_count</b>	Number of paths to the tape

Several other paging-space-related metrics (such as name, type, and active) are also returned. For a complete list of paging-space-related metrics, see the **perfstat\_pagingspace\_t** section in the [libperfstat.h](#) header file in *Files Reference*.

The following code shows an example of how the **perfstat\_tape** interface is used:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
    int ret, tot, i;
    perfstat_tape_t *statp;
    perfstat_id_t first;

    /* check how many perfstat_tape_t structures are available */
    tot = perfstat_tape(NULL, NULL, sizeof(perfstat_tape_t), 0);

    /* check for error */
    if (tot < 0)
    {
        perror("perfstat_tape");
        exit(-1);
    }
    if (tot == 0)
    {
        printf("No tape found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    statp = calloc(tot, sizeof(perfstat_tape_t));
    if(statp==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* set name to first interface */
    strcpy(first.name, FIRST_TAPE);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_tape(&first, statp,
        sizeof(perfstat_tape_t), tot);

    /* check for error */
    if (ret <= 0)
    {
        perror("perfstat_tape");
        exit(-1);
    }

    for(i=0;i<ret;i++){

        printf("Name of the tape=%s\n",statp[i].name);
        printf("Tape description=%s\n",statp[i].description);
        printf("Size of the tape (in MB)=%lld\n",statp[i].size);
        printf("Free portion of the tape (in MB)=%lld\n",statp[i].free);
        printf("Tape block size (in bytes)=%lld\n",statp[i].bsize);
        printf("Number of transfers to/from tape=%lld\n",statp[i].xfers);
        printf("Number of read transfers to/from tape=%lld\n",statp[i].rxfers);
        printf("Number of blocks written to tape=%lld\n",statp[i].wblks);
        printf("Number of blocks read from tape=%lld\n",statp[i].rblks);
        printf("Amount of time tape is active=%lld\n",statp[i].time);
        printf("Tape adapter name =%s\n",statp[i].adapter);
        printf("Number of paths to this tape=%d\n",statp[i].paths_count);
        printf("\n");
    }
}
```

## perfstat\_thread interfaces

The `perfstat_thread` interface returns a set of structures of type `perfstat_thread_t`, which is defined in the `libperfstat.h` file.

The field of the `perfstat_thread_t` structure includes the following:

Item	Description
Pid	The process ID of the thread.
Tid	The kernel ID of the thread.
Cpuid	The processor on which the thread is bound.
ucpu_time	The user mode CPU time in milliseconds.
scpu_time	The system mode CPU time in milliseconds.

The following is an example of code for the `perfstat_thread_t` API:

```
#include <libperfstat.h>

void main()
{
    perfstat_thread_t *threadt;
    perfstat_id_t id;
    int i,rc,thread_count;

    /* Get the count of threads */
    thread_count = perfstat_thread(NULL, NULL,sizeof(perfstat_thread_t),0);

    /* check for error */
    if(thread_count <= 0)
    {
        perror("Error in perfstat_thread");
        exit(-1) ;
    }
    printf("Number of Threads = %d\n",thread_count);

    /* Allocate enough memory */
    threadt = (perfstat_thread_t *)calloc(thread_count,sizeof(perfstat_thread_t));
    if(threadt == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1) ;
    }

    strcpy(id.name,"");
    rc = perfstat_thread(&id,threadt,sizeof(perfstat_thread_t),thread_count);
    if(rc <= 0)
    {
        free(threadt);
        perror("Error in perfstat_thread");
        exit(-1) ;
    }

    printf("\n =====Thread Related metrics =====\n");
    for(i=0 ; i<thread_count ;i++)
    {
        printf("Process ID =                %u\n",threadt[i].pid);
        printf("Thread ID =                %u\n",threadt[i].tid);
        printf("\nCPU Related Statistics \n");
        printf("User Mode CPU time =                %f ms\n",threadt[i].ucpu_time);
        printf("System Mode CPU time =                %f ms\n",threadt[i].scpu_time);
        printf("Processor to which the thread is bound = %d\n", threadt[i].cpuid);
        printf("===== \n");
        printf("\n\n");
    }
    free(threadt);
}
```

The program displays an output that is similar to the following example output:

```
Process ID = 6553744
Thread ID  = 12345

CPU Related Statistics
User Mode CPU time = 714000.000000 ms
System Mode CPU time = 3000.000000 ms
Processor to which the thread is bound = 1
```

## Related information

[libperfstat.h command](#)

## perfstat\_thread\_util interface

The `perfstat_thread_util` interface returns a set of structures of type `perfstat_thread_t`, which is defined in the `libperfstat.h` file.

The following is an example of code for the `perfstat_thread_util` API:

```
#include <libperfstat.h>
#define PERIOD 5

void main()
{
    perfstat_thread_t *cur, *prev;
    perfstat_rawdata_t buf;
    perfstat_thread_t *thread_util;
    perfstat_id_t id;
    int cur_thread_count, prev_thread_count;
    int i, rc;
    prev_thread_count = perfstat_thread(NULL, NULL, sizeof(perfstat_thread_t), 0);
    if (prev_thread_count <= 0)
    {
        perror("Error in perfstat_thread");
        exit(-1);
    }
    prev = (perfstat_thread_t *)calloc(prev_thread_count, sizeof(perfstat_thread_t));
    if (prev == NULL)
    {
        perror("Memory Allocation Error");
        exit(-1);
    }
    strcpy(id.name, "");
    prev_thread_count = perfstat_thread(&id, prev, sizeof(perfstat_thread_t), prev_thread_count);
    if (prev_thread_count <= 0)
    {
        free(prev);
        perror("Error in perfstat_thread");
        exit(-1);
    }
    sleep(PERIOD);

    cur_thread_count = perfstat_thread(NULL, NULL, sizeof(perfstat_thread_t), 0);
    if (cur_thread_count <= 0)
    {
        free(prev);
        perror("Error in perfstat_thread");
        exit(-1);
    }
    cur = (perfstat_thread_t *)calloc(cur_thread_count, sizeof(perfstat_thread_t));
    thread_util = (perfstat_thread_t *)calloc(cur_thread_count, sizeof(perfstat_thread_t));
    if (cur == NULL || thread_util == NULL)
    {
        free(prev);
        perror("Memory Allocation Error");
        exit(-1);
    }
    cur_thread_count = perfstat_thread(&id, cur, sizeof(perfstat_thread_t), cur_thread_count);
    if (cur_thread_count <= 0)
    {
        free(prev);
        free(cur);
        free(thread_util);
        perror("Error in perfstat_thread");
        exit(-1);
    }

    bzero(&buf, sizeof(perfstat_rawdata_t));
```

```

buf.type = UTIL_PROCESS;
buf.curstat = cur;
buf.prevstat = prev;
buf.sizeof_data = sizeof(perfstat_thread_t);
buf.cur_elems = cur_thread_count;
buf.prev_elems = prev_thread_count;

/* Calculate Thread Utilization. This returns the number of thread_util structures that are
filled */
rc = perfstat_thread_util(&buf,thread_util,sizeof(perfstat_thread_t),cur_thread_count);
if(rc <= 0)
{
    free(prev);
    free(cur);
    free(thread_util);
    perror("Error in perfstat_thread_util");
    exit(-1);
}

printf("\n =====Thread Related Utilization Metrics =====\n");
for(i=0 ; i<rc ;i++)
{
    printf("Process ID =                %u\n",thread_util[i].pid);
    printf("Thread ID =                  %u\n",thread_util[i].tid);
    printf("User Mode CPU time =            %f \n",thread_util[i].ucpu_time);
    printf("System Mode CPU time =          %f \n",thread_util[i].scpu_time);
    printf(" Bound CPU Id                    =    %d\n", thread_util[i].cpuid);
    printf("===== \n");
    printf("\n\n");
}
free(prev);
free(cur);
free(thread_util);
}

```

The program displays an output that is similar to the following example output:

```

Process ID = 6160532
Thread ID = 123456
User Mode CPU time = 21.824531
System Mode CPU time = 0.000000
Bound CPU Id = 1

```

## Related information

[libperfstat.h command](#)

## perfstat\_volumegroup Interface

The **perfstat\_volumegroup** interface returns a set of structures of type **perfstat\_logicalvolume\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_logicalvolume\_t** structure include:

Item	Descriptor
<b>Total_disks</b>	Total number of disks in the volume group
<b>Active_disks</b>	Total number of active disks in the volume group
<b>Iocnt</b>	Number of read and write requests

The following code shows an example of how the **perfstat\_logicalvolume** interface is used:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
int vg_count, rc,i;
perfstat_id_t first;
perfstat_volumegroup_t *vg;

strcpy(first.name,NULL);

```

```

/* to enable the volume group statistical collection */
perfstat_config(PERFSTAT_ENABLE|PERFSTAT_LV,NULL);

/* to get the number of volume groups */
vg_count = perfstat_volume group (NULL, NULL, sizeof(perfstat_logical volume_t), 0);
/* check the subroutine return code for any error */
if (vg_count <=0 ){
    perror("perfstat_volume group");
    exit(-1);
}

/* Allocate enough memory to hold all the structures */
vg = (perfstat_volume group_t *)calloc(vg_count, sizeof(perfstat_volume group_t));
if (vg == NULL){
    perror(".malloc");
    exit(-1);
}

/* Call the API to get the data */
rc = perfstat_volume group(&first,vg,sizeof(perfstat_volume group_t),vg_count);
/* check the return code for any error */
if (rc <= 0){
    perror("perfstat_volume group ");
    exit(-1);
}
for(i=0;i<vg_count;i++){
    printf("Volume group name=%s\n",vg[i].name);
    printf("Number of physical volumes in the volume group=%lld\n",vg[i].total_disks);
    printf("Number of active physical volumes in the volume group=%lld\n",vg[i].active_disks);
    printf("Number of logical volumes in the volume group=%lld\n",vg[i].total_logical_volumes);
    printf("Number of logical volumes opened in the volume group=%lld\n",vg[i].opened_logical_volumes);
    printf("Number of read and write requests=%lld\n",vg[i].iocnt);
    printf("Number of Kilobytes read=%lld\n",vg[i].kbreads);
    printf("Number of Kilobytes written=%lld\n",vg[i].kbwrites);
}

/* disable logical volume statistical collection */
perfstat_config(PERFSTAT_DISABLE | PERFSTAT_LV , NULL);

return 0;
}

```

The program displays an output that is similar to the following example output:

```

Volume group name=rootvg
Number of physical volumes in the volume group=1
Number of active physical volumes in the volume group=1
Number of logical volumes in the volume group=16
Number of logical volumes opened in the volume group=11
Number of read and write requests=0
Number of Kilobytes read=0
Number of Kilobytes written=0

```

The preceding program emulates **vmstat** behavior and also shows how **perfstat\_volume group** is used.

## WPAR Interfaces

The following are two types of WPAR interfaces:

- The metrics related to a set of components for a WPAR (such as processors, or memory).
- The specific metrics related to individual components on a WPAR (such as a processor, network interface, or memory page).

All of the following WPAR interfaces use the naming convention **perfstat\_subsystem\_total\_wpar**, and use a common signature:

Item	Descriptor
<b>perfstat_cpu_total_wpar</b>	Retrieves WPAR processor summary usage metrics
<b>perfstat_memory_total_wpar</b>	Retrieves WPAR memory summary usage metrics
<b>perfstat_wpar_total</b>	Retrieves WPAR information metrics
<b>perfstat_memory_page_wpar</b>	Retrieves WPAR memory page usage metrics

The signature used by the **subsystem\_total** interfaces, except for **perfstat\_memory\_page\_wpar**, is as follows:

```
int perfstat_subsystem_total_wpar(perfstat_id_wpar_t *name,
                                perfstat_subsystem_total_t *userbuff,
                                int sizeof_struct,
                                int desired_number);
```

The signature used by the **perfstat\_memory\_page\_wpar** interface is as follows:

```
int perfstat_memory_page_wpar(perfstat_id_wpar_t *name,
                              perfstat_psize_t *psize,
                              perfstat_subsystem_total_t *userbuff,
                              int sizeof_struct,
                              int desired_number);
```

The usage of the parameters for all of the interfaces is as follows:

Item	Descriptor
<b>perfstat_id_wpar_t *name</b>	The WPAR ID or WPAR name for which the metrics must be retrieved.  <b>Note:</b> When called inside of a WPAR environment, the name must be NULL.
<b>perfstat_subsystem_total_t *userbuff</b>	A memory area with enough space for the returned structure.
<b>int sizeof_struct</b>	The size of the <b>perfstat_memory_total_wpar_t</b> structure.
<b>int desired_number</b>	The number of different page size statistics to be collected.

The number of structures copied and returned without errors use the return value of 1. If there are errors, the return value is -1.

An exception to this scheme is **perfstat\_wpar\_total**. For this function, when name=NULL, userbuff=NULL and desired\_number=0, the total number of **perfstat\_wpar\_total\_t** structures available is returned.

To retrieve all **perfstat\_wpar\_total\_t** structures, select one of the following methods:

- Determine the number of structures and allocate the required memory to hold all structure at one time. You can then call the appropriate API to retrieve all structures using one call.
- Allocate a fixed set of structures and repeatedly call the API to get the next number of structures, each time passing the name returned by the previous call. Start the process by using one of the following queries:
  - wparname set to ""
  - FIRST\_WPARNAME
  - wpar\_id set to -1
  - FIRST\_WPARID

Repeat the process until the wparname is returned equal to “ or the wpar\_id is returned equal to -1.

The **perfstat\_id\_wpar\_total** interface returns a set of structures of type **perfstat\_id\_wpar\_total\_t**, which is defined in the [libperfstat.h](#) file. Selected fields from the **perfstat\_id\_wpar\_total\_t** structure include:

Item	Descriptor
<b>spec</b>	Select WPAR ID, WPAR Name, or the RSET Handle from the union
<b>wpar_id</b>	Specifies the WPAR ID
<b>wparname</b>	Specifies the WPAR Name

Item	Descriptor
<b>rset</b>	Specifies the RSET Handle of the rset associated with the WPAR
<b>name</b>	Reserved for future use, must be NULL

The following sections provide examples of the type of data returned and code using each of the interfaces.

## perfstat\_wpar\_total Interface

The **perfstat\_wpar\_total** interface returns a set of structures of type **perfstat\_wpar\_total\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_wpar\_total\_t** structure include:

Item	Descriptor
<b>Type</b>	WPAR type.
<b>online_cpus</b>	The number of virtual processors currently allocated to the partition rset or the number of virtual processors currently allocated to the system partition.
<b>online_memory</b>	The amount of memory currently allocated to the system partition.
<b>cpu_limit</b>	The maximum limit of processor resources this WPAR consumes. The processor limit is in 100ths of percentage units.

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_wpar\_total\_t** section in the **libperfstat.h** header file in *Files Reference*.

The following program emulates **wparstat** behavior and also shows an example of how **perfstat\_wpar\_total** is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main() {
    perfstat_wpar_total_t *winfo;
    perfstat_id_wpar_t wparid;
    int tot, rc, i;

    tot = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);

    if (tot < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (tot == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(tot, sizeof(perfstat_wpar_total_t));
    if(winfo==NULL) {
        printf("No sufficient memory\n");
        exit(-1);
    }

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, FIRST_WPARNAME);
    rc = perfstat_wpar_total(&wparid, winfo, sizeof(perfstat_wpar_total_t), tot);

    if (rc < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }
}
```

```

for(i=0;i<tot;i++){
    printf("Name of the Workload Partition=%s\n",winfo[i].name);
    printf("Workload partition identifier=%u\n",winfo[i].wpar_id);
    printf("Number of Virtual CPUs in partition rset=%d\n",winfo[i].online_cpus);
    printf("Amount of memory currently online in Global Partition=%lld\n",winfo[i].online_memory);
    printf("Number of processor units this partition is entitled to
receive=%d\n",winfo[i].entitled_proc_capacity);
    printf("\n");
}

return(0);
}

```

The program displays an output that is similar to the following example output:

```

Name of the Workload Partition=test
Workload partition identifier=1
Number of Virtual CPUs in partition rset=2
Amount of memory currently online in Global Partition=4096
Number of processor units this partition is entitled to receive=100

```

The following code shows an example of how **perfstat\_wpar\_total** is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_wpar_total_t *winfo;
    perfstat_id_wpar_t wparid;
    int tot, rc, i;

    tot = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);

    if (tot < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (tot == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(tot,sizeof(perfstat_wpar_total_t));
    if(winfo==NULL){
        printf("No sufficient memory\n");
        exit(-1);
    }

    rc = perfstat_wpar_total(NULL, winfo, sizeof(perfstat_wpar_total_t), tot);

    if (rc < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    for(i=0;i<tot;i++){
        printf("Name of the Workload Partition=%s\n",winfo[i].name);
        printf("Workload partition identifier=%u\n",winfo[i].wpar_id);
        printf("Number of Virtual CPUs in partition rset=%d\n",winfo[i].online_cpus);
        printf("Amount of memory currently online in Global Partition=%lld\n",winfo[i].online_memory);
        printf("Number of processor units this partition is entitled to
receive=%d\n",winfo[i].entitled_proc_capacity);
        printf("\n");
    }

    return(0);
}

```

## perfstat\_cpu\_total\_wpar Interface

The **perfstat\_cpu\_total\_wpar** interface returns a set of structures of type **perfstat\_cpu\_total\_wpar\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_total\_wpar\_t** structure include:

Item	Descriptor
<b>processorHz</b>	Processor speed in Hertz (from ODM)
<b>Description</b>	Processor type (from ODM)
<b>Ncpus</b>	Current number of active processors available to the WPAR
<b>ncpus_cfg</b>	Number of configured processors; that is, the maximum number of processors that this copy of AIX® can handle simultaneously
<b>Puser</b>	Total number of physical processor ticks spent in user mode
<b>Psys</b>	Total number of physical processor ticks spent in system (kernel) mode
<b>Piddle</b>	Total number of physical processor ticks spent idle with no I/O pending
<b>Pwait</b>	Total number of physical processor ticks spent idle with I/O pending

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_cpu\_total\_wpar\_t** section in the `libperfstat.h` header file.

The following program emulates **wparstat** behavior and also shows an example of how **perfstat\_cpu\_total\_wpar\_t** is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main() {
    perfstat_cpu_total_wpar_t *cpustats;
    perfstat_id_wpar_t wparid;
    perfstat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

    /* Retrieve total number of WPARs in the system */
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);
    if (totwpars < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (totwpars == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(totwpars,sizeof(perfstat_wpar_total_t));

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, "test");
    rc = perfstat_wpar_total(&wparid, winfo, sizeof(perfstat_wpar_total_t), totwpars);

    if (rc <= 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    for(i=0; i < totwpars; i++)
    {
        bzero(&wparid, sizeof(perfstat_id_wpar_t));
        wparid.spec = WPARID;
        wparid.u.wpar_id = winfo[i].wpar_id;

        cpustats=calloc(1,sizeof(perfstat_cpu_total_wpar_t));
        rc = perfstat_cpu_total_wpar(&wparid, cpustats, sizeof(perfstat_cpu_total_wpar_t), 1);
        if (rc != 1) {
            perror("perfstat_cpu_total_wpar");
            exit(-1);
        }
        for(j=0;j<rc;j++){
            printf("Number of active logical processors in Global=%d\n",cpustats[j].ncpus);
            printf("Processor description=%s\n",cpustats[j].description);
        }
    }
}
```

```

        printf("Processor speed in Hz=%lld\n",cpustats[j].processorHZ);
        printf("Number of process switches=%lld\n",cpustats[j].pswitch);
        printf("Number of forks system calls executed=%lld\n",cpustats[j].sysfork);
        printf("Length of the run queue=%lld\n",cpustats[j].runque);
        printf("Length of the swap queue=%lld\n",cpustats[j].swpque);
    }
}
}

```

The program displays an output that is similar to the following example output:

```

Number of active logical processors in Global=8
Processor description=PowerPC_POWER7
Processor speed in Hz=3304000000
Number of process switches=1995
Number of forks system calls executed=322
Length of the run queue=3
Length of the swap queue=1

```

The following code shows an example of how **perfstat\_cpu\_total\_wpar** is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_wpar_t *cpustats;
    perfstat_id_wpar_t wparid;
    perfstat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

    /* Retrieve total number of WPARs in the system */
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);
    if (totwpars < 0) {

        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    if (totwpars == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(totwpars,sizeof(perfstat_wpar_total_t));

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, "test");
    rc = perfstat_wpar_total(NULL, winfo, sizeof(perfstat_wpar_total_t), totwpars);

    if (rc <= 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }

    for(i=0; i < totwpars; i++)
    {
        bzero(&wparid, sizeof(perfstat_id_wpar_t));
        wparid.spec = WPARID;
        wparid.u.wpar_id = winfo[i].wpar_id;

        cpustats=calloc(1,sizeof(perfstat_cpu_total_wpar_t));
        rc = perfstat_cpu_total_wpar(NULL, cpustats, sizeof(perfstat_cpu_total_wpar_t), 1);
        if (rc != 1) {
            perror("perfstat_cpu_total_wpar");
            exit(-1);
        }
        for(j=0;j<rc;j++){
            printf("Number of active logical processors in Global=%d\n",cpustats[j].ncpus);
            printf("Processor description=%s\n",cpustats[j].description);
            printf("Processor speed in Hz=%lld\n",cpustats[j].processorHZ);
            printf("Number of process switches=%lld\n",cpustats[j].pswitch);
            printf("Number of forks system calls executed=%lld\n",cpustats[j].sysfork);
            printf("Length of the run queue=%lld\n",cpustats[j].runque);
            printf("Length of the swap queue=%lld\n",cpustats[j].swpque);
        }
    }
}

```

```
}  
}
```

## perfstat\_memory\_total\_wpar Interface

The **perfstat\_memory\_total\_wpar** interface returns a set of structures of type **perfstat\_memory\_total\_wpar\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_memory\_total\_wpar\_t** structure include:

Item	Descriptor
<b>real_total</b>	Amount of Global real memory (in units of 4 KB pages)
<b>real_free</b>	Amount of Global free real memory (in units of 4 KB pages)
<b>real_pinned</b>	Amount of WPAR pinned memory (in units of 4 KB pages)
<b>Pgins</b>	Number of WPAR pages paged in
<b>Pgouts</b>	Number of WPAR pages paged out

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_memory\_total\_wpar\_t** section in the [libperfstat.h](#) header file.

The following program emulates **wparstat** behavior and also shows an example of how **perfstat\_memory\_total\_wpar** is used from the global environment:

```
#include <stdio.h>  
#include <stdlib.h>  
#include <libperfstat.h>  
int main(){  
    perfstat_memory_total_wpar_t *memstats;  
    perfstat_id_wpar_t wparid;  
    perfstat_wpar_total_t *winfo;  
    int i,j,rc,totwpars;  
  
    /* Retrieve total number of WPARs in the system */  
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);  
    if (totwpars < 0) {  
        perror("Error in perfstat_wpar_total");  
        exit(-1);  
    }  
    if (totwpars == 0) {  
        printf("No WPARs found in the system\n");  
        exit(-1);  
    }  
  
    /* allocate enough memory for all the structures */  
    winfo = calloc(totwpars,sizeof(perfstat_wpar_total_t));  
  
    /* Retrieve all WPARs */  
    bzero(&wparid, sizeof(perfstat_id_wpar_t));  
    wparid.spec = WPARNAME;  
    strcpy(wparid.u.wparname, "test");  
    rc = perfstat_wpar_total(&wparid, winfo, sizeof(perfstat_wpar_total_t), totwpars);  
    if (rc <= 0) {  
        perror("Error in perfstat_wpar_total");  
        exit(-1);  
    }  
  
    for(i=0; i < totwpars; i++)  
    {  
  
        bzero(&wparid, sizeof(perfstat_id_wpar_t));  
        wparid.spec = WPARID;  
        wparid.u.wpar_id = winfo[i].wpar_id;  
  
        memstats=calloc(1,sizeof(perfstat_memory_total_wpar_t));  
        rc = perfstat_memory_total_wpar(&wparid, memstats, sizeof(perfstat_memory_total_wpar_t), 1);  
        if (rc != 1) {  
            perror("perfstat_memory_total_wpar");  
            exit(-1);  
        }  
    }  
}
```

```

for(j=0;j<rc;j++){
    printf("Global total real memory=%lld\n",memstats[j].real_total);
    printf("Global free real memory=%lld\n",memstats[j].real_free);
    printf("Real memory which is pinned=%lld\n",memstats[j].real_pinned);
    printf("Real memory which is in use=%lld\n",memstats[j].real_inuse);
    printf("Number of page faults=%lld\n",memstats[j].pgexct);
    printf("Number of pages paged in=%lld\n",memstats[j].pgins);
    printf("Number of pages paged out=%lld\n",memstats[j].pgouts);
}
}
}

```

The program produces output that is similar to the following output:

```

Global total real memory=1048576
Global free real memory=721338
Real memory which is pinned=464
Real memory which is in use=2886
Number of page faults=37176802
Number of pages paged in=1304
Number of pages paged out=64

```

The following code shows an example of how **perfstat\_memory\_total\_wpar** is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_memory_total_wpar_t *memstats;
    perfstat_id_wpar_t wparid;
    perfstat_wpar_total_t *winfo;
    int i,j,rc,totwpars;

    /* Retrieve total number of WPARs in the system */
    totwpars = perfstat_wpar_total(NULL, NULL, sizeof(perfstat_wpar_total_t), 0);
    if (totwpars < 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }
    if (totwpars == 0) {
        printf("No WPARs found in the system\n");
        exit(-1);
    }

    /* allocate enough memory for all the structures */
    winfo = calloc(totwpars,sizeof(perfstat_wpar_total_t));

    /* Retrieve all WPARs */
    bzero(&wparid, sizeof(perfstat_id_wpar_t));
    wparid.spec = WPARNAME;
    strcpy(wparid.u.wparname, "test");
    rc = perfstat_wpar_total(NULL, winfo, sizeof(perfstat_wpar_total_t), totwpars);
    if (rc <= 0) {
        perror("Error in perfstat_wpar_total");
        exit(-1);
    }
    for(i=0; i < totwpars; i++)
    {
        bzero(&wparid, sizeof(perfstat_id_wpar_t));
        wparid.spec = WPARID;
        wparid.u.wpar_id = winfo[i].wpar_id;

        memstats=calloc(1,sizeof(perfstat_memory_total_wpar_t));
        rc = perfstat_memory_total_wpar(NULL, memstats, sizeof(perfstat_memory_total_wpar_t), 1);
        if (rc != 1) {
            perror("perfstat_memory_total_wpar");
            exit(-1);
        }
    }
    for(j=0;j<rc;j++){
        printf("Global total real memory=%lld\n",memstats[j].real_total);
        printf("Global free real memory=%lld\n",memstats[j].real_free);
        printf("Real memory which is pinned=%lld\n",memstats[j].real_pinned);
        printf("Real memory which is in use=%lld\n",memstats[j].real_inuse);
        printf("Number of page faults=%lld\n",memstats[j].pgexct);
        printf("Number of pages paged in=%lld\n",memstats[j].pgins);
        printf("Number of pages paged out=%lld\n",memstats[j].pgouts);
    }
}

```

```

}
}
}

```

## perfstat\_memory\_page\_wpar Interface

The `perfstat_memory_page_wpar` interface returns a set of structures of type `perfstat_memory_page_wpar_t`, which is defined in the `libperfstat.h` file.

Selected fields from the `perfstat_memory_page_wpar_t` structure include:

Item	Descriptor
<b>Psize</b>	Page size in bytes
<b>real_total</b>	Amount of Global real memory (in units of the psize)
<b>real_pinned</b>	Amount of WPAR pinned memory (in units of psize)
<b>Pgins</b>	Number of WPAR pages paged in
<b>Pgouts</b>	Number of WPAR pages paged out

Several other paging-space-related metrics (such as number of system calls, number of reads, writes, forks, execs, and load average) are also returned. For a complete list of other paging-space-related metrics, see the `perfstat_memory_page_wpar_t` section in the `libperfstat.h` header file.

The following program emulates `vmstat` behavior and also shows an example of how `perfstat_memory_page_wpar` is used from the global environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
int i, psize, rc;
perfstat_memory_page_wpar_t *pageinfo;
perfstat_id_wpar_t wparid;
wparid.spec = WPARNAME;
strcpy(wparid.u.wparname, "test");
perfstat_psize_t psize;

psize.psize = FIRST_PSIZE;
/* Get the number of page sizes */
psizes = perfstat_memory_page_wpar(&wparid, NULL, NULL, sizeof(perfstat_memory_page_wpar_t), 0);
/*check for error */
if (psizes <= 0){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

/*Allocate enough memory to hold the structures */
pageinfo = (perfstat_memory_page_wpar_t *)calloc(psizes, sizeof(perfstat_memory_page_wpar_t));

/*check for memory allocation */
if (!pageinfo){
    perror("calloc");
    exit(-1);
}

/* call the API and get the data */
rc = perfstat_memory_page_wpar(&wparid, &psize, pageinfo,
sizeof(perfstat_memory_page_wpar_t), psizes);
/* check the return values for any error */
if (rc <= 0){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

for(i=0; i<psizes; i++){
    printf("Page size in bytes=%lld\n", pageinfo[i].psize);
    printf("Number of real memory frames of this page size=%lld\n", pageinfo[i].real_total);
    printf("Number of pages pinned=%lld\n", pageinfo[i].real_pinned);
    printf("Number of pages in use=%lld\n", pageinfo[i].real_inuse);
    printf("Number of page faults=%lld\n", pageinfo[i].pgexct);
    printf("Number of pages paged in=%lld\n", pageinfo[i].pgins);
}
}

```

```

printf("Number of pages paged out=%lld\n",pageinfo[i].pgouts);
printf("Number of page ins from paging space=%lld\n",pageinfo[i].pgspins);
printf("Number of page outs from paging space=%lld\n",pageinfo[i].pgspouts);
printf("Number of page scans by clock=%lld\n",pageinfo[i].scans);
printf("Number of page steals=%lld\n",pageinfo[i].pgsteals);

```

The program produces output that is similar to the following output:

```

Page size in bytes=4096
Number of real memory frames of this page size=572640
Number of pages pinned=143
Number of pages in use=2542
Number of page faults=1613483
Number of pages paged in=1296
Number of pages paged out=58
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0
Page size in bytes=65536
Number of real memory frames of this page size=29746
Number of pages pinned=20
Number of pages in use=20
Number of page faults=25294
Number of pages paged in=0
Number of pages paged out=0
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0
Page size in bytes=0
Number of real memory frames of this page size=0
Number of pages pinned=0
Number of pages in use=0
Number of page faults=0
Number of pages paged in=0
Number of pages paged out=0
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0
Page size in bytes=0
Number of real memory frames of this page size=0
Number of pages pinned=0
Number of pages in use=0
Number of page faults=0
Number of pages paged in=0
Number of pages paged out=0
Number of page ins from paging space=0
Number of page outs from paging space=0
Number of page scans by clock=0
Number of page steals=0

```

The following code shows an example of how **perfstat\_memory\_page\_wpar** is used from the WPAR environment:

```

#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(){
int i, psizes, rc;
perfstat_memory_page_wpar_t *pageinfo;
perfstat_id_wpar_t wparid;
perfstat_psize_t psize;

psize.psize = FIRST_PSIZE;
/* Get the number of page sizes */
psizes = perfstat_memory_page_wpar(&wparid, NULL, NULL, sizeof(perfstat_memory_page_wpar_t),0);
/*check for error */
if (psizes <= 0 ){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

/*Allocate enough memory to hold the structures */
pageinfo = (perfstat_memory_page_wpar_t *)calloc(psizes, sizeof(perfstat_memory_page_wpar_t));

```

```

/*check for memory allocation */
if (!pageinfo){
    perror("calloc");
    exit(-1);
}

/* call the API and get the data */
rc = perfstat_memory_page_wpar(NULL, &psize, pageinfo ,
sizeof(perfstat_memory_page_wpar_t), psize);
/* check the return values for any error */
if (rc <= 0){
    perror("perfstat_memory_page_wpar ");
    exit(-1);
}

for(i=0;i<psize;i++){
    printf("Page size in bytes=%lld\n",pageinfo[i].psize);
    printf("Number of real memory frames of this page size=%lld\n",pageinfo[i].real_total);
    printf("Number of pages pinned=%lld\n",pageinfo[i].real_pinned);
    printf("Number of pages in use=%lld\n",pageinfo[i].real_inuse);
    printf("Number of page faults=%lld\n",pageinfo[i].pgexct);
    printf("Number of pages paged in=%lld\n",pageinfo[i].pgins);
    printf("Number of pages paged out=%lld\n",pageinfo[i].pgouts);
    printf("Number of page ins from paging space=%lld\n",pageinfo[i].pgspins);
    printf("Number of page outs from paging space=%lld\n",pageinfo[i].pgspouts);
    printf("Number of page scans by clock=%lld\n",pageinfo[i].scans);
    printf("Number of page steals=%lld\n",pageinfo[i].pgsteals);
}
}
}

```

## RSET Interfaces

The RSET interface reports processor metrics related to an RSET.

All of the following AIX 6.1 RSET interfaces use the naming convention **perfstat\_subsystem[\_total]\_rset**, and use a common signature:

Item	Descriptor
<b>perfstat_cpu_total_rset</b>	Retrieves processor summary metrics of the processors in an RSET
<b>perfstat_cpu_rset</b>	Retrieves per processor metrics of the processors in an RSET

The signature used by the previous [“perfstat\\_memory\\_page\\_wpar Interface” on page 183](#) is as follows:

```

int perfstat_cpu_rset(perfstat_wpar_id_t *name,
                    perfstat_cpu_t * userbuff,
                    int sizeof_struct,
                    int desired_number);

int perfstat_cpu_total_rset(perfstat_wpar_id_t *name,
                           perfstat_cpu_total_t * userbuff,
                           int sizeof_struct,
                           int desired_number);

```

The usage of the parameters for all of the interfaces is as follows:

<b>Item</b>	<b>Descriptor</b>
<b>perfstat_id_wpar_t *name</b>	Specifies the RSET identifier and the name of the first component (for example, cpu0) for which statistics are desired. A structure containing the specifier, which can be an RSETHANDLE, WPARID, or WPARNAME, a union to specify the wpar ID, or wpar name or rsethandle and a char * field to specify the name of the first component. To start from the first component of a subsystem, set the char* field of the name parameter to "" (empty string). You can also use the macro FIRST_CPU defined in the libperfstat.h file.
<b>perfstat_cpu[_total]_t *userbuff</b>	A pointer to a memory area with enough space for the returned structures.
<b>int sizeof_struct</b>	Should be set to sizeof(perfstat_cpu[_total]_t).
<b>int desired_number</b>	The number of structures of type perfstat_cpu[_total]_t to return in userbuff.

The number of structures copied and returned without errors uses the return value of 1. If there are errors, the return value is -1. The field name is either set to NULL or to the name of the next structure available.

An exception to this scheme is when name=NULL, userbuff=NULL, and desired\_number=0, the total number of structures available is returned.

To retrieve all structures of a given type, either ask first for their number, allocate enough memory to hold them all at once, then call the appropriate API to retrieve them all in one call. Else, allocate a fixed set of structures and repeatedly call the API to get the next such number of structures, each time passing the name returned by the previous call. Start the process with the name set to "" or FIRST\_CPU, and repeat the process until the name returned is equal to "".

The following sections provide examples of the type of data returned and code using each of the interfaces.

## perfstat\_cpu\_rset interface

The **perfstat\_cpu\_rset** interface returns a set of structures of type **perfstat\_cpu\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_t** structure include:

<b>Item</b>	<b>Descriptor</b>
<b>name</b>	Logical processor name (cpu0, cpu1, and so on)
<b>user</b>	Number of clock ticks spent in user mode
<b>sys</b>	Number of clock ticks spent in system (kernel) mode
<b>idle</b>	Number of clock ticks spent idle with no I/O pending
<b>wait</b>	Number of clock ticks spent idle with I/O pending
<b>syscall</b>	Number of system call executed

Several other paging-space-related metrics (such as number of forks, reads, writes, and execs) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_cpu\_t** section in the [libperfstat.h](#) header file.

The following code shows an example of how **perfstat\_cpu\_rset** is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    int i, retcode, rsetcpus;
```

```

perfstat_id_wpar_t wparid;
perfstat_cpu_t *statp;
wparid.spec = WPARNAME;
strcpy(wparid.u.wparname, NULL);

/* give the wparname "wpar1" as the identifier */
strcpy(wparid.u.wparname, "test");

/* check how many perfstat_cpu_t structures are available */
rsetcpus = perfstat_cpu_rset(&wparid, NULL, sizeof(perfstat_cpu_t), 0);

if (rsetcpus < 0 ){
    perror("perfstat_cpu_rset");
    exit(-1);
}

/*allocate memory for perfstat_cpu_t structures */
statp = (perfstat_cpu_t *)calloc(rsetcpus , sizeof(perfstat_cpu_t));

if(!statp){
    perror("calloc");
}

/*call the API and get the values */

retcode = perfstat_cpu_rset(&wparid, statp, sizeof(perfstat_cpu_t), rsetcpus);

if(retcode < 0){
    perror("perfstat_cpu_rset");
}

for(i=0;i<retcode;i++){
    printf("Logical processor name=%s\n", statp[i].name);
    printf("Raw number of clock ticks spent in user mode=%lld\n", statp[i].user);
    printf("Raw number of clock ticks spent in system mode=%lld\n", statp[i].sys);
    printf("Raw number of clock ticks spent in idle mode=%lld\n", statp[i].idle);
    printf("Raw number of clock ticks spent in wait mode=%lld\n", statp[i].wait);
}
return 0;
}

```

The program displays an output that is similar to the following example output:

```

Logical processor name=cpu0
Raw number of clock ticks spent in user mode=2050
Raw number of clock ticks spent in system mode=22381
Raw number of clock ticks spent in idle mode=6863114
Raw number of clock ticks spent in wait mode=3002
Logical processor name=cpu1
Raw number of clock ticks spent in user mode=10
Raw number of clock ticks spent in system mode=651
Raw number of clock ticks spent in idle mode=6876627
Raw number of clock ticks spent in wait mode=42
Logical processor name=cpu2
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=610
Raw number of clock ticks spent in idle mode=6876712
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu3
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=710
Raw number of clock ticks spent in idle mode=6876612
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu4
Raw number of clock ticks spent in user mode=243
Raw number of clock ticks spent in system mode=1659
Raw number of clock ticks spent in idle mode=6875427
Raw number of clock ticks spent in wait mode=62
Logical processor name=cpu5
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=207327
Raw number of clock ticks spent in idle mode=6848952
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu6
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=207904
Raw number of clock ticks spent in idle mode=6849969
Raw number of clock ticks spent in wait mode=0
Logical processor name=cpu7
Raw number of clock ticks spent in user mode=0
Raw number of clock ticks spent in system mode=207375

```

```
Raw number of clock ticks spent in idle mode=6848209
Raw number of clock ticks spent in wait mode=0
```

The following code shows an example of how **perfstat\_cpu\_rset** is used from the WPAR environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    int i, retcode, rsetcpus;
    perfstat_id_wpar_t wparid;
    perfstat_cpu_t *statp;

    /* check how many perfstat_cpu_t structures are available */
    rsetcpus = perfstat_cpu_rset(NULL, NULL, sizeof(perfstat_cpu_t), 0);

    if (rsetcpus < 0 ){
        perror("perfstat_cpu_rset");
        exit(-1);
    }

    /*allocate memory for perfstat_cpu_t structures */
    statp = (perfstat_cpu_t *)calloc(rsetcpus , sizeof(perfstat_cpu_t));

    if(!statp){
        perror("calloc");
    }

    /*call the API and get the values */

    retcode = perfstat_cpu_rset(NULL, statp,sizeof(perfstat_cpu_t), rsetcpus);

    if(retcode < 0){
        perror("perfstat_cpu_rset");
    }

    for(i=0;i<retcode;i++){
        printf("Logical processor name=%s\n",statp[i].name);
        printf("Raw number of clock ticks spent in user mode=%lld\n",statp[i].user);
        printf("Raw number of clock ticks spent in system mode=%lld\n",statp[i].sys);
        printf("Raw number of clock ticks spent in idle mode=%lld\n",statp[i].idle);
        printf("Raw number of clock ticks spent in wait mode=%lld\n",statp[i].wait);
    }
    return 0;
}
```

## perfstat\_cpu\_total\_rset interface

The **perfstat\_cpu\_total\_rset** interface returns a set of structures of type **perfstat\_cpu\_total\_t**, which is defined in the **libperfstat.h** file.

Selected fields from the **perfstat\_cpu\_t** structure include:

Item	Descriptor
<b>processorHz</b>	Processor speed in Hertz (from ODM)
<b>description</b>	Processor type (from ODM)
<b>CPUs</b>	Current number of active processors
<b>ncpus_cfg</b>	Number of configured processors (maximum number of processors that this copy of AIX can handle simultaneously)
<b>ncpus_high</b>	Maximum number of active processors; that is, the maximum number of active processors since the last reboot
<b>User</b>	Total number of clock ticks spent in user mode
<b>Sys</b>	Total number of clock ticks spent in system (kernel) mode
<b>Idle</b>	Total number of clock ticks spent idle with no I/O pending
<b>Wait</b>	Total number of clock ticks spent idle with I/O pending

Several other paging-space-related metrics (such as number of forks, read, writes, and execs) are also returned. For a complete list of other paging-space-related metrics, see the **perfstat\_cpu\_total\_t** section in the [libperfstat.h](#) header file.

The following code shows an example of how the **perfstat\_cpu\_total\_rset** interface is used from the global environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_t *cpustats;
    perfstat_id_wpar_t wparid;
    int rc,i;
    wparid.spec = WPARNAME;

    rc = perfstat_cpu_total_rset(NULL,NULL,sizeof(perfstat_cpu_total_t),0);
    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }

    cpustats=calloc(rc,sizeof(perfstat_cpu_total_t));
    if(cpustats==NULL){
        perror("MALLOC error:");
        exit(-1);
    }

    strcpy(wparid.u.wparname,"test");
    rc = perfstat_cpu_total_rset(&wparid, cpustats, sizeof(perfstat_cpu_total_t), rc);

    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }
    for(i=0;i<rc;i++){
        printf("Number of active logical processors=%d\n",cpustats[i].ncpus);
        printf("Number of configured processors=%d\n",cpustats[i].ncpus_cfg);
        printf("Processor description=%s\n",cpustats[i].description);
        printf("Processor speed in Hz=%lld\n",cpustats[i].processorHZ);
        printf("Raw total number of clock ticks spent in user mode=%lld\n",cpustats[i].user);
        printf("Raw total number of clock ticks spent in system mode=%lld\n",cpustats[i].sys);
        printf("Raw total number of clock ticks spent idle=%lld\n",cpustats[i].idle);
        printf("Raw total number of clock ticks spent wait=%lld\n",cpustats[i].wait);
    }
    return 0;
}
```

The program produces output that is similar to the following output:

```
Number of active logical processors=8
Number of configured processors=8
Processor description=PowerPC_POWER7
Processor speed in Hz=3304000000
Raw total number of clock ticks spent in user mode=86400
Raw total number of clock ticks spent in system mode=30636100
Raw total number of clock ticks spent idle=2826632699
Raw total number of clock ticks spent wait=852000
```

The following code shows an example of how **perfstat\_cpu\_total\_rset** is used from the WPAR environment:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>
int main(){
    perfstat_cpu_total_t *cpustats;
    perfstat_id_wpar_t wparid;
    int rc,i;

    rc = perfstat_cpu_total_rset(NULL,NULL,sizeof(perfstat_cpu_total_t),0);
    if (rc <= 0) {
        perror("perfstat_cpu_total_rset");
        exit(-1);
    }

    cpustats=calloc(rc,sizeof(perfstat_cpu_total_t));
```

```

if(cpustats==NULL){
    perror("MALLOC error:");
    exit(-1);
}

rc = perfstat_cpu_total_rset(NULL, cpustats, sizeof(perfstat_cpu_total_t), rc);

if (rc <= 0) {
    perror("perfstat_cpu_total_rset");
    exit(-1);
}
for(i=0;i<rc;i++){
    printf("Number of active logical processors=%d\n",cpustats[i].ncpus);
    printf("Number of configured processors=%d\n",cpustats[i].ncpus_cfg);
    printf("Processor description=%s\n",cpustats[i].description);
    printf("Processor speed in Hz=%lld\n",cpustats[i].processorHZ);
    printf("Raw total number of clock ticks spent in user mode=%lld\n",cpustats[i].user);
    printf("Raw total number of clock ticks spent in system mode=%lld\n",cpustats[i].sys);
    printf("Raw total number of clock ticks spent idle=%lld\n",cpustats[i].idle);
    printf("Raw total number of clock ticks spent wait=%lld\n",cpustats[i].wait);
}
return 0;
}

```

## Cached metrics interfaces

Cached metrics interfaces are used when the system configuration changes to inform the **libperfstat** API that it must reset cached metrics, which consist of values that seldom change such as disk size or processor description.

The following table lists the metrics that are cached:

Object	Content	Sample value
<b>perfstat_cpu_total</b>	char cpu_description [IDENTIFIER_LENGTH] u_longlong_t processorHZ	PowerPC_POWER3375000000
<b>perfstat_diskadapter</b>	The list of disk adapters The number of disk adapters u_longlong_t size u_longlong_t free char description [IDENTIFIER_LENGTH]	scsi0, scsi1, ide0 3 17344 15296 Wide/Ultra-3 SCSI I/O Controller
<b>perfstat_pagingSPACE</b>	The list of paging spaces The number of paging spaces char automatic char type longlong_t lpsize longlong_t mbsize char hostname [IDENTIFIER_LENGTH] char filename [IDENTIFIER_LENGTH]	hd6 1 1 NFS_PAGING 16 512pompei or rootvg /var/tmp/ nfsswap/swapfile1
<b>perfstat_disk</b>	char adapter [IDENTIFIER_LENGTH] char description [IDENTIFIER_LENGTH] char vgname [IDENTIFIER_LENGTH] u_longlong_t sizeu_longlong_t free	scsi0 16 Bit LVD SCSI Disk Drive rootvg 17344 15296
<b>perfstat_diskpath</b>	char adapter [IDENTIFIER_LENGTH]	scsi0
<b>perfstat_netinterface</b>	char description [IDENTIFIER_LENGTH]	Standard Ethernet Network Interface
<b>perfstat_logicalvolume</b>	char description [IDENTIFIER_LENGTH]	Logical volume1
<b>perfstat_volumegroup</b>	char description [IDENTIFIER_LENGTH]	Volume group1

You can use the following AIX interfaces to refresh the cached metrics:

Interface	Purpose	Definition of interface
<b>perfstat_reset</b>	Resets every cached metric	<code>void perfstat_reset (void);</code>
<b>perfstat_partial_reset</b>	Resets selected cached metrics or resets the system's minimum and maximum counters for disks	<code>void perfstat_partial_reset (char * name, u_longlong_t resetmask);</code>

The usage of the parameters for all of the interfaces is as follows:

Parameter	Usage
<code>char *name</code>	Identifies the name of the component of the cached metric that must be reset from the <b>libperfstat</b> API cache. If the value of the parameter is NULL, this signifies all of the components.
<code>u_longlong_t resetmask</code>	Identifies the category of the component if the value of the <b>name</b> parameter is not NULL. The possible values are: <ul style="list-style-type: none"> <li>• FLUSH_CPUTOTAL</li> <li>• FLUSH_DISK</li> <li>• RESET_DISK_MINMAX</li> <li>• FLUSH_DISKADAPTER</li> <li>• FLUSH_DISKPATH</li> <li>• FLUSH_NETINTERFACE</li> <li>• FLUSH_PAGINGSPEACE</li> <li>• FLUSH_LOGICALVOLUME</li> <li>• FLUSH_VOLUMEGROUP</li> </ul> If the value of the <b>name</b> parameter is NULL, the <b>resetmask</b> parameter value consists of a combination of values. For example: RESET_DISK_MINMAX   FLUSH_CPUTOTAL   FLUSH_DISK

## The perfstat\_reset interface

The **perfstat\_reset** interface resets every cached metric that is stored by the **libperfstat** API. It also resets the system's minimum and maximum counters related to disks and paths. To be more selective, it is advised to use the **perfstat\_partial\_reset** interface.

## perfstat\_partial\_reset Interface

The **perfstat\_partial\_reset** interface resets the specified cached metrics that are stored by the **libperfstat** API.

The **perfstat\_partial\_reset** interface can also reset the system's minimum and maximum counters related to disks and paths. The following table summarizes the various actions of the **perfstat\_partial\_reset** interface:

The resetmask value	Action taken when the value of name is NULL	Action taken when the value of name is not NULL and a single resetmask value is set
<b>FLUSH_CPUTOTAL</b>	Flushes the speed and description values in the <b>perfstat_cputotal_t</b> structure.	Error. The value of <b>errno</b> is set to EINVAL.

The resetmask value	Action taken when the value of name is NULL	Action taken when the value of name is not NULL and a single resetmask value is set
<b>FLUSH_DISK</b>	Flushes the description, adapter, size, free, and vname values in every <b>perfstat_disk_t</b> structure. Flushes the list of disk adapters. Flushes the size, free, and description values in every <b>perfstat_diskadapter_t</b> structure.	Flushes the description, adapter, size, free, and vname values in the specified <b>perfstat_disk_t</b> structure. Flushes the adapter value in every <b>perfstat_diskpath_t</b> structure that matches the disk name that is followed by the <b>_Path</b> identifier. Flushes the size, free, and description values of each <b>perfstat_diskadapter_t</b> structure that is linked to a path leading to the disk or to the disk itself.
<b>RESET_DISK_MINMAX</b>	Resets the following values in every <b>perfstat_diskadapter_t</b> structure: <ul style="list-style-type: none"> <li>• wq_min_time</li> <li>• wq_max_time</li> <li>• min_rserv</li> <li>• max_rserv</li> <li>• min_wserv</li> <li>• max_wserv</li> </ul>	Error. The value of <b>errno</b> is set to ENOTSUP.
<b>FLUSH_DISKADAPTER</b>	Flushes the list of disk adapters. Flushes the size, free, and description values in every <b>perfstat_diskadapter_t</b> structure. Flushes the adapter value in every <b>perfstat_diskpath_t</b> structure. Flushes the description and adapter values in every <b>perfstat_disk_t</b> structure.	Flushes the list of disk adapters. Flushes the size, free, and description values in every <b>perfstat_diskadapter_t</b> structure. Flushes the adapter value in every <b>perfstat_diskpath_t</b> structure. Flushes the description and adapter values in every <b>perfstat_disk_t</b> structure.
<b>FLUSH_DISKPATH</b>	Flushes the adapter value in every <b>perfstat_diskpath_t</b> structure.	Flushes the adapter value in the specified <b>perfstat_diskpath_t</b> structure.
<b>FLUSH_PAGINGSPEACE</b>	Flushes the list of paging spaces. Flushes the automatic, type, lpsize, mbsize, hostname, filename, and vname values in every <b>perfstat_pagingspace_t</b> structure.	Flushes the list of paging spaces. Flushes the automatic, type, lpsize, mbsize, hostname, filename, and vname values in the specified <b>perfstat_pagingspace_t</b> structure.
<b>FLUSH_NETINTERFACE</b>	Flushes the description value in every <b>perfstat_netinterface_t</b> structure.	Flushes the description value in the specified <b>perfstat_netinterface_t</b> structure.
<b>FLUSH_LOGICALVOLUME</b>	Flushes the description value in every <b>perfstat_logicalvolume_t</b> structure.	Flushes the description value in every <b>perfstat_logicalvolume_t</b> structure.

The resetmask value	Action taken when the value of name is NULL	Action taken when the value of name is not NULL and a single resetmask value is set
<b>FLUSH_VOLUMEGROUP</b>	Flushes the description value in every <b>perfstat_volumegroup_t</b> structure.	Flushes the description value in every <b>perfstat_volumegroup_t</b> structure.

You can see how to use the **perfstat\_partial\_reset** interface in the following example code:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

int main(int argc, char *argv[]) {
    int i, retcode;
    perfstat_id_t diskname;
    perfstat_disk_t *statp;

    /* set name of the disk */
    strcpy(diskname.name, "hdisk0");

    /* we will now reset global system min/max metrics
     * Be careful as this could interact with other programs.
     */
    perfstat_partial_reset(NULL, RESET_DISK_MINMAX);

    /* min/max values are now reset.
     * We can now wait for some time before checking the variation range.
     */
    sleep(10);

    retcode = perfstat_disk(NULL, NULL, sizeof(perfstat_disk_t), 0);
    statp = calloc (retcode, sizeof(perfstat_disk_t));
    /* get disk metrics - min/max counters illustrate variations during the
     * last 60 seconds unless someone else reset these
     * values in the meantime.
     */
    retcode = perfstat_disk(&diskname, statp, sizeof(perfstat_disk_t), 1);

    /* At this point, we assume the disk free part changes due to chfs for example */

    /* if we get disk metrics here, the free field will be wrong as it was
     * cached by the libperfstat.
     */

    /* That is why we reset cached metrics */
    perfstat_partial_reset("hdisk0", FLUSH_DISK);

    /* we can now get updated disk metrics */
    retcode = perfstat_disk(&diskname, statp, sizeof(perfstat_disk_t), 1);

    for(i=0; i<retcode; i++){
        printf("Name of the disk=%s\n", statp[i].name);
        printf("Disk description=%s\n", statp[i].description);
        printf("Volume group name=%s\n", statp[i].vgname);
        printf("Size of the disk=%lld\n", statp[i].size);
        printf("Free portion of the disk=%lld\n", statp[i].free);
        printf("Disk block size=%lld\n", statp[i].bsize);
    }
}
```

The program displays an output that is similar to the following example output:

```
Name of the disk=hdisk0
Disk description=Virtual SCSI Disk Drive
Volume group name=rootvg
Size of the disk=25568
Free portion of the disk=18752
Disk block size=512
```

## Node interfaces

Node interfaces report metrics related to a set of components or individual components of a remote node in the cluster. The components include processors or memory, and individual components include a processor, network interface, or memory page of the remote node in the cluster.

The remote node must belong to one of the clusters of the current node, which uses the perfstat API.

The following node interfaces use the `perfstat_subsystem_node` as the naming convention and a common signature:

Item	Descriptor
<b>perfstat_cpu_node</b>	Retrieves the usage metrics of an individual processor on a remote node.
<b>perfstat_disk_node</b>	Retrieves the usage metrics of an individual disk on a remote node.
<b>perfstat_diskadapter_node</b>	Retrieves the adapter metrics of a disk on a remote node.
<b>perfstat_diskpath_node</b>	Retrieves the path metrics of a disk on a remote node.
<b>perfstat_logicalvolume_node</b>	Retrieves the usage metrics of a logical volume on a remote node.
<b>perfstat_memory_page_node</b>	Retrieves the usage metrics of a memory page size on a remote node.
<b>perfstat_netbuffer_node</b>	Retrieves the buffer allocation metrics of a network on a remote node.
<b>perfstat_netinterface_node</b>	Retrieves the interface metrics of a network on a remote size node.
<b>perfstat_pagingpage_node</b>	Retrieves the space metrics of a page on a remote node.
<b>perfstat_protocol_node</b>	Retrieves the protocol-related metrics of a network on a remote node.
<b>perfstat_tape_node</b>	Retrieves the usage metrics of a tape on a remote node.
<b>perfstat_volumegroup_node</b>	Retrieves the usage metrics of a volume group on a remote node.
<b>perfstat_cpu_total_node</b>	Retrieves the summary on the usage metrics of a processor on a remote node.
<b>perfstat_partition_total_node</b>	Retrieves the partition metrics on a remote node.
<b>perfstat_tape_total_node</b>	Retrieves the summary on the usage metrics of a tape on a remote node.
<b>perfstat_memory_total_node</b>	Retrieves the summary on the usage metrics of a memory on a remote node.
<b>perfstat_netinterface_total_node</b>	Retrieves the summary on the usage metrics of a network interface on a remote node.
<b>perfstat_disk_total_node</b>	Retrieves the summary on the usage metrics of a disk on a remote node.

The following common signature is used by the `perfstat_subsystem_node` interface except the `perfstat_memory_page_node` interface:

```
int perfstat_subsystem_node(perfstat_id_node_t *name,
perfstat_subsystem_t *userbuff,
int sizeof_struct,
int desired_number);
```

The following signature is used by the `perfstat_memory_page_node` interface:

```
int perfstat_memory_page_node(perfstat_id_node_t *name,
perfstat_psize_t *psize;
perfstat_subsystem_t *userbuff,
int sizeof_struct,
int desired_number);
```

The following table describes the usage of the parameters of the `perfstat_subsystem_node` interface:

Item	Descriptor
<b>perfstat_id_node_t *name</b>	Specify the name of the node in <code>name-&gt;u.nodenameformat</code> . The name must contain the name of the first component. For example, <code>hdisk2</code> for <code>perfstat_disk_node()</code> , where <code>hdisk 2</code> is the name of the disk for which you require the statistics.  <b>Note:</b> When you specify a nodename, it must be initialized as <code>NODENAME</code> .
<b>perfstat_subsystem_t *userbuff</b>	Points to a memory area that has enough space for the returned structure.
<b>int sizeof_struct</b>	Sets this parameter to the size of <code>perfstat_subsystem_t</code> .
<b>int desired_number</b>	Specifies the number of structures of type <code>perfstat_subsystem_t</code> to return to a <code>userbuff</code> field.

The `perfstat_subsystem_node` interface return -1 value for error. Otherwise it returns the number of structures copied. The field `namename` is set to the name of the next available structure, and an exceptional case when `userbuff` equals `NULL` and `desired_number` equals `0`, the total number of structures available is returned.

The following example shows the usage of the `perfstat_disk_node` interface:

```
#include <stdio.h>
#include <stdlib.h>
#include <libperfstat.h>

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

int main(int argc, char* argv[])
{
    int i, ret, tot;
    int interval = INTERVAL_DEFAULT, count = COUNT_DEFAULT;
    int collect_remote_node_stats = 0;
    char nodename[MAXHOSTNAMELEN];
    perfstat_disk_t *stap;
    perfstat_id_t first;
    perfstat_id_node_t nodeid;

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of interations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and terminate */
                fprintf(stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>] [-n <node name in the cluster>]\n",
argv[0]);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        ret = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (ret == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }
}
```

```

/* check how many perfstat_disk_t structures are available */
if(collect_remote_node_stats)
{
    strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
    nodeid.spec = NODENAME;
    tot = perfstat_disk_node(&nodeid, NULL, sizeof(perfstat_disk_t), 0);
}
else
{
    tot = perfstat_disk(NULL, NULL, sizeof(perfstat_disk_t), 0);
}

/* check for error */
if (tot < 0)
{
    perror("perfstat_disk");
    exit(-1);
}
if (tot == 0)
{
    printf("No disks found\n");
    exit(-1);
}

/* allocate enough memory for all the structures */
statp = calloc(tot, sizeof(perfstat_disk_t));
if(statp==NULL){
    printf("No sufficient memory\n");
    exit(-1);
}

if(collect_remote_node_stats)
{
    /* Remember nodename is already set */
    /* Now set name to first interface */
    strcpy(nodeid.name, FIRST_DISK);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_disk_node(&nodeid, statp,
        sizeof(perfstat_disk_t), tot);
}
else
{
    /* set name to first interface */
    strcpy(first.name, FIRST_DISK);

    /* ask to get all the structures available in one call */
    /* return code is number of structures returned */
    ret = perfstat_disk(&first, statp,
        sizeof(perfstat_disk_t), tot);
}

/* check for error */
if (ret <= 0)
{
    perror("perfstat_disk");
    exit(-1);
}

/* print statistics for each of the disks */
for (i = 0; i < ret; i++) {
    printf("\nStatistics for disk : %s\n", statp[i].name);
    printf("-----\n");
    printf("description          : %s\n", statp[i].description);
    printf("volume group name      : %s\n", statp[i].vgname);
    printf("adapter name           : %s\n", statp[i].adapter);
    printf("size                   : %llu MB\n", statp[i].size);
    printf("free space              : %llu MB\n", statp[i].free);
    printf("number of blocks read   : %llu blocks of %llu bytes\n", statp[i].rblks, statp[i].bsize);
    printf("number of blocks written : %llu blocks of %llu bytes\n", statp[i].wblks, statp[i].bsize);
}

if(collect_remote_node_stats) {
    /* Now disable cluster statistics by calling perfstat_config */
    perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}
}

```

The program displays an output that is similar to the following example output:

```

Statistics for disk : hdisk0
-----
description          : Virtual SCSI Disk Drive
volume group name    : rootvg
adapter name         : vscsi0
size                 : 25568 MB
free space           : 19616 MB
number of blocks read : 315130 blocks of 512 bytes
number of blocks written : 228352 blocks of 512 bytes

```

The following program shows the usage of the **vmstat** command and an example of using the `perfstat_memory_total_node` interface to retrieve the virtual memory details of the remote node:

```

#include <stdio.h>
#include <libperfstat.h>

#define INTERVAL_DEFAULT 2
#define COUNT_DEFAULT 10

```

```

int main(int argc, char* argv[])
{
    perfstat_memory_total_t minfo;
    perfstat_id_node_t nodeid;
    char nodename[MAXHOSTNAMELEN];
    int interval = INTERVAL_DEFAULT, count = COUNT_DEFAULT;
    int collect_remote_node_stats = 0;
    int i, rc;

    /* Process the arguments */
    while ((i = getopt(argc, argv, "i:c:n:")) != EOF)
    {
        switch(i)
        {
            case 'i': /* Interval */
                interval = atoi(optarg);
                if( interval <= 0 )
                    interval = INTERVAL_DEFAULT;
                break;
            case 'c': /* Number of iterations */
                count = atoi(optarg);
                if( count <= 0 )
                    count = COUNT_DEFAULT;
                break;
            case 'n': /* Node name in a cluster environment */
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                nodename[MAXHOSTNAMELEN-1] = '\0';
                collect_remote_node_stats = 1;
                break;
            default:
                /* Invalid arguments. Print the usage and end */
                fprintf(stderr, "usage: %s [-i <interval in seconds>] [-c <number of iterations>] [-n <node name in the cluster>]\n",
argv[0]);
        }
    }

    if(collect_remote_node_stats)
    {
        /* perfstat_config needs to be called to enable cluster statistics collection */
        rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
        if (rc == -1)
        {
            perror("cluster statistics collection is not available");
            exit(-1);
        }
    }

    if(collect_remote_node_stats)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
        nodeid.spec = NODENAME;
        rc = perfstat_memory_total_node(&nodeid, &minfo, sizeof(perfstat_memory_total_t), 1);
    }
    else
    {
        rc = perfstat_memory_total(NULL, &minfo, sizeof(perfstat_memory_total_t), 1);
    }

    if (rc != 1) {
        perror("perfstat_memory_total");
        exit(-1);
    }

    printf("Memory statistics\n");
    printf("-----\n");
    printf("real memory size           : %llu MB\n",
minfo.real_total*4096/1024/1024);
    printf("reserved paging space      : %llu MB\n",minfo.pgsp_rsvd);
    printf("virtual memory size        : %llu MB\n",
minfo.virt_total*4096/1024/1024);
    printf("number of free pages       : %llu\n",minfo.real_free);
    printf("number of pinned pages     : %llu\n",minfo.real_pinned);
    printf("number of pages in file cache : %llu\n",minfo.numperm);
    printf("total paging space pages   : %llu\n",minfo.pgsp_total);
    printf("free paging space pages    : %llu\n", minfo.pgsp_free);
    printf("used paging space          : %3.2f%%\n",
(float)(minfo.pgsp_total-minfo.pgsp_free)*100.0/
(float)minfo.pgsp_total);
    printf("number of paging space page ins : %llu\n",minfo.pgspins);
    printf("number of paging space page outs : %llu\n",minfo.pgspouts);
    printf("number of page ins         : %llu\n",minfo.pgins);
    printf("number of page outs        : %llu\n",minfo.pgouts);

    if(collect_remote_node_stats) {
        /* Now disable cluster statistics by calling perfstat_config */
        perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
    }
}

```

The program displays an output that is similar to the following example output:

```

Memory statistics
-----
real memory size           : 4096 MB
reserved paging space      : 512 MB
virtual memory size        : 4608 MB
number of free pages       : 768401
number of pinned pages     : 237429
number of pages in file cache : 21473
total paging space pages   : 131072
free paging space pages    : 128821
used paging space          : 1.72%
number of paging space page ins : 0

```

```

number of paging space page outs : 0
number of page ins                 : 37301
number of page outs                 : 9692

```

The `perfstat_cluster_total` interface is used to retrieve cluster statistics from the `perfstat_cluster_total_t` structure, which is defined in the `libperfstat.h` file. The following selected fields are from the `perfstat_cpu_total_t` structure:

Item	Descriptor
<b>name</b>	Specifies the name of the cluster.
<b>Type</b>	Specifies the set of bits that describes the cluster.
<b>num_nodes</b>	Specifies the number of nodes in the cluster.
<b>node_data</b>	Points to a memory area that describes the details of all the nodes.
<b>num_disks</b>	Specifies the number of disks in the cluster.
<b>disk_data</b>	Points to a memory area that describes the details of all the disks.

For a complete list of parameters related to the `perfstat_cluster_total_t` structure, see the [libperfstat.h](#) header file.

The following code example shows the usage of the `perfstat_cluster_total` interface:

```

#include <stdio.h>
#include <libperfstat.h>

typedef enum {
    DISPLAY_DEFAULT = 0,
    DISPLAY_NODE_DATA = 1,
    DISPLAY_DISK_DATA = 2
} display_t;

int main(int argc, char* argv[])
{
    perfstat_cluster_total_t cstats;
    perfstat_node_data_t *node_details;
    perfstat_disk_data_t *disk_details;
    perfstat_id_node_t nodeid;
    display_t display = DISPLAY_DEFAULT;
    int num_nodes;
    int i, rc;

    /* Process the arguments */
    while ((i = getopt(argc, argv, "lnd")) != EOF)
    {
        switch(i)
        {
            case 'n': /* Request to display node data */
                display |= DISPLAY_NODE_DATA;
                break;
            case 'd': /* Request to display disk data */
                display |= DISPLAY_DISK_DATA;
                break;
            case 'h': /* Print help message */
            default:
                /* Print the usage and end */
                fprintf(stderr, "usage: %s [-n] [-d]\n", argv[0]);
                exit(-1);
        }
    }

    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }

    /* Collect cluster statistics */
    strncpy(nodeid.u.nodename, FIRST_CLUSTERNAME, MAXHOSTNAMELEN);
    nodeid.spec = CLUSTERNAME;
    cstats.node_data = NULL; /* To indicate no interest in node details */

```

```

cstats.disk_data = NULL; /* To indicate no interest in disk details */
rc = perfstat_cluster_total(&nodeid, &cstats, sizeof(perfstat_cluster_total_t), 1);
if (rc == -1)
{
    perror("perfstat_cluster_total failed");
    exit(-1);
}
fprintf(stdout, "Cluster statistics\n");
fprintf(stdout, "-----\n");
fprintf(stdout, "Cluster Name : %s\n", cstats.name);
fprintf(stdout, "Cluster type : ");
if (cstats.type.b.is_local)
    fprintf(stdout, "LOCAL\n");
else if (cstats.type.b.is_zone)
    fprintf(stdout, "ZONE\n");
else if (cstats.type.b.is_link)
    fprintf(stdout, "LINK\n");
fprintf(stdout, "Number of nodes : %u\n", cstats.num_nodes);
fprintf(stdout, "Number of disks : %u\n", cstats.num_disks);

/* check if the user requested node data */
if(((display & DISPLAY_NODE_DATA) && (cstats.num_nodes > 0)) ||
    ((display & DISPLAY_DISK_DATA) && (cstats.num_disks > 0)))
{
    if(display & DISPLAY_NODE_DATA)
    {
        cstats.sizeof_node_data = sizeof(perfstat_node_data_t);
        /* Make sure you allocate at least cstats.num_nodes */
        /* Otherwise, perfstat_cluster_total() fails with ENOSPC */
        cstats.node_data = (perfstat_node_data_t *) malloc(cstats.sizeof_node_data *
cstats.num_nodes);
        if(cstats.node_data == NULL)
        {
            perror("malloc failed for node_data");
            exit(-1);
        }
    }
    if(display & DISPLAY_DISK_DATA)
    {
        cstats.sizeof_disk_data = sizeof(perfstat_disk_data_t);
        /* Make sure you allocate at least cstats.num_disks */
        /* Otherwise, perfstat_cluster_total() fails with ENOSPC */
        cstats.disk_data = (perfstat_disk_data_t *) malloc(cstats.sizeof_disk_data *
cstats.num_disks);
        if(cstats.disk_data == NULL)
        {
            perror("malloc failed for disk_data");
            exit(-1);
        }
    }

    rc = perfstat_cluster_total(&nodeid, &cstats, sizeof(perfstat_cluster_total_t), 1);
    if (rc == -1)
    {
        perror("perfstat_cluster_total failed");
        exit(-1);
    }
    if(display & DISPLAY_NODE_DATA)
    {
        fprintf(stdout, "\nNode details:\n");
        fprintf(stdout, "-----\n");
        node_details = cstats.node_data;
        for (i = 0; i < cstats.num_nodes; i++, node_details++)
        {
            fprintf(stdout, "Node name : %s\n", node_details->name);
            fprintf(stdout, "Node shorthand id : %llu\n",
                node_details->shorthand_id);
            fprintf(stdout, "Status of the node : ");
            if (node_details->status.b.is_up)
                fprintf(stdout, "UP\n");
            else if (node_details->status.b.is_down)
                fprintf(stdout, "DOWN\n");
            fprintf(stdout, "Number of clusters the node is participating : %u\n", node_details-
>num_clusters);
            fprintf(stdout, "Number of zones the node is participating : %u\n", node_details-
>num_zones);
            fprintf(stdout, "Number of points of contact to the node :%u\n", node_details-
>num_points_of_contact);
            fprintf(stdout, "\n");
        }
    }
}

```

```

if(display & DISPLAY_DISK_DATA)
{
    fprintf(stdout, "\nDisk details:\n");
    fprintf(stdout, "-----\n");
    disk_details = cstats.disk_data;
    for (i = 0; i < cstats.num_disks; i++, disk_details++)
    {
        fprintf(stdout, "Disk name : %s\n", disk_details->name);
        fprintf(stdout, "Status of the disk :");
        if (disk_details->status.b.is_found)
        {
            fprintf(stdout, " FOUND");
            if (disk_details->status.b.is_ready)
                fprintf(stdout, " | READY");
            else
                fprintf(stdout, " | NOT READY");
        }
        else
            fprintf(stdout, " NOT FOUND");
        fprintf(stdout, "\n");
        fprintf(stdout, "\n");
    }
}

/* Now disable cluster statistics by calling perfstat_config */
perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
}

```

The `perfstat_node_list` interface is used to retrieve the list of nodes in the `perfstat_node_t` structure, which is defined in the `libperfstat.h` file. The following selected fields are from the `perfstat_node_t` structure:

Item	Descriptor
<b>nodeid</b>	Specifies the identifier of the node.
<b>nodename</b>	Specifies the name of the node.

The following code example shows the usage of the `perfstat_node_list` interface:

```

#include <stdio.h>
#include <libperfstat.h>

int main(int argc, char* argv[])
{
    perfstat_id_node_t nodeid;
    perfstat_node_t *node_list;
    int num_nodes;
    int i, rc;

    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }

    strncpy(nodeid.u.nodename, FIRST_CLUSTERNAME, MAXHOSTNAMELEN);
    nodeid.spec = CLUSTERNAME;
    num_nodes = perfstat_node_list(&nodeid, NULL, sizeof(perfstat_node_t), 0);
    if (num_nodes == -1)
    {
        perror("perfstat_node_list failed");
        exit(-1);
    }
    if (num_nodes == 0)
    {
        /* This cannot happen */
        fprintf(stdout, "No nodes in the cluster.\n");
        exit(-1);
    }
    node_list = (perfstat_node_t *) malloc(sizeof(perfstat_node_t) * num_nodes);
    num_nodes = perfstat_node_list(&nodeid, node_list, sizeof(perfstat_node_t), num_nodes);
    if (num_nodes == -1)
    {
        perror("perfstat_node_list failed");
        exit(-1);
    }
}

```

```

}
fprintf(stdout, "Number of nodes : %d\n\n", num_nodes);
for (i = 0; i < num_nodes; i++)
{
    fprintf(stdout, "Node name : %s\n", node_list[i].nodename);
    fprintf(stdout, "Node id : %llu\n", node_list[i].nodeid);
    fprintf(stdout, "\n");
}

/* Now disable cluster statistics by calling perfstat_config */
perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);

return (0);
}

```

The **perfstat\_cluster\_disk** interface is used to retrieve the list of disks in the `perfstat_disk_data_t` structure. The **perfstat\_cluster\_disk** interface is defined in the `libperfstat.h` file.

The following example code shows the usage of the **perfstat\_cluster\_disk** subroutine:

```

#include <stdio.h>
#include <libperfstat.h>

typedef enum {
    DISPLAY_NODE_DATA = 1,
    DISPLAY_DISK_DATA = 2,
} display_t;

int main(int argc, char* argv[])
{
    perfstat_node_data_t *node_details;
    perfstat_disk_data_t *disk_details;
    perfstat_id_node_t nodeid;
    char nodename[MAXHOSTNAMELEN];
    display_t display = DISPLAY_DISK_DATA;
    int num_nodes;
    int i, rc, num_of_disks = 0;

    /* Process the arguments */
    while ((i = getopt(argc, argv, "n:d")) != EOF)
    {
        switch(i)
        {
            case 'n':
                /* Request to display node data */
                display |= DISPLAY_NODE_DATA;
                strncpy(nodename, optarg, MAXHOSTNAMELEN);
                break;
            case 'd':
                /* Request to display disk data */
                display |= DISPLAY_DISK_DATA;
                break;
            case 'h':
                /* Print help message */
            default:
                /* Print the usage and terminate */
                fprintf(stderr, "usage: %s [-n <nodename>] [-d]\n", argv[0]);
                exit(-1);
        }
    }

    /* perfstat_config needs to be called to enable cluster statistics collection */
    rc = perfstat_config(PERFSTAT_ENABLE|PERFSTAT_CLUSTER_STATS, NULL);
    if (rc == -1)
    {
        perror("cluster statistics collection is not available");
        exit(-1);
    }

    /*If Node details are specified pass that data as input to get the disk details
    for that node . Else pass FIRST_NODENAME */
    if (display & DISPLAY_NODE_DATA)
    {
        strncpy(nodeid.u.nodename, nodename, MAXHOSTNAMELEN);
    }
    else
        strncpy(nodeid.u.nodename, FIRST_NODENAME, MAXHOSTNAMELEN);

    nodeid.spec = NODENAME;
    /*Get the number of disks for that node */

```

```

num_of_disks = perfstat_cluster_disk(&nodeid,NULL, sizeof(perfstat_disk_data_t), 0);
if (num_of_disks == -1)
{
    perror("perfstat_cluster_disk failed");
    exit(-1);
}

disk_details = (perfstat_disk_data_t *)calloc(num_of_disks,sizeof(perfstat_disk_data_t));
/* collect all the disk data for the node */
if(!disk_details){
    perror("calloc");
    exit(-1);
}
num_of_disks =
perfstat_cluster_disk(&nodeid,disk_details,sizeof(perfstat_disk_data_t),num_of_disks);
fprintf(stdout, "Disk Details\n");
fprintf(stdout, "-----\n");
for(i = 0; i < num_of_disks; i++)
{
    fprintf(stdout,"Disk Name:%s\t UDID:%s\n",disk_details[i].name,disk_details[i].uuid);
}

/* Now disable cluster statistics by calling perfstat_config */
perfstat_config(PERFSTAT_DISABLE|PERFSTAT_CLUSTER_STATS, NULL);
free(disk_details);
disk_details = NULL;
}

```

## Change history of the perfstat API

The following changes and additions have been made to the perfstat APIs.

### Interface changes

With the following filesets the **rblks** and **wblks** fields of **libperfstat** are represented by blocks of 512 bytes in the **perfstat\_disk\_total\_t**, **perfstat\_diskadapter\_t** and **perfstat\_diskpath\_t** structures, regardless of the actual block size used by the device for which metrics are being retrieved.

- **bos.perf.libperfstat 4.3.3.4**
- **bos.perf.libperfstat 5.1.0.50**
- **bos.perf.libperfstat 5.2.0.10**

### Interface additions

Review the specific interfaces that are available for a fileset.

The following interfaces were added in the **bos.perf.libperfstat 5.2.0** file set:

- **perfstat\_netbuffer**
- **perfstat\_protocol**
- **perfstat\_pagingospace**
- **perfstat\_diskadapter**
- **perfstat\_reset**

The **perfstat\_diskpath** interface was added in the **bos.perf.libperfstat 5.2.0.10** file set.

The **perfstat\_partition\_total** interface was added in the **bos.perf.libperfstat 5.3.0.0** file set.

The **perfstat\_partial\_reset** interface was added in the **bos.perf.libperfstat 5.3.0.10** file set.

The following interfaces were added in the **bos.perf.libperfstat 6.1.2** file set:

- **perfstat\_cpu\_total\_wpar**
- **perfstat\_memory\_total\_wpar**
- **perfstat\_cpu\_total\_rset**
- **perfstat\_cpu\_rset**

- **perfstat\_wpar\_total**
- **perfstat\_tape**
- **perfstat\_tape\_total**
- **perfstat\_memory\_page**
- **perfstat\_memory\_page\_wpar**
- **perfstat\_logicalvolume**
- **perfstat\_volumegroup**
- **perfstat\_config**

The following interfaces were added in the **bos.perf.libperfstat 6.1.6.0** file set:

- **perfstat\_cpu\_node**
- **perfstat\_disk\_node**
- **perfstat\_diskadapter\_node**
- **perfstat\_diskpath\_node**
- **perfstat\_logicalvolume\_node**
- **perfstat\_memory\_page\_node**
- **perfstat\_netbuffer\_node**
- **perfstat\_netinterface\_node**
- **perfstat\_protocol\_node**
- **perfstat\_volumegroup\_node**
- **perfstat\_cpu\_total\_node**
- **perfstat\_disk\_total\_node**
- **perfstat\_memory\_total\_node**
- **perfstat\_netinterface\_total\_node**
- **perfstat\_partition\_total\_node**
- **perfstat\_tape\_total\_node**
- **perfstat\_cluster\_total**
- **perfstat\_node\_list**

The following interfaces were added in the **bos.perf.libperfstat 6.1.7.0** file set:

- **perfstat\_hfistat**
- **perfstat\_hfistat\_window**

## Field additions

The following additions have been made to the specified file set levels.

### *The bos.perf.libperfstat 5.1.0.15 file set*

The following fields were added to **perfstat\_cpu\_total\_t**:

```
u_longlong_t bread
u_longlong_t bwrite
u_longlong_t lread
u_longlong_t lwrite
u_longlong_t phread
u_longlong_t phwrite
```

Support for C++ was added in this file set level.

## The *bos.perf.libperfstat 5.1.0.25* file set

The following fields were added to **perfstat\_cpu\_t**:

```
u_longlong_t bread
u_longlong_t bwrite
u_longlong_t lread
u_longlong_t lwrite
u_longlong_t phread
u_longlong_t phwrite
```

## The *bos.perf.libperfstat 5.2.0* file set

The following fields were added to **perfstat\_cpu\_t**:

```
u_longlong_t iget
u_longlong_t namei
u_longlong_t dirblk
u_longlong_t msg
u_longlong_t sema
```

The **name** field which returns the logical processor name is now of the form *cpu0*, *cpu1*, instead of *proc0*, *proc1* as it was in previous releases.

The following fields were added to **perfstat\_cpu\_total\_t**:

```
u_longlong_t runocc
u_longlong_t swpocc
u_longlong_t iget
u_longlong_t namei
u_longlong_t dirblk
u_longlong_t msg
u_longlong_t sema
u_longlong_t rcvint
u_longlong_t xmtint
u_longlong_t mdmint
u_longlong_t tty_rawinch
u_longlong_t tty_caninch
u_longlong_t tty_rawoutch
u_longlong_t ksched
u_longlong_t koverf
u_longlong_t kexit
u_longlong_t rbread
u_longlong_t rcread
u_longlong_t rbwrt
u_longlong_t rcwrt
u_longlong_t traps
int ncpus_high
```

The following field was added to **perfstat\_disk\_t**:

```
char adapter[IDENTIFIER_LENGTH]
```

The following field was added to **perfstat\_netinterface\_t**:

```
u_longlong_t bitrate
```

The following fields were added to **perfstat\_memory\_total\_t**:

```
u_longlong_t real_system
u_longlong_t real_user
u_longlong_t real_process
```

The following defines were added to **libperfstat.h**:

```
#define FIRST_CPU          ""
#define FIRST_DISK        ""
#define FIRST_DISKADAPTER ""
#define FIRST_NETINTERFACE ""
#define FIRST_PAGINGSPACE ""
#define FIRST_PROTOCOL    ""
#define FIRST_ALLOC       ""
```

### ***The bos.perf.libperfstat 5.2.0.10 file set***

The following field was added to the **perfstat\_disk\_t** interface:

```
uint paths_count
```

The following define was added to **libperfstat.h**:

```
#define FIRST_DISKPATH ""
```

### ***The bos.perf.libperfstat 5.3.0.0 file set***

The following fields were added to the **perfstat\_cpu\_t** interface:

```
u_longlong_t puser
u_longlong_t psyss
u_longlong_t pidle
u_longlong_t pwait
u_longlong_t redispsd0
u_longlong_t redispsd1
u_longlong_t redispsd2
u_longlong_t redispsd3
u_longlong_t redispsd4
u_longlong_t redispsd5
u_longlong_t migration_push
u_longlong_t migration_S3grq
u_longlong_t migration_S3pul
u_longlong_t invol_cswitch
u_longlong_t vol_cswitch
u_longlong_t runque
u_longlong_t bound
u_longlong_t decrintrs
u_longlong_t mpcrintrs
u_longlong_t mpcsintrs
u_longlong_t devintrs
u_longlong_t softintrs
u_longlong_t phantintrs
```

The following fields were added to the **perfstat\_cpu\_total\_t** interface:

```
u_longlong_t puser
u_longlong_t psys
u_longlong_t pidle
u_longlong_t pwait
u_longlong_t decrintrs
u_longlong_t mpcrintrs
u_longlong_t mpcsintrs
u_longlong_t phantintrs
```

### ***The bos.perf.libperfstat 5.3.0.10 file set***

The following fields were added to both the **perfstat\_disk\_t** and **perfstat\_diskpath\_t** interfaces:

```
u_longlong_t q_full
u_longlong_t rserv
u_longlong_t rtimeout
u_longlong_t rfailed
u_longlong_t min_rserv
u_longlong_t max_rserv
u_longlong_t wserv
u_longlong_t wtimeout
u_longlong_t wfailed
u_longlong_t min_wserv
u_longlong_t max_wserv
u_longlong_t wq_depth
u_longlong_t wq_sampled
u_longlong_t wq_time
u_longlong_t wq_min_time
u_longlong_t wq_max_time
u_longlong_t q_sampled
```

In addition, the `xrate` field in the following data structures has been renamed to `_rxfers` and contains the number of read transactions when used with selected device drivers or zero:

```
perfstat_disk_t
perfstat_disk_total_t
perfstat_diskadapter_t
perfstat_diskpath_t
```

The following definitions were added to the **libperfstat.h** header file:

```
#define FLUSH_CPUTOTAL
#define FLUSH_DISK
#define RESET_DISK_MINMAX
#define FLUSH_DISKADAPTER
#define FLUSH_DISKPATH
#define FLUSH_PAGINGSPACE
#define FLUSH_NETINTERFACE
```

### ***The bos.perf.libperfstat 5.3.0.50 file set***

The following fields were added to **perfstat\_partition\_total\_t**:

```
u_longlong_t reserved_pages
u_longlong_t reserved_pagesize
```

### ***The bos.perf.libperfstat 5.3.0.60 file set***

The following fields were added to **perfstat\_cpu\_t**, **perfstat\_cpu\_total\_t** and **perfstat\_partition\_total\_t**:

```
u_longlong_t idle_donated_purr
u_longlong_t idle_donated_spurr
u_longlong_t busy_donated_purr
u_longlong_t busy_donated_spurr
u_longlong_t idle_stolen_purr
u_longlong_t idle_stolen_spurr
u_longlong_t busy_stolen_purr
u_longlong_t busy_stolen_spurr
```

The following flags were added to **perfstat\_partition\_type\_t**:

```
unsigned donate_capable
unsigned donate_enabled
```

### ***The bos.perf.libperfstat 6.1.6.0 file set***

The following field is added to all existing interfaces:

```
u_longlong_t version
```

## **Structure additions**

Review the specific structure additions that are available for different file sets.

The following structures are added in the **bos.perf.libperfstat 6.1.2.0** file set:

```
perfstat_cpu_total_wpar_t
perfstat_cpu_total_rset_t
perfstat_cpu_rset_t
perfstat_wpar_total_t
perfstat_tape_t
perfstat_tape_total_t
perfstat_memory_page_t
perfstat_memory_page_wpar_t
perfstat_logicalvolume_t
perfstat_volume_group_t
```

The following structures are added in the **bos.perf.libperfstat 6.1.6.0** file set:

```
perfstat_id_node_t
perfstat_node_t
perfstat_cluster_total_t
perfstat_cluster_type_t
perfstat_node_data_t
perfstat_disk_data_t
perfstat_disk_status_t
perfstat_ip_addr_t
```

The following structures are added in the **bos.perf.libperfstat 6.1.7.0** file set:

```
perfstat_hfistat_t
perfstat_hfistat_window_t
```

## Kernel tuning

You can make permanent kernel-tuning changes without having to edit any **rc** files. This is achieved by centralizing the reboot values for all tunable parameters in the **/etc/tunables/nextboot** stanza file. When a system is rebooted, the values in the **/etc/tunables/nextboot** file are automatically applied.

The following commands are used to manipulate the **nextboot** file and other files containing a set of tunable parameter values:

- The **tunchange** command is used to change values in a stanza file.
- The **tunsave** command is used to save values to a stanza file.
- The **tunrestore** is used to apply a file; that is, to change all tunables parameter values to those listed in a file.
- The **tuncheck** command must be used to validate a file created manually.
- The **tundefault** is available to reset tunable parameters to their default values.

The preceding commands work on both current and reboot values.

All six tuning commands (**no**, **nfso**, **vmo**, **ioo**, **raso**, and **schedo**) use a common syntax and are available to directly manipulate the tunable parameter values. Available options include making permanent changes and displaying detailed help on each of the parameters that the command manages. A large majority of tunable parameter values are not modifiable when the login session is initiated outside of the global WPAR partition. Attempts to modify such a read only tunable parameter value is refused by the command and a diagnostic message written to standard error output.

SMIT panel is also available to manipulate the current and reboot values for all tuning parameters, as well as the files in the **/etc/tunables** directory.

### Related information

[bosboot command](#)

[no command](#)

[tunables command](#)

## Migration and compatibility

When machines are migrated from a previous release of AIX, the tuning commands are automatically set to run in compatibility mode.

Most of the information in this section does not apply to compatibility mode. For more information, see [compatibility mode](#) in *Files Reference*.

When a machine is initially installed with AIX, it is automatically set to run in the tuning mode, which is described in this chapter. The tuning mode is controlled by the **sys0** attribute called **pre520tune**, which can be set to enable to run in compatibility mode and disable to run in the tuning mode.

To retrieve the current setting of the **pre520tune** attribute, run the following command:

```
lsattr -E -l sys0
```

To change the current setting of the **pre520tune** attribute, run the following command:

```
chdev -l sys0 -a pre520tune=enable
```

OR

use SMIT panel.

## Tunables file directory

Information about tunable parameter values is located in the **/etc/tunables** directory. Except for a log file created during each reboot, this directory only contains ASCII stanza files with sets of tunable parameters.

These files contain **parameter=value** pairs specifying tunable parameter changes, classified in six stanzas corresponding to the six tuning commands: **schedo**, **vmo**, **ioo**, **no**, **raso**, and **nfso**. Additional information about the level of AIX, when the file was created, and a user-provided description of file usage is stored in a special stanza in the file. For detailed information on the file's format, see the **tunables** file.

The main file in the tunables directory is called **nextboot**. It contains all the tunable parameter values to be applied at the next reboot. The **lastboot** file in the tunables directory contains all the tunable values that were set at the last machine reboot, a *timestamp* for the last reboot, and *checksum* information about the matching **lastboot.log** file, which is used to log any changes made, or any error messages encountered, during the last rebooting. >| The **usermodified** file in the **/etc/tunables** directory contains all the dynamic tunable values that were modified by using the **-o** flag. |< The **usermodified**, **lastboot**, and **lastboot.log** files are set to be read-only and are owned by the root user, as are the directory and all of the other files.

Users can create as many **/etc/tunables** files as needed, but only the **nextboot** file is ever automatically applied. Manually created files must be validated using the **tuncheck** command. Parameters and stanzas can be missing from a file. Only tunable parameters present in the file will be changed when the file is applied with the **tunrestore** command. Missing tunables will simply be left at their current or default values. To force resetting of a tunable to its default value with **tunrestore** (presumably to force other tunables to known values, otherwise **tundefault**, which sets all parameters to their default value, could have been used), **DEFAULT** can be specified. Specifying **DEFAULT** for a tunable in the **nextboot** file is the same as not having it listed in the file at all because the reboot tuning procedure enforces default values for missing parameters. This will guarantee to have all tunables parameters set to the values specified in the **nextboot** file after each reboot.

Tunable files can have a special stanza named **info** containing the parameters **AIX\_level**, **Kernel\_type** and **Last\_validation**. Those parameters are automatically set to the level of AIX and to the type of kernel (MP64) running when the **tuncheck** or **tunsave** is run on the file. Both commands automatically update those fields. However, the **tuncheck** command will only update if no error was detected.

The **lastboot** file always contains values for every tunable parameters. Tunables set to their default value will be marked with the comment **DEFAULT VALUE**. Restricted tunables modified from their default value are marked, after the value, with an additional comment **# RESTRICTED not at default value**. The **Logfile\_checksum** parameter only exists in that file and is set by the tuning reboot process (which also sets the rest of the info stanza) after closing the log file.

Tunable files can be created and modified using one of the following options:

- Using SMIT to modify the next reboot value for tunable parameters, or to ask to save all current values for next boot, or to ask to use an existing tunable file at the next reboot. All those actions will update the **/etc/tunables/nextboot** file. A new file in the **/etc/tunables** directory can also be created to save all current or all **nextboot** values.
- Using the tuning commands (**ioo**, **raso**, **vmo**, **schedo**, **no** or **nfso**) with the **-p** or **-r** options, which will update the **/etc/tunables/nexboot** file.
- A new file can also be created directly with an editor or copied from another machine. Running **tuncheck [-r | -p] -f** must then be done on that file.

- Using the **tunsave** command to create or overwrite files in the **/etc/tunables** directory
- Using the **tunrestore -r** command to update the **nextboot** file.

## Tunable parameters type

The manual page for each of the six tuning commands contains the complete list of all the parameter manipulated by each of the commands and for each parameter, its type, range, default value, and any dependencies on other parameters.

All the tunable parameters manipulated by the tuning commands (**no**, **nfso**, **vmo**, **ioo**, **raso**, and **schedo**) have been classified into the following categories:

- **Dynamic**: if the parameter can be changed at any time
- **Static**: if the parameter can never be changed
- **Reboot**: if the parameter can only be changed during reboot
- **Bosboot**: if the parameter can only be changed by running **bosboot** and rebooting the machine
- **Mount**: if changes to the parameter are only effective for future file systems or directory mounts
- **Incremental**: if the parameter can only be incremented, except at boot time
- **Connect**: if changes to the parameter are only effective for future socket connections
- **Deprecated**: if changing this parameter is no longer supported by the current release of AIX

For parameters of type Bosboot, whenever a change is performed, the tuning commands automatically prompt the user to ask if they want to execute the **bosboot** command. When specifying a restricted tunable for modification in association with the option **-p** or **-r**, you are also prompted to confirm the change. For parameters of type Connect, the tuning commands automatically restart the **inetd** daemon.

The tunables classified as restricted use tunables exist primarily for specialized intervention by the support or development teams and are not recommended for end user modification. For this reason, they are not displayed by default and require the force option on the command line. When modifying a restricted tunable, a warning message is displayed and confirmation required if the change is specified for reboot or permanent.

## Common syntax for tuning commands

Review the syntax for all the tuning commands.

The **no**, **nfso**, **vmo**, **ioo**, **raso**, and **schedo** tuning commands all support the following syntax:

```
command [-p|-r] {-o tunable[=newvalue]}
command [-p|-r] {-d tunable}
command [-p|-r] -D
command [-p|-r] [-F]-a
command -h [tunable]
command [-F] -L [tunable]
command [-F] -x [tunable]
```

The flags of the tuning command are:

Item	Descriptor
<b>-a</b>	Displays current, reboot (when used in conjunction with <b>-r</b> ) or permanent (when used in conjunction with <b>-p</b> ) value for all tunable parameters, one per line in pairs <code>tunable = value</code> . For the permanent options, a value is displayed for a parameter only if its reboot and current values are equal. Otherwise, NONE is displayed as the value. If a tunable is not supported by the running kernel or the current platform, "n/a" is displayed as the value.
<b>-d tunable</b>	Resets tunable to default value. If a tunable needs to be changed (that is, it is currently not set to its default value) and is of type <b>Bosboot</b> or <b>Reboot</b> , or if it is of type Incremental and has been changed from its default value, and <b>-r</b> is not used in combination, it is not changed, but a message displays instead.

The flags of the tuning command are: *(continued)*

---

Item	Descriptor
<b>-D</b>	Resets all tunables to their default value. If tunables needing to be changed are of type <b>Bosboot</b> or <b>Reboot</b> , or are of type Incremental and have been changed from their default value, and <b>-r</b> is not used in combination, they are not changed, but a message displays instead.
<b>-F</b>	Forces display of restricted tunable parameters when the options <b>-a</b> , <b>-L</b> , or <b>-x</b> are specified alone on the command line to list all tunables. When <b>-F</b> is not specified, restricted tunables are not included in a display unless specifically named in association with a display option.
<b>-h</b> [ <i>tunable</i> ]	Displays help about tunable parameter. Otherwise, displays the command usage statement.
<b>-o</b> <i>tunable</i> [= <i>newvalue</i> ]	<p>Displays the value or sets tunable to <i>newvalue</i>. If a tunable needs to be changed (the specified value is different than current value), and is of type <b>Bosboot</b> or <b>Reboot</b>, or if it is of type Incremental and its current value is bigger than the specified value, and <b>-r</b> is not used in combination, it is not changed, but a message displays instead.</p> <p>When <b>-r</b> is used in combination without a new value, the <b>nextboot</b> value for tunable is displayed. When <b>-p</b> is used in combination without a new value, a value is displayed only if the current and next boot values for tunable are the same. Otherwise, NONE is displayed as the value. If a tunable is not supported by the running kernel or the current platform, "n/a" is displayed as the value.</p>
<b>-p</b>	<p>When used in combination with <b>-o</b>, <b>-d</b> or <b>-D</b>, makes changes apply to both current and reboot values; that is, turns on the updating of the <b>/etc/tunables/nextboot</b> file in addition to the updating of the current value. This flag cannot be used on <b>Reboot</b> and <b>Bosboot</b> type parameters because their current value cannot be changed.</p> <p>When used with <b>-a</b> or <b>-o</b> flag without specifying a new value, values are displayed only if the current and next boot values for a parameter are the same. Otherwise, NONE is displayed as the value.</p>
<b>-r</b>	<p>When used in combination with <b>-o</b>, <b>-d</b> or <b>-D</b> flags, makes changes apply to reboot values only; that is, turns on the updating of the <b>/etc/tunables/nextboot</b> file. If any parameter of type <b>Bosboot</b> is changed, the user will be prompted to run <b>bosboot</b>.</p> <p>When used with <b>-a</b> or <b>-o</b> without specifying a new value, next boot values for tunables are displayed instead of current values.</p>

The flags of the tuning command are: *(continued)*

Item	Descriptor
<b>-x</b> [ <i>tunable</i> ]	Lists the characteristics of one or all tunables, one per line, using the following format:

```
tunable,current,default,reboot, min,max,unit,type,{dtunable }
```

where:

```
current = current value
default = default value
reboot = reboot value
min = minimal value
max = maximum value
unit = tunable unit of measure
type = parameter type: D(for Dynamic), S(for Static),
      R(for Reboot), B(for Bosboot), M(for Mount),
      I(for Incremental), C (for Connect), and
      d (for Deprecated)
dtunable = space separated list of dependent tunable
           parameters
```

<b>-L</b> [ <i>tunable</i> ]	Lists the characteristics of one or all tunables, one per line, using the following format:
------------------------------	---

NAME	CUR	DEF	BOOT	MIN	MAX	UNIT	TYPE
DEPENDENCIES							
memory_frames	128K	128K				4KB pages	S
maxfree	128	128	128	16	200K	4KB pages	D
minfree							
memory_frames							

where:

```
CUR = current value
DEF = default value
BOOT = reboot value
MIN = minimal value
MAX = maximum value
UNIT = tunable unit of measure
TYPE = parameter type: D (for Dynamic), S (for Static),
      R (for Reboot), B (for Bosboot),
      M (for Mount), I (for Incremental),
      C (for Connect), and d (for Deprecated)
DEPENDENCIES = list of dependent tunable parameters,
              one per line
```

Any change (with **-o**, **-d** or **-D**) to a restricted tunable parameter will result in a message being displayed to warn the user that a tunable of the restricted use type has been modified and, if the **-r** or **-p** options are also specified on the command line, the user will be prompted for confirmation of the change. In addition, at system reboot, the presence of restricted tunables modified to a value different from their default using a command line specifying the **-r** or **-p** options will cause the addition of an error log entry identifying the list of these modified tunables.

Any change (with **-o**, **-d** or **-D** flags) to a parameter of type **Mount** will result in a message displays to warn the user that the change is only effective for future mountings.

Any change (with **-o**, **-d** or **-D** flags) to a parameter of type **Connect** will result in the **inetd** daemon being restarted, and a message will display to warn the user that the change is only effective for socket connections.

Any attempt to change (with **-o**, **-d** or **-D** flags) a parameter of type **Bosboot** or **Reboot** without **-r**, will result in an error message.

Any attempt to change (with **-o**, **-d** or **-D** flags but without **-r**) the current value of a parameter of type **Incremental** with a new value smaller than the current value, will result in an error message.

## Tunable file-manipulation commands

The following commands normally manipulate files in the **/etc/tunables** directory, but the files can be located anywhere. Therefore, as long as the file name does not contain a forward slash (/), all the file names specified are expanded to **/etc/tunables/filename**.

To guarantee the consistency of their content, all the files are locked before any updates are made. The commands **tunsave**, **tuncheck** (only if successful), and **tundefault -r** all update the info stanza.

### tunchange Command

The **tunchange** command is used to update one or more tunable stanzas in a file.

The following is the syntax for the **tunchange** command:

```
tunchange -f filename ( -t stanza ( {-o parameter[=value]} | -D ) | -m filename2 )
```

where stanza is **schedo**, **vmo**, **ioo**, **raso**, **no**, or **nfso**.

The following is an example of how to update the **pacefork** parameter in the **/etc/tunables/mytunable** directory:

```
tunchange -f mytunable -t schedo -o pacefork=10
```

The following is an example of how to unconditionally update the **pacefork** parameter in the **/etc/tunables/nextboot** directory. This should be done with caution because no warning will be printed if a parameter of type **bosboot** was changed.

```
tunchange -f nextboot -t schedo -o pacefork=10
```

The following is an example of how to clear the **schedo** stanza in the **nextboot** file.

```
tunchange -f nextboot -t schedo -D
```

The following is an example of how to merge the **/home/admin/schedo\_conf** file with the current **nextboot** file. If the file to merge contains multiple entries for a parameter, only the first entry will be applied. If both files contain an entry for the same tunable, the entry from the file to merge will replace the current **nextboot** file's value.

```
tunchange -f nextboot -m /home/admin/schedo_conf
```

The **tunchange** command is called by the tuning commands to implement the **-p** and **-r** flags using **-f nextboot**.

### tuncheck Command

The **tuncheck** command is used to validate a file.

The syntax of the **tuncheck** command is as follows:

```
tuncheck [-r [-K]|-p] -f filename
```

The following example validates the **/etc/tunables/mytunable** file for usage on current values.

```
tuncheck -f mytunable
```

The following example validates the `/etc/tunables/nextboot` file or `my_nextboot` file for usage during reboot. The `-r` flag is the only valid option when the file to check is the `nextboot` file.

```
tuncheck -r -f nextboot
tuncheck -r -f /home/bill/my_nextboot
```

>|The following example validates the `/etc/tunables/nextliveupdate` file or `/home/bill/my_nextliveupdate` file. The validated file is used during the reboot and Live Update operation. You must use the `-r` flag and the `-K` flag to check the `nextliveupdate` file.

```
tuncheck -r -K -f nextliveupdate
tuncheck -r -K -f /home/bill/my_nextliveupdate
```

|<

All tunable parameters in the specified `nextliveupdate` or `my_nextliveupdate` file are checked for range, and dependencies, and if a problem is detected, a message similar to: `Parameter X is out of range` or `Dependency problem between parameter A and B` is issued. The `-r` and `-p` options control the values that are used in dependency checking for parameters that are not listed in the file and the handling of proposed changes to parameters of type **Incremental**, **Bosboot**, and **Reboot**. >|When you use the `-K` flag with the `-r` flag, the `tuncheck` command validates the file that contains the tunable parameter values. The validated file is used during the next boot and Live Update operations. |<

Except when used with the `-r` option, checking is performed on parameter of type **Incremental** to make sure that the value in the file is not less than the current value. If one or more parameters of type **Bosboot** are listed in the file with a different value than its current value, the user will either be prompted to run `bosboot` (when `-r` is used) or an error message will display.

Parameters having dependencies are checked for compatible values. When one or more parameters in a set of interdependent parameters is not listed in the file being checked, their values are assumed to either be set at their current value (when the `tuncheck` command is called without `-p` or `-r`), or their default value. This is because when called without `-r`, the file is validated to be applicable on the current values, while with `-r`, it is validated to be used during reboot when parameters not listed in the file will be left at their default value. Calling this command with `-p` is the same as calling it twice; once with no argument, and once with the `-r` flag. This checks whether a file can be used both immediately, and at reboot time.

**Note:** Users creating a file with an editor, or copying a file from another machine, must run the `tuncheck` command to validate their file.

## tunrestore Command

The `tunrestore` command is used to restore all the parameters from a file.

The following is the syntax for the `tunrestore` command:

```
tunrestore -R | [-r [-K]] -f filename
```

The following example changes the current values for all tunable parameters present in the file if ranges, dependencies, and incremental parameter rules are all satisfied.

```
tunrestore -f mytunable
tunrestore -f /etc/tunables/mytunable
```

In case of problems, only the changes possible will be made.

The following example changes the **reboot** values for all tunable parameters present in the file if ranges and dependencies rules are all satisfied. In other words, they will be copied to the `/etc/tunables/nextboot` file.

```
tunrestore -r -f mytunable
```

>|The following example changes the values for all tunable parameters that are present in the specified file and associated with the next boot and Live Update operations if ranges and dependency rules are satisfied. The values of the tunable parameters are copied to the **/etc/tunables/nextboot** and **/etc/tunables/nextliveupdate** files. |<

```
tunrestore -r -K -f mytunable
```

If changes to parameters of type **bosboot** are detected, the user will be prompted to run the **bosboot** command.

The following command can only be called from the **/etc/inittab** file and changes tunable parameters to values from the **/etc/tunables/nextboot** file.

```
tunrestore -R
```

Any problem found or change made is logged in the **/etc/tunables/lastboot.log** file. A new **/etc/tunables/lastboot** file is always created with the list of current values for all parameters. Any change to restricted tunable parameters from their default values will cause the addition of an error log entry identifying the list of these modified tunable parameters.

If *filename* does not exist, an error message displays. If the **nextboot** file does not exist, an error message displays when you use the **-r** flag. >| If the **nextliveupdate** file does not exist, an error message is displayed when you use the **-K** flag. |< If you use the **-R** flag, all the tuning parameters of a type other than **bosboot** will be set to their default value, and a **nextboot** file containing only an info stanza will be created. A warning will also be logged in the **lastboot.log** file.

Except when **-r** is used, parameters requiring a call to **bosboot** and a **reboot** are not changed, but an error message is displayed to indicate they could not be changed. When **-r** is used, if any parameter of type **bosboot** needs to be changed, the user will be prompted to run **bosboot**. Parameters missing from the file are simply left unchanged, except when **-R** is used, in which case missing parameters are set to their default values. If the file contains multiple entries for a parameter, only the first entry will be applied, and a warning will be displayed or logged (if called with **-R**).

## tunsave Command

The **tunsave** command is used to save current tunable parameter values into a file.

The following is the syntax for the **tunsave** command:

```
tunsave [-a|-A] -f|-F filename
```

For example, the following saves all of the current tunable parameter values that are different from their default into the **/etc/tunables/mytunable** file.

```
tunsave -f mytunable
```

If the file already exists, an error message is printed instead. The **-F** flag must be used to overwrite an existing file.

For example, the following saves all of the current tunable parameter values different from their default into the **/etc/tunables/nextboot** file.

```
tunsave -f nextboot
```

If necessary, the **tunsave** command will prompt the user to run **bosboot**.

For example, the following saves all of the current tunable parameters values (including parameters for which default is their value) into the **mytunable** file.

```
tunsave -A -f mytunable
```

This permits you to save the current setting. This setting can be reproduced at a later time, even if the default values have changed (default values can change when the file is used on another machine or when running another version of AIX).

For example, the following saves all current tunable parameter values into the **/etc/tunables/mytunable** file or the **mytunable** file in the current directory.

```
tunsave -a -f mytunable
tunsave -a -f ./mytunable
```

For the parameters that are set to default values, a line using the keyword **DEFAULT** will be put in the file. This essentially saves only the current changed values, while forcing all the other parameters to their default values. This permits you to return to a known setup later using the **tunrestore** command.

## tundefault Command

The **tundefault** command is used to force all tuning parameters to be reset to their default value. The **-p** flag makes changes permanent, while the **-r** flag defers changes until the next reboot operation. The **-K** flag defers changes until the next Live Update operation.

The following is the syntax for the **tundefault** command:

```
tundefault [-p|-r [-K]]
```

The following example resets all tunable parameters to their default value, except the parameters of type **Bosboot** and **Reboot**, and parameters of type **Incremental** set at values bigger than their default value.

```
tundefault
```

Error messages will be displayed for any parameter change that is not permitted.

The following example resets all the tunable parameters to their default value. It also updates the **/etc/tunables/nextboot** file, and if necessary, offers to run **bosboot**, and displays a message warning that rebooting is needed for all the changes to be effective.

```
tundefault -p
```

This command permanently resets *all* tunable parameters to their default values, returning the system to a consistent state and making sure the state is preserved after the next reboot.

The following example clears all the stanzas in the **/etc/tunables/nextboot** file, and proposes **bosboot** if necessary.

```
tundefault -r
```

>|When you use the **-K** flag with the **-r** flag as shown in the following example, the **tundefault** command resets all tunable parameters in the specified **nextboot** and **nextliveupdate** files to its default value. The **-r** flag clears the stanzas in the **/etc/tunables/nextboot** file, and prompts for a **bosboot** operation if necessary. The **-K** flag sets the tunable parameters in the **/etc/tunables/nextliveupdate** file to the default values if a non-default value was set.

```
tundefault -r -K
```

|<

## Initial setup

Installing the **bos.perf.tune** fileset automatically creates an initial **/etc/tunables/nextboot** file.

When you install the **bos.perf.tune** fileset the following line is added at the beginning of the **/etc/inittab** file:

```
tunable:23456789:wait:/usr/bin/tunrestore -R > /dev/console 2>&1
```

This entry sets the **reboot** value of all tunable parameters to their default. For more information about migration from a previous version of AIX and the compatibility mode automatically setup in case of migration, see the *Files Reference* guide.

## Reboot tuning procedure

Parameters of type **Bosboot** are set by the **bosboot** command, which retrieves their values from the **nextboot** file when creating a new boot image.

Parameters of type **Reboot** are set during the reboot process by the appropriate configuration methods, which also retrieve the necessary values from the **nextboot** file. In both cases, if there is no **nextboot** file, the parameters will be set to their default values. All other parameters are set using the following process:

1. When **tunrestore -R** is called, any tunable changed from its default value is logged in the **lastboot.log** file. The parameters of type **Reboot** and **Bosboot** present in the **nextboot** file, and which should already have been changed by the time **tunrestore -R** is called, will be checked against the value in the file, and any difference will also be logged.
2. The **lastboot** file will record all the tunable parameter settings, including default values, which will be flagged using **# DEFAULT VALUE**, and the **AIX\_level**, **Kernel\_type**, **Last\_validation**, and **Logfile\_checksum** fields will be set appropriately.
3. If there is no **/etc/tunables/nextboot** file, all tunable parameters, except those of type **Bosboot**, will be set to their default value, a **nextboot** file with only an info stanza will be created, and the following warning: "cannot access the /etc/tunables/nextboot file" will be printed in the log file. The **lastboot** file will be created as described in step 2.
4. If the desired value for a parameter is found to be out of range, the parameter will be left to its default value, and a message similar to the following: "Parameter A could not be set to X, which is out of range, and was left to its current value (Y) instead" will be printed in the log file. Similarly, if a set of interdependent parameters have values incompatible with each other, they will all be left at their default values and a message similar to the following: "Dependent parameter A, B and C could not be set to X, Y and Z because those values are incompatible with each other. Instead, they were left to their current values (T, U and V)" will be printed in the log file.

All of these error conditions could exist if a user modified the **/etc/tunables/nextboot** file with an editor or copied it from another machine, possibly running a different version of AIX with different valid ranges, and did not run **tuncheck -r -f** on the file. Alternatively, **tuncheck -r -f** prompted the user to run **bosboot**, but this was not done.

## Recovery Procedure

If the machine becomes unstable with a given **nextboot** file, users should put the system into maintenance mode, make sure the **sys0 pre520tune** attribute is set to disable, delete the **nextboot**

file, run the **bosboot** command and reboot. This action will guarantee that all tunables are set to their default value.

## Kernel tuning using the SMIT interface

To start the SMIT panels that manage AIX kernel tuning parameters, use the SMIT fast path **smitty tuning**.

The following is a view of the tuning panel:

### Tuning Kernel & Network Parameters

```
Save/Restore All Kernel & Network Parameters
Tuning Scheduler and Memory Load Control Parameters
Tuning Virtual Memory Manager Parameters
Tuning Network Parameters
Tuning NFS Parameters
Tuning I/O Parameters
Tuning RAS Parameters
Tuning Development Parameters
```

Select **Save/Restore All Kernel & Network Parameters** to manipulate all tuning parameter values at the same time. To individually change tuning parameters managed by one of the tuning commands, select any of the other lines.

## Global manipulation of tuning parameters

Review the following steps to globally manipulate tuning parameters.

The main panel to manipulate all tunable parameters by sets looks similar to the following:

### Save/Restore All Kernel Tuning Parameters

```
View Last Boot Parameters
View Last Boot Log File

Save All Current Parameters for Next Boot
Save All Current Parameters
Restore All Current Parameters from Last Boot Values
Restore All Current Parameters from Saved Values
Reset All Current Parameters To Default Value

Save All Next Boot Parameters
Restore All Next Boot Parameters from Last Boot Values
Restore All Next Boot Parameters from Saved Values
Reset All Next Boot Parameters To Default Value

Save All Next Boot and Next Live Update Parameters
Restore All Next Boot and Next Live Update Parameters from Saved Values
```

Each of the options in this panel are explained in the following sections.

#### View Last Boot Parameters

All last boot parameters are listed stanza by stanza, retrieved from the **/etc/tunables/lastboot** file.

#### View Last Boot Log File

Displays the content of the file **/etc/tunables/lastboot.log**.

#### Save All Current Parameters for Next Boot

##### Save All Current Kernel Tuning Parameters for Next Boot

```
ARE YOU SURE ?
```

After selecting **yes** and pressing **ENTER**, all the current tuning parameter values are saved in the **/etc/tunables/nextboot** file. **Bosboot** will be offered if necessary.

## Save All Current Parameters

```
Save All Current Kernel Tuning Parameters
File name                               []
Description                              []
```

Type or select values for the two entry fields:

- **>|File name:** F4 displays the list of existing files. This list contains all the files in the **/etc/tunables** directory except the special files **nextboot**, **lastboot**, **lastboot.log**, **nextliveupdate**, and any special file that has the file name ending with **.lvup**. You must not specify any of these reserved names for the files. |<
- **Description:** This field is written in the **info** stanza of the selected file.

After pressing **ENTER**, all of the current tuning parameter values will be saved in the selected stanza file of the **/etc/tunables** directory.

## Restore All Current Parameters from Last Boot Values

```
Restore All Current Parameters from Last Boot Values
ARE YOU SURE ?
```

After selecting **yes** and pressing **ENTER**, all the tuning parameters will be set to values from the **/etc/tunables/lastboot** file. Error messages will be displayed if any parameter of type **Bosboot** or **Reboot** would need to be changed, which can only be done when changing reboot values.

## Restore All Current Parameters from Saved Values

```
Restore Saved Kernel Tuning Parameters
Move cursor to desired item and press Enter.
mytunablefile      Description field of mytunable file
tun1               Description field of lastweek file
```

A select menu shows existing files in the **/etc/tunables** directory, except the special files **nextboot**, **lastboot**, **lastboot.log**, **nextliveupdate**, and any special file that has the file name ending with **.lvup**. After you press **ENTER**, the parameters present in the selected file in the **/etc/tunables** directory will be set to the value listed if possible. Error messages will be displayed if any parameter of type **Bosboot** or **Reboot** would need to be changed, which can't be done on the current values. Error messages will also be displayed for any parameter of type **Incremental** when the value in the file is smaller than the current value, and for out of range and incompatible values present in the file. All possible changes will be made.

## Reset All Current Parameters To Default Value

```
Reset All Current Kernel Tuning Parameters To Default Value
ARE YOU SURE ?
```

After pressing **ENTER**, each tunable parameter will be reset to its default value. Parameters of type **Bosboot** and **Reboot**, are never changed, but error messages are displayed if they should have been changed to get back to their default values.

## Save All Next Boot Parameters

```
Save All Next Boot Kernel Tuning Parameters
File name                               []
```

Type or select values for the entry field. Pressing F4 displays a list of existing files. This list contains all the files in the **/etc/tunables** directory except the special files **nextboot**, **lastboot**, **lastboot.log**, **nextliveupdate**, and any special file that has the file name ending with **.lvup**. You cannot specify any of these reserved names for the file. After you press **ENTER**, the **nextboot** file is copied to the specified **/etc/tunables** file if it can be successfully **tunchecked**.

### Restore All Next Boot Parameters from Last Boot Values

```
Restore All Next Boot Kernel Tuning Parameters from Last Boot Values
ARE YOU SURE ?
```

After selecting **yes** and pressing **ENTER**, all values from the **lastboot** file will be copied to the **nextboot** file. If necessary, the user will be prompted to run **bosboot**, and warned that for all the changes to be effective, the machine must be rebooted.

### Restore All Next Boot Parameters from Saved Values

```
Restore All Next Boot Kernel Tuning Parameters from Saved Values
Move cursor to desired item and press Enter.
mytunablefile      Description field of mytunablefile file
tun1                Description field of tun1 file
```

A select menu shows existing files in the **/etc/tunables** directory, except the special files **nextboot**, **lastboot**, **lastboot.log**, **nextliveupdate**, and any special file that has the file name ending with **.lvup**. After you select a file and press **ENTER**, all values from the selected file will be copied to the **nextboot** file, if the file was successfully **tunchecked** first. If necessary, the user will be prompted to run **bosboot**, and warned that for all the changes to be effective, rebooting the machine is necessary.

### Reset All Next Boot Parameters To Default Value

```
Reset All Next Boot Kernel Tuning Parameters To Default Value
ARE YOU SURE ?
```

After hitting **ENTER**, the **/etc/tunables/nextboot** file will be cleared. If necessary **bosboot** will be proposed and a message indicating that a reboot is needed will be displayed.

### > Save All Next Boot and Next Live Update Parameters

```
Save All Next Boot and Next Live Update Parameters
File name []
```

Type or select values for the file name field. When you press F4, you can view a list of existing files in the **/etc/tunables** directory except the special files **nextboot**, **lastboot**, **lastboot.log**, **nextliveupdate**, and any special file that has the file name ending with **.lvup**. You must not specify any of these reserved names for the files. After you press **ENTER**, the **nextboot** file is copied to the specified **/etc/tunables** directory with the **.lvup** extension if the **tuncheck** command ran successfully on the file. |<

## > Restore All Next Boot and Next Live Update Parameters from Saved Values

### Restore All Next Boot and Next Live Update Parameters from Saved Values

Move cursor to desired item and press Enter.

```
mytunablefile      Description field of mytunable file
tun1                Description field of tun1 file
```

A select menu shows existing files in the `/etc/tunables` directory, except the special files `nextboot`, `lastboot`, `lastboot.log`, `nextliveupdate`, and any special file that has the file name ending with `.lvup`. You are prompted to select two files: `nextboot` and `nextliveupdate` files. After you select the files and press ENTER, all values from the selected file for next boot are copied to the `nextboot` file, and all values from the selected file for next Live Update operation are copied to the `nextliveupdate` file, if the **tuncheck** command ran successfully on the files. If necessary, you are prompted to run the `bosboot` operation. You are also warned that for all the changes to be effective, you must reboot the system. |<

## Changing individual parameters managed by a tuning command

All the panels for all six commands behave the same way. In the following sections, we will use the example of the Scheduler and Memory Load Control (i.e. **schedo**) panels to explain the behavior.

Here is the main panel to manipulate parameters managed by the **schedo** command:

### Tuning Scheduler and Memory Load Control Parameters

```
List All Characteristics of Current Parameters
Change / Show Current Parameters
Change / Show Parameters for next boot
Save Current Parameters for Next Boot
Reset Current Parameters to Default value
Reset Next Boot Parameters To Default Value
Change / Show Parameters for Next Live Update
Reset Next Boot and Next Live Update Parameters To Default Value
```

## Interaction between parameter types and the different SMIT sub-panels

Review the following information to learn about the SMIT panel actions.

The following table shows the interaction between parameter types and the different SMIT sub-panels:

Sub-panel name	Action
List All Characteristics of Current Parameters	Lists current, default, reboot, limit values, unit, type and dependencies. This is the output of a tuning command called with the <b>-L</b> option.
Change / Show Current Parameters	Displays and changes current parameter value, except for parameter of type Static, Bosboot and Reboot which are displayed without surrounding square brackets to indicate that they cannot be changed.
Change / Show Parameters for Next Boot	Displays values from and rewrite updated values to the <b>nextboot</b> file. If necessary, <b>bosboot</b> will be proposed. Only parameters of type Static cannot be changed (no brackets around their value).
Save Current Parameters for Next Boot	Writes current parameters in the <b>nextboot</b> file, <b>bosboot</b> will be proposed if any parameter of type Bosboot was changed.

Sub-panel name	Action
Reset Current Parameters to Default value	Resets current parameters to default values, except those which need a <b>bosboot</b> plus reboot or a reboot (bosboot and reboot type).
Reset Next Boot Parameters to Default value	Clears values in the <b>nextboot</b> file, and propose <b>bosboot</b> if any parameter of type Bosboot was different from its default value.

Each of the sub-panels behavior is explained in the following sections using examples of the scheduler and memory load control sub-panels:

1. List All Characteristics of Tuning Parameters The output of **schedo -L** is displayed.
2. Change/Show Current Scheduler and Memory Load Control Parameters

#### Change / Show Current Scheduler and Memory Load Control Parameters

[Entry Field]

```

affinity_lim           [7]
idle_migration_barrier [4]
fixed_pri_global       [0]
maxspin                [1]
pacefork               [10]
sched_D                [16]
sched_R                [16]
timeslice              [1]
%usDelta               [100]
v_exempt_secs          [2]
v_min_process          [2]
v_repage_hi            [2]
v_repage_proc          [6]
v_sec_wait             [4]

```

This panel is initialized with the current **schedo** values (output from the **schedo -a** command). Any parameter of type **Bosboot**, **Reboot** or **Static** is displayed with no surrounding square bracket indicating that it cannot be changed. From the F4 list, type or select values for the entry fields corresponding to parameters to be changed. Clearing a value results in resetting the parameter to its default value. The F4 list also shows minimum, maximum, and default values, the unit of the parameter and its type. Selecting F1 displays the help associated with the selected parameter. The text displayed will be identical to what is displayed by the tuning commands when called with the **-h** option. Press **ENTER** after making all the required changes. Doing so will launch the **schedo** command to make the changes. Any error message generated by the command, for values out of range, incompatible values, or lower values for parameter of type **Incremental**, will be displayed to the user.

3. The following is an example of the Change / Show Scheduler and Memory Load Control Parameters for next boot panel.

**Change / Show Scheduler and Memory Load Control Parameters for next boot**

[Entry Field]

affinity_lim	[7]
idle_migration_barrier	[4]
fixed_pri_global	[0]
maxpin	[1]
pacefork	[10]
sched_D	[16]
sched_R	[16]
timeslice	[1]
%usDelta	[100]
v_exempt_secs	[2]
v_min_process	[2]
v_repage_hi	[2]
v_repage_proc	[6]
v_sec_wait	[4]

This panel is similar to the previous panel, in that, any parameter value can be changed except for parameters of type **Static**. It is initialized with the values listed in the `/etc/tunables/nextboot` file, completed with default values for the parameter not listed in the file. Type or select (from the F4 list) values for the entry field corresponding to the parameters to be changed. Clearing a value results in resetting the parameter to its default value. The F4 list also shows minimum, maximum, and default values, the unit of the parameter and its type. Pressing F1 displays the help associated with the selected parameter. The text displayed will be identical to what is displayed by the tuning commands when called with the `-h` option. Press **ENTER** after making all desired changes. Doing so will result in the `/etc/tunables/nextboot` file being updated with the values modified in the panel, except for out of range, and incompatible values for which an error message will be displayed instead. If necessary, the user will be prompted to run **bosboot**.

4. The following is an example of the Save Current Scheduler and Memory Load Control Parameters for Next Boot panel.

**Save Current Scheduler and Memory Load Control Parameters for Next Boot**

ARE YOU SURE ?

After pressing **ENTER** on this panel, all the current **schedo** parameter values will be saved in the `/etc/tunables/nextboot` file . If any parameter of type **Bosboot** needs to be changed, the user will be prompted to run **bosboot**.

5. The following is an example of the Reset Current Scheduler and Memory Load Control Parameters to Default Values

**Reset Current Scheduler and Memory Load Control Parameters to Default Value**

ARE YOU SURE ?

After selecting **yes** and pressing **ENTER** on this panel, all the tuning parameters managed by the **schedo** command will be reset to their default value. If any parameter of type **Incremental**, **Bosboot** or **Reboot** should have been changed, and error message will be displayed instead.

6. The following is an example of the Reset Scheduler and Memory Load Control Next Boot Parameters To Default Values

**Reset Next Boot Parameters To Default Value**

ARE YOU SURE ?

After pressing **ENTER**, the **schedo** stanza in the `/etc/tunables/nextboot` file will be cleared. This will defer changes until next reboot. If necessary, **bosboot** will be proposed.

# The procmon tool

---

This section provides detailed information about the **procmon** tool.

## Overview of the procmon tool

You can use the **procmon** tool on systems running AIX.

The **procmon** tool enables you to view and manage the processes running on a system. The **procmon** tool has a graphical interface and displays a table of process metrics that you can sort on the different fields that are provided. The default number of processes listed in the table is 20, but you can change the value in the **Table Properties** panel from the main menu. Only the top processes based on the sorting metric are displayed and the default sorting key is CPU consumption.

The default value of the refresh rate for the table of process metrics is 5 seconds, but you can change the refresh rate by either using the **Table Properties** panel in the main menu or by clicking on the **Refresh** button.

By default, the **procmon** tool displays the following:

- How long a process has been running
- How much CPU resource the processes are using
- Whether processes are being penalized by the system
- How much memory the processes are using
- How much I/O a process is performing
- The priority and nice values of a process
- Who has created a particular process

You can choose other metrics to display from the **Table Properties** panel in the main menu. For more information, see [“The process table of the procmon tool”](#) on page 224.

You can filter any of the processes that are displayed. For more information, see [“Filtering processes”](#) on page 226.

You can also perform certain AIX performance commands on these processes. For more information, see [“Performing AIX commands on processes”](#) on page 226.

The **procmon** tool is a Performance Workbench plugin, so you can only launch the **procmon** tool from within the Performance Workbench framework. You must install the **bos.perf.gtools** filesset by either using the **smitty** tool or the **installp** command. You can then access the Performance Workbench by running the **/usr/bin/perfwb** script.

**Note:** Do not run the **/opt/perfwb/perfwb** binary file.

## Components of the procmon tool

The graphical interface of the **procmon** tool consists of the following components.

### The global statistics area of the procmon tool

The global statistics area is a table that is displayed at the top of the **procmon** tool window. The global statistics area displays the amount of CPU and memory that is being used by the system.

You can refresh the statistics data by either clicking on the **Refresh** button in the menu bar or by activating the automatic refresh option through the menu bar. To save the statistics information, you can export the table to any of the following file formats:

- XML
- HTML
- CSV

## The process table of the procmon tool

The process table is the main component of the **procmon** tool. The process table displays the various processes that are running on the system, ordered and filtered according to the user configuration.

The default value of the number of processes listed in the process table is 20, but you can change this value from the **Table Properties** panel from the main menu.

The yellow arrow key in the column header indicates the sort key for the process table. The arrow points either up or down, depending on whether the sort order is ascending or descending, respectively. You can change the sort key by clicking on any of the column headers.

You can customize the process table, modify the information on the various processes, and run commands on the displayed processes. By default, the **procmon** tool displays the following columns:

<b>PID</b>	<b>Process identifier</b>
<b>CPUPER</b>	Percentage of CPU used per process since the last refresh
<b>PRM</b>	Percent real memory usage
<b>ELOGIN</b>	Effective login of the process user
<b>COMMAND</b>	Short name of the process launched
<b>WPAR</b>	WPAR of the process

You can choose to display other metrics, like the following:

<b>Item</b>	<b>Descriptor</b>
<b>PPID</b>	Parent process identifier
<b>NICE</b>	Nice value for the process
<b>PRI</b>	Priority of the process
<b>DRSS</b>	Data resident set size
<b>TRSS</b>	Text resident set size
<b>STARTTIME</b>	Time when the command started
<b>EUID</b>	Effective user identifier
<b>RUID</b>	Real user identifier
<b>EGID</b>	Effective group identifier
<b>RGID</b>	Real group identifier
<b>THCOUNT</b>	Number of threads used
<b>CLASSID</b>	Identifier of the class which pertains to the WLM process
<b>CLASSNAME</b>	Name of the class which pertains to the WLM process
<b>TOTDISKIO</b>	Disk I/O for that process
<b>NVCSW</b>	N voluntary context switches
<b>NIVCSW</b>	N involuntary context switches
<b>MINFLT</b>	Minor page faults
<b>MAJFLT</b>	Major page faults
<b>INBLK</b>	Input blocks
<b>OUBLK</b>	Output blocks

Item	Descriptor
<b>MSGSEND</b>	Messages sent
<b>MSGRECV</b>	Messages received
<b>EGROUP</b>	Effective group name
<b>RGROUP</b>	Real group name

You can use either the table properties or preference to display the metrics you are interested in. If you choose to change the table properties, the new configuration values are set for the current session only. If you change the preferences, the new configuration values are set for the next session of the **procmon** tool.

There are two types of values listed in the process table:

- Real values
- Delta values

Real values are retrieved from the kernel and displayed in the process table. An example of a real value is the PID, PPID, or TTY.

Delta values are values that are computed from the last-stored measurements. An example of a delta value is the CPU percent for each process, which is computed using the values measured between refreshes.

Below the process table, there is another table that displays the sum of the values for each column of the process table. For example, this table might provide a good idea of the percentage of total CPU used by the top 20 CPU-consuming processes.

You can refresh the data by either clicking on the **Refresh** button in the menu bar or by activating the automatic refresh option through the menu bar. To save the statistics information, you can export the table to any of the following file formats:

- XML
- HTML
- CSV

## The status line of the Performance Workbench

The Performance Workbench status line displays the date on which the information was retrieved, as well as the name of the system. The status line is hidden if you activate another view or perspective, but automatically reappears if you refresh the information.

## The WPAR table of the procmon tool

A WPAR tabulation displays all the WPAR defined on the system in a table.

By default, the procmon tool displays the following columns:

Item	Descriptor
<b>Name</b>	WPAR name
<b>Hostname</b>	WPAR hostname
<b>Type</b>	WPAR type, either System or Application
<b>State</b>	WPAR state—this can have one of the following values: Active, Defined, Transitional, Broken, Paused, Loaded, Error
<b>Directory</b>	WPAR root directory
<b>Nb. virtual PIDs</b>	Number of virtual PIDs running in this WPAR

## Filtering processes

You can filter processes based on the various criteria that is displayed in the process table. To create a filter, select **Table Filters** from the menu bar. A new window opens and displays a list of filters.

## Performing AIX commands on processes

To run any of the following commands on one or more processes, select the processes in the process table and right click your mouse, and select either **Commands** or **Modify** and then select the command you want to run. A new window opens, which displays the command output while the command is running.

You can interrupt the command by clicking on the **STOP** button.

You can run the following AIX commands on the processes you select in the process table:

- The **svmon** command
- The **renice** command
- The **kill** command
- The following **proctools** commands:
  - The **procfiles** command
  - The **proctree** command
  - The **procsig** command
  - The **procstack** command
  - The **procrun** command
  - The **procmmap** command
  - The **procflags** command
  - The **proccred** command
  - The **procldd** command

## Profiling tools

You can use profiling tools to identify which portions of the program are executed most frequently or where most of the time is spent.

Profiling tools are typically used after a basic tool, such as the **vmstat** or **iostat** commands, shows that a CPU bottleneck is causing a performance problem.

Before you begin locating hot spots in your program, you need a fully functional program and realistic data values.

## The timing commands

Use the timing commands for testing and debugging programs whose performance you are recording and trying to improve.

The output from the **time** command is in minutes and seconds, as follows:

```
real    0m26.72s
user    0m26.53s
sys     0m0.03s
```

The output from the **timex** command is in seconds, as follows:

```
real 26.70
user 26.55
sys  0.02
```

Comparing the user+sys CPU time to the real time will give you an idea if your application is CPU-bound or I/O-bound.

**Note:** Be careful when you do this on an SMP system. For more information, see [time and timex Cautions](#)).

The **timex** command is also available through the SMIT command on the Analysis Tools menu, found under Performance and Resource Scheduling. The **-p** and **-s** options of the **timex** command enable data from accounting (**-p**) and the sar command (**-s**) to be accessed and reported. The **-o** option reports on blocks read or written.

## The prof command

The **prof** command displays a profile of CPU usage for each external symbol, or routine, of a specified program.

In detail, it displays the following:

- The percentage of execution time spent between the address of that symbol and the address of the next
- The number of times that function was called
- The average number of milliseconds per call

The **prof** command interprets the profile data collected by the **monitor()** subroutine for the object file (**a.out** by default), reads the symbol table in the object file, and correlates it with the profile file (**mon.out** by default) generated by the **monitor()** subroutine. A usage report is sent to the terminal, or can be redirected to a file.

To use the **prof** command, use the **-p** option to compile a source program in C, FORTRAN, or COBOL. This inserts a special profiling startup function into the object file that calls the **monitor()** subroutine to track function calls. When the program is executed, the **monitor()** subroutine creates a **mon.out** file to track execution time. Therefore, only programs that explicitly exit or return from the main program cause the **mon.out** file to be produced. Also, the **-p** flag causes the compiler to insert a call to the **mccount()** subroutine into the object code generated for each recompiled function of your program. While the program runs, each time a parent calls a child function, the child calls the **mccount()** subroutine to increment a distinct counter for that parent-child pair. This counts the number of calls to a function.

**Note:** You cannot use the **prof** command for profiling optimized code.

By default, the displayed report is sorted by decreasing percentage of CPU time. This is the same as when specifying the **-t** option.

The **-c** option sorts by decreasing number of calls and the **-n** option sorts alphabetically by symbol name.

If the **-s** option is used, a summary file **mon.sum** is produced. This is useful when more than one profile file is specified with the **-m** option (the **-m** option specifies files containing monitor data).

The **-z** option includes all symbols, even if there are zero calls and time associated.

Other options are available and explained in the **prof** command in the *Files Reference*.

The following example shows the first part of the **prof** command output for a modified version of the Whetstone benchmark (Double Precision) program.

```
# cc -o cwhet -p -lm cwhet.c
# cwhet > cwhet.out
# prof
Name           %Time    Seconds    Cumsecs    #Calls    msec/call
.main          32.6     17.63     17.63      1         17630.
.__mcount      28.2     15.25     32.88
.mod8          16.3     8.82      41.70     8990000   0.0010
.mod9          9.9      5.38      47.08     6160000   0.0009
.cos           2.9      1.57      48.65     1920000   0.0008
.exp           2.4      1.32      49.97     930000    0.0014
.log           2.4      1.31      51.28     930000    0.0014
.mod3          1.9      1.01      52.29     140000    0.0072
.sin           1.2      0.63      52.92     640000    0.0010
.sqrt          1.1      0.59      53.51
.atan          1.1      0.57      54.08     640000    0.0009
.pout          0.0      0.00      54.08     10        0.0
.exit          0.0      0.00      54.08     1         0.
```

.free	0.0	0.00	54.08	2	0.
.free_y	0.0	0.00	54.08	2	0.

In this example, we see many calls to the **mod8()** and **mod9()** routines. As a starting point, examine the source code to see why they are used so much. Another starting point could be to investigate why a routine requires so much time.

**Note:** If the program you want to monitor uses a **fork()** system call, be aware that the parent and the child create the same file (**mon.out**). To avoid this problem, change the current directory of the child process.

## The gprof command

The **gprof** command produces an execution profile of C, FORTRAN, or COBOL programs.

The statistics of called subroutines are included in the profile of the calling program. The **gprof** command is useful in identifying how a program consumes CPU resources. It is roughly a superset of the **prof** command, giving additional information and providing more visibility to active sections of code.

### Implementation of the gprof command

The source code must be compiled with the **-pg** option.

This action links in versions of library routines compiled for profiling and reads the symbol table in the named object file (**a.out** by default), correlating it with the call graph profile file (**gmon.out** by default). This means that the compiler inserts a call to the **mccount()** function into the object code generated for each recompiled function of your program. The **mccount()** function counts each time a parent calls a child function. Also, the **monitor()** function is enabled to estimate the time spent in each routine.

The **gprof** command generates two useful reports:

- The call-graph profile, which shows the routines, in descending order by CPU time, plus their descendants. The profile permits you to understand which parent routines called a particular routine most frequently and which child routines were called by a particular routine most frequently.
- The flat profile of CPU usage, which shows the usage by routine and number of calls, similar to the **prof** output.

Each report section begins with an explanatory part describing the output columns. You can suppress these pages by using the **-b** option.

Use **-s** for summaries and **-z** to display routines with zero usage.

Where the program is executed, statistics are collected in the **gmon.out** file. These statistics include the following:

- The names of the executable program and shared library objects that were loaded
- The virtual memory addresses assigned to each program segment
- The **mccount()** data for each parent-child
- The number of milliseconds accumulated for each program segment

Later, when the **gprof** command is issued, it reads the **a.out** and **gmon.out** files to generate the two reports. The call-graph profile is generated first, followed by the flat profile. It is best to redirect the **gprof** output to a file, because browsing the flat profile first might answer most of your usage questions.

The following example shows the profiling for the **cwhtet** benchmark program. This example is also used in [“The prof command” on page 227](#):

```
# cc -o cwhtet -pg -lm cwhtet.c
# cwhtet > cwhtet.out
# gprof cwhtet > cwhtet.gprof
```

## The call-graph profile

The call-graph profile is the first part of the **cwHet.gprof** file.

The following is an example of the **cwHet.gprof** file:

```
granularity: each sample hit covers 4 byte(s) Time: 62.85 seconds

index  %time    self descendent  called/total  parents
      %time    self descendent  called+self  name         index
      %time    self descendent  called/total  children

[1]    64.6    19.44    21.18         1/1          .__start [2]
      19.44    21.18         1          .main [1]
      8.89     0.00    8990000/8990000 .mod8 [4]
      5.64     0.00    6160000/6160000 .mod9 [5]
      1.58     0.00    930000/930000   .exp [6]
      1.53     0.00    1920000/1920000 .cos [7]
      1.37     0.00    930000/930000   .log [8]
      1.02     0.00    140000/140000   .mod3 [10]
      0.63     0.00    640000/640000   .atan [12]
      0.52     0.00    640000/640000   .sin [14]
      0.00     0.00    10/10          .pout [27]

-----
[2]    64.6    0.00     40.62        <spontaneous>
      19.44    21.18         1/1          .__start [2]
      0.00     0.00         1/1          .main [1]
      0.00     0.00         1/1          .exit [37]
-----
```

Usually the call graph report begins with a description of each column of the report, but it has been deleted in this example. The column headings vary according to type of function (current, parent of current, or child of current function). The current function is indicated by an index in brackets at the beginning of the line. Functions are listed in decreasing order of CPU time used.

To read this report, look at the first index [1] in the left-hand column. The `.main` function is the current function. It was started by `.__start` (the parent function is on top of the current function), and it, in turn, calls `.mod8` and `.mod9` (the child functions are beneath the current function). All the accumulated time of `.main` is propagated to `.__start`. The `self` and `descendent` columns of the children of the current function add up to the `descendent` entry for the current function. The current function can have more than one parent. Execution time is allocated to the parent functions based on the number of times they are called.

## Flat profile

The flat profile sample is the second part of the **cwHet.gprof** file.

The following is an example of the **cwHet.gprof** file:

```
granularity: each sample hit covers 4 byte(s) Total time: 62.85 seconds

%   cumulative  self      self     total
time seconds    seconds   calls   ms/call  ms/call  name
30.9  19.44      19.44         1 19440.00 40620.00 .main [1]
30.5  38.61      19.17      8990000  0.00     0.00 .__mcount [3]
14.1  47.50       8.89 8990000  0.00     0.00 .mod8 [4]
9.0   53.14       5.64 6160000  0.00     0.00 .mod9 [5]
2.5   54.72       1.58 930000  0.00     0.00 .exp [6]
2.4   56.25       1.53 1920000  0.00     0.00 .cos [7]
2.2   57.62       1.37 930000  0.00     0.00 .log [8]
2.0   58.88       1.26 .qincrement [9]
1.6   59.90       1.02 140000  0.01     0.01 .mod3 [10]
1.2   60.68       0.78 .__stack_pointer [11]
1.0   61.31       0.63 640000  0.00     0.00 .atan [12]
0.9   61.89       0.58 .qincrement1 [13]
0.8   62.41       0.52 640000  0.00     0.00 .sin [14]
0.7   62.85       0.44 .sqrt [15]
0.0   62.85       0.00 180 0.00     0.00 .fwrite [16]
0.0   62.85       0.00 180 0.00     0.00 .memchr [17]
0.0   62.85       0.00 90 0.00     0.00 .__flsbuf [18]
0.0   62.85       0.00 90 0.00     0.00 ._flsbuf [19]
```

The flat profile is much less complex than the call-graph profile and very similar to the output of the **prof** command. The primary columns of interest are the `self` seconds and the `calls` columns. These reflect the CPU seconds spent in each function and the number of times each function was called. The next columns to look at are `self` ms/call (CPU time used by the body of the function itself) and `total` ms/call (time in the body of the function plus any descendent functions called).

Normally, the top functions on the list are candidates for optimization, but you should also consider how many calls are made to the function. Sometimes it can be easier to make slight improvements to a frequently called function than to make extensive changes to a piece of code that is called once.

A cross reference index is the last item produced and looks similar to the following:

```
Index by function name

[18] .__flsbuf          [37] .exit                [5] .mod9
[34] .__ioctl          [6] .exp                  [43] .moncontrol
[20] .__mcount          [39] .expand_catname     [44] .monitor
[3]  .__mcount          [32] .free                 [22] .myecvt
[23] .__nl_langinfo_std [33] .free_y              [28] .nl_langinfo
[11] .__stack_pointer    [16] .fwrite               [27] .pout
[24] .doprint           [40] .getenv               [29] .printf
[35] .findbuf            [41] .ioctl                [9] .qincrement
[19] .flsbuf             [42] .isatty               [13] .qincrement1
[36] .wrtchk             [8] .log                  [45] .saved_category_nam
[25] .xflsbuf            [1] .main                 [46] .setlocale
[26] .xwrite             [17] .memchr               [14] .sin
[12] .atan               [21] .mf2x2                [31] .splay
[38] .catopen            [10] .mod3                 [15] .sqrt
[7]  .cos               [4]  .mod8                 [30] .write
```

**Note:** If the program you want to monitor uses a **fork()** system call, be aware that by default, the parent and the child create the same file, **gmon.out**. To avoid this problem, use the GPROF environment variable. You can also use the GPROF environment variable to profile multi-threaded applications.

## The tprof command

The typical program execution is a variable combination of application code, library subroutines, and kernel services. Frequently, programs that have not been tuned expend most of their CPU cycles in certain statements or subroutines.

You can determine which particular statements or subroutines to examine with the **tprof** command.

The **tprof** command is a versatile profiler that provides a detailed profile of CPU usage by every process ID and name. It further profiles at the application level, routine level, and even to the source statement level and provides both a global view and a detailed view. In addition, the **tprof** command can profile kernel extensions, stripped executable programs, and stripped libraries. It does subroutine-level profiling for most executable programs on which the **stripnm** command produces a symbols table. The **tprof** command can profile any program produced by any of the following compilers:

- C
- C++
- FORTRAN
- Java™

The **tprof** command only profiles CPU activity. It does not profile other system resources, such as memory or disks.

The **tprof** command can profile Java programs using Java Persistence API (JPA) (**-x java -Xrunjpa**) to collect Java Just-in-Time (JIT) source line numbers and instructions, if the following parameters are added to **-Xrunjpa**:

- **source=1**; if IBM® Java Runtime Environment (JRE) 1.5.0 is installed, this parameter enables JIT source line collecting.
- **instructions=1**; enables JIT instructions collecting.

## Time-based profiling

Time-based profiling is the default profiling mode and it is triggered by the decremter interrupt, which occurs every 10 milliseconds.

With time-based profiling, the **tprof** command cannot determine the address of a routine when interrupts are disabled. While interrupts are disabled, all ticks are charged to the **unlock\_enable()** routines.

## Event-based profiling

Event-based profiling is triggered by any one of the software-based events or any Performance Monitor event that occurs on the processor.

The primary advantages of event-based profiling over time-based profiling are the following:

- The routine addresses are visible when interrupts are disabled.
- The ability to vary the profiling event
- The ability to vary the sampling frequency

With event-based profiling, ticks that occur while interrupts are disabled are charged to the proper routines. Also, you can select the profiling event and sampling frequency. The profiling event determines the trigger for the interrupt and the sampling frequency determines how often the interrupt occurs. After the specified number of occurrences of the profiling event, an interrupt is generated and the executing instruction is recorded.

The default type of profiling event is processor cycles. The following are various types of software-based events:

- Emulation interrupts (EMULATION)
- Alignment interrupts (ALIGNMENT)
- Instruction Segment Lookaside Buffer misses (ISLBMISS)
- Data Segment Lookaside Buffer misses (DSLBMIS)

The sampling frequency for the software-based events is specified in milliseconds and the supported range is 1 to 500 milliseconds. The default sampling frequency is 10 milliseconds.

The following command generates an interrupt every 5 milliseconds and retrieves the record for the last emulation interrupt:

```
# tprof -E EMULATION -f 5
```

The following command generates an interrupt every 100 milliseconds and records the contents of the Sampled Instruction Address Register, or SIAR:

```
# tprof -E -f 100
```

The following are other types of Performance Monitor events:

- Completed instructions
- Cache misses

For a list of all the Performance Monitor events that are supported on the processors of the system, use the **pmlist** command. The chosen Performance Monitor event must be taken in a group where we can also find the PM\_INST\_CMPL Performance Monitor event. The sampling frequency for these events is specified in the number of occurrences of the event. The supported range is 10,000 to MAXINT occurrences. The default sampling frequency is 10,000 occurrences.

The following command generates an interrupt after the processor completes 50,000 instructions:

```
# tprof -E PM_INST_CMPL -f 50000
```

Event-based profiling uses the SIAR, which contains the address of an instruction close to the executing instruction. For example, if the profiling event is PM\_FPU0\_FIN, which means the floating point unit 0

produces a result, the SIAR might not contain that floating point instruction but might contain another instruction close to it. This is more relevant for profiling based on Performance Monitor events. In fact for the proximity reason, on systems based on POWER4 and later, it is recommended that the Performance Monitor profiling event be one of the marked events. Marked events have the **PM\_MRK** prefix.

Certain combinations of profiling event, sampling frequency, and workload might cause interrupts to occur at such a rapid rate that the system spends most of its time in the interrupt handler. The **tprof** command detects this condition by keeping track of the number of completed instructions between two consecutive interrupts. When the **tprof** command detects five occurrences of the count falling below the acceptable limit, the trace collection stops. Reports are still generated and an error message is displayed. The default threshold is 1,000 instructions.

## Large page analysis

The **tprof -a** command collects profile trace from a representative application run and produces performance projections for mapping different portions of the application's data space to different page sizes.

Large Page Analysis uses the information in the trace to project translation buffer performance when mapping any of the following four application memory regions to a different page size:

- static application data (initialized and uninitialized data)
- application heap (dynamically allocated data)
- stack
- application text

The performance projections are provided for each of the page sizes supported by the operating system. The first performance projection is a baseline projection for mapping all four memory regions to the default 4 KB pages. Subsequent projections map one region at a time to a different page size. The statistics reported for each projection include: the page size, the number of pages needed to back all four regions, a translation miss score, and a cold translation miss score.

The summary section lists the processes profiled and the statistics reported including: number/percentage of memory reference, modeled memory reference, malloc calls, and free calls.

### *How to interpret the results*

The translation miss score is an indicator of the translation miss rate and ranges from 0 (no translation misses) to 1 (every reference results in a translation miss).

The translation miss rate is defined as:

```
Translation miss rate = (Number of translation misses)/(Number of translation buffer accesses)
```

The translation miss score differs from the actual translation miss rate because it is based on sampled references. Sampling has the effect of reducing the denominator (Number of translation buffer accesses) in the above equation faster than the numerator (Number of translation misses). As a result, the translation miss score tends to overestimate the actual translation miss rate at increasing sampling rates. Thus, the translation score should be interpreted as a relative measure for comparing the effectiveness of different projections rather than as a predictor of actual translation miss rates.

The translation miss score is directly affected by larger page sizes: growing the page size reduces the translation miss score. The performance projection report includes both a cold translation miss score (such as compulsory misses) and a total translation miss score (such as compulsory and capacity misses). The cold translation miss score provides a useful lower bound; if growing the page size has reduced the translation miss score to the cold translation miss score, then all capacity translation misses have been eliminated and further increases in page size can only have negligible additional benefits.

The performance projection for a process would appear similar to the following:

```
Modeled region for the process ./workload [661980]
```

Region	Start	End	Size (KB)	%MemRef
heap	0x1100059b0	0x1207b0b60	269996.43	74.45
data	0x110000710	0x11000598c	20.63	1.55
stack	0xffffffffced10	0xffffffffffe0	196.71	20.44
text	0x100000288	0x100053710	333.14	2.56

Performance projection for the process ./workload [661980]

Region	PageSize	# Pages	TMissScore	ColdTMissScore
heap	4 KB	67500	0.92343 (100.0%)	0.09234 (100.0%)
heap	64 KB	4219	0.53615 ( 45.0%)	0.02744 ( 30.0%)
heap	16 MB	17	0.00010 ( 00.1%)	0.00002 ( 00.1%)
data	4 KB	6	0.53615 (100.0%)	0.02744 (100.0%)
data	64 KB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)
data	16 MB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)
stack	4 KB	50	0.53615 (100.0%)	0.02744 (100.0%)
stack	64 KB	4	0.05361 ( 10.0%)	0.00274 ( 10.0%)
stack	16 MB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)
text	4 KB	84	0.53615 (100.0%)	0.04744 (100.0%)
text	64 KB	6	0.05361 ( 10.0%)	0.00274 ( 10.0%)
text	16 MB	1	0.00053 ( 00.1%)	0.00009 ( 00.1%)

#### Data profiling

The **tprof -b** command turns on basic data profiling and collects data access information.

The summary section reports access information across kernel data, library data, user global data, and stackheap sections for each process, as shown in the following example:

Table 8. Data profiling of the tprof -b command

Process	Freq	Total	Kernel	User	Shared	Other
tlbref	1	60.49	0.07	59.71	0.38	0.00
/usr/bin/dd	1	39.30	26.75	11.82	0.73	0.00
tprof	2	0.21	0.21	0.00	0.33	0.00
Total	20	100.00	27.03	71.53	1.44	0.00

Table 9. An example of the data profiling report for the /usr/bin/dd process.

Process	PID	TID	Total	Kernel	User	Shared	Other
tlbref	327688	757943	60.49	0/07	59.71	0.38	0.00
	Kernel:	0.04%					
	lib:	0.00%					
	u_global:	0.00%					

Table 9. An example of the data profiling report for the /usr/bin/dd process. (continued)

Process	PID	TID	Total	Kernel	User	Shared	Other
	stackheap:	u_global:	0.00%				
	unresolved:	99.42%					
tprof	3278000	792863	0.21	0.21	0.00	0.00	0.00
	kernel:	0.20%					
	lib:	0.00%					
	u_global:	0.00%					
	stackheap	0.00%					
	unresolved:	0.01%					
/usr/bin/dd	323768	974985	39.30	26.75	11.82	0.73	0.00
	kernel:	12.86%					
	lib:	0.00%					
	u_global:	7.80%					
	stackheap:	2.42%					
	unresolved:	2.18%					
Total			100.00	27.03	99.01	1.44	0.00

When used with the **-s**, **-u**, **-k** and **-e** flags, the **tprof** command's data profiling reports most-used data structures (exported data symbols) in shared library, binary, kernel and kernel extensions. The **-B** flag also reports the functions that use data structures.

The second table shown is an example of the data profiling report for the /usr/bin/dd process.. The example report shows that `__start` data structure is the most used data structure in the /usr/bin/dd process, based on the samples collected. The data structure is a list of functions (right aligned) that use the data structure, reported along with their share and source as shown in the following example:

Total % For /usr/bin/dd[323768] (/usr/bin/dd) = 11.69	
Subroutine	% Source
.noconv	11.29 /usr/bin/dd
.main	0.14 /usr/bin/dd
.read	0.07 glink.s
.setobuf	0.05 /usr/bin/dd
.rpipe	0.04 /usr/bin/dd
.flsh	0.04 /usr/bin/dd
.write	0.04 glink.s
.wbuf	0.02 /usr/bin/dd
.rbuf	0.02 /usr/bin/dd
Data	% Source
__start	7.80 /usr/bin/dd
.noconv	6.59 /usr/bin/dd

Data	% Source
.main	0.14 /usr/bin/dd
.read	0.04 glink.s
.wbuf	0.02 /usr/bin/dd
.write	0.02 glink.s
.flsh	0.102 /usr/bin/dd

## Implementation of the tprof command

The **tprof** command uses the system trace facility. Since you can only execute the trace facility one user at a time, you can only execute one **tprof** command at a time.

You can obtain the raw data for the **tprof** command through the trace facility. For more information about the trace facility, see [Analyzing Performance with the Trace Facility in Files Reference](#).

When a program is profiled, the trace facility is activated and instructed to collect data from the trace hook with hook ID 234 that records the contents of the Instruction Address Register, or IAR, when a system-clock interrupt occurs (100 times a second per processor). Several other trace hooks are also activated to enable the **tprof** command to track process and dispatch activity. The trace records are not written to a disk file. They are written to a pipe that is read by a program that builds a table of the unique program addresses that have been encountered and the number of times each one occurred. When the workload being profiled is complete, the table of addresses and their occurrence counts are written to disk. The data-reduction component of the **tprof** command then correlates the instruction addresses that were encountered with the ranges of addresses occupied by the various programs and reports the distribution of address occurrences, or *ticks*, across the programs involved in the workload.

The distribution of ticks is roughly proportional to the CPU time spent in each program, which is 10 milliseconds per tick. After the high-use programs are identified, you can take action to restructure the hot spots or minimize their use.

## Example: tprof command

You can view the complete details of the **tprof** command in [Files Reference](#).

The following example demonstrates how to collect a CPU tick profile of a program using the **tprof** command. The example was executed on a 4-way SMP system and since it is a fast-running system, the command completed in less than a second. To make this program run longer, the array size, or *Asize*, was changed to 4096 instead of 1024.

Upon running the following command, the **version1.prof** file is created in the current directory:

```
# tprof -z -u -p version1 -x version1
```

The **version1.prof** file reports how many CPU ticks for each of the programs that were running on the system while the **version1** program was running.

The following is an example of what the **version1.prof** file contains:

Process	Freq	Total	Kernel	User	Shared	Other	
=====	====	=====	=====	====	=====	=====	
wait	4	5810	5810	0	0	0	
./version1	1	1672	35	1637	0	0	
/usr/bin/tprof	2	15	13	0	2	0	
/etc/syncd	1	2	2	0	0	0	
/usr/bin/sh	2	2	2	0	0	0	
swapper	1	1	1	0	0	0	
/usr/bin/trcstop	1	1	1	0	0	0	
rmcd	1	1	1	0	0	0	
=====	====	=====	=====	====	=====	=====	
Total	13	7504	5865	1637	2	0	
Process	PID	TID	Total	Kernel	User	Shared	Other
=====	====	====	=====	=====	====	=====	=====

```

        wait      16392    16393    1874    1874        0        0        0
        wait      12294    12295    1873    1873        0        0        0
        wait      20490    20491    1860    1860        0        0        0
./version1 245974    606263    1672     35    1637        0        0
        wait      8196     8197     203     203        0        0        0
/usr/bin/tprof 291002    643291     13     13         0        0        0
/usr/bin/tprof 274580    610467     2         0         0        2        0
/etc/syncd    73824    110691     2         2         0        0        0
/usr/bin/sh   245974    606263     1         1         0        0        0
/usr/bin/sh   245976    606265     1         1         0        0        0
/usr/bin/trcstop 245976    606263     1         1         0        0        0
swapper       0         3         1         1         0        0        0
rmcd         155876    348337     1         1         0        0        0
=====
Total        7504     5865    1637         2         0

```

Total Samples = 7504      Total Elapsed Time = 18.76s

Profile: ./version1  
Total Ticks For All Processes (./version1) = 1637

Subroutine	Ticks	%	Source	Address	Bytes
.main	1637	21.82	version1.c	350	536

Profile: ./version1  
Total Ticks For ./version1[245974] (./version1) = 1637

Subroutine	Ticks	%	Source	Address	Bytes
.main	1637	21.82	version1.c	350	536

The first section of the report summarizes the results by program, regardless of the process ID, or PID. It shows the number of different processes, or Freq, that ran each program at some point.

The second section of the report displays the number of ticks consumed by, or on behalf of, each process. In the example, the **version1** program used 1637 ticks itself and 35 ticks occurred in the kernel on behalf of the **version1** process.

The third section breaks down the user ticks associated with the executable program being profiled. It reports the number of ticks used by each function in the executable program and the percentage of the total run's CPU ticks (7504) that each function's ticks represent. Since the system's CPUs were mostly idle, most of the 7504 ticks are idle ticks.

To see what percentage of the busy time this program took, subtract the wait thread's CPU ticks, which are the idle CPU ticks, from the total and then divide the difference from the total number of ticks.

```

Total number of ticks / (Total - Idle CPU ticks) = % busy time of program
1637 / (7504 - 5810) =
1637 / 1694 = 0.97

```

So, the percentage of system busy ticks is 97%.

## The raso tunables

As the root user, you can tune the instruction threshold with the **tprof\_inst\_threshold** tunable of the **raso** command.

As the root user, you can tune the sampling frequency with the following **raso** tunables:

- **tprof\_cyc\_mult**
- **tprof\_evt\_mult**

For example, for events based on processor cycles, setting the **tprof\_cyc\_mult** tunable to 50 and specifying the **-f** flag as 100 is equivalent to specifying a sampling frequency of 100/50 milliseconds.

For other Performance Monitor events, setting the **tprof\_evt\_mult** tunable to 100 and specifying the **-f** flag as 20,000 is equivalent to specifying a sampling frequency of 20,000/100 occurrences.

## Manual offline processing with the tprof command

You can perform offline processing of trace files with the **tprof** command, but you must specify filenames with a *rootstring* name.

Also, there are certain suffixes required for the input files that the **tprof** command uses. For example, the trace binary file must end in *.trc*. Also, you need to collect the **gensyms** command output and put it in a file called the **rootstring.syms** file.

To insure the trace file contains sufficient information to be post-processed by **tprof**, the **trace** command line must include the **-M** and **-j tprof** flags.

If you name the *rootstring* file **trace1**, to collect a trace, you can use the **trace** command using all of the hooks or at least the following hooks:

```
# trace -af -M -T 1000000 -L 10000000 -o trace1.trc -j tprof
# workload
# trcoff
# gensyms > trace1.syms
# trcstop
# trcript -r trace1 -k -u -s -z
```

The example above creates a **trace1.prof** file, which gives you a CPU profile of the system while the **trace** command was running.

## The svmon command

---

The **svmon** command provides a more in-depth analysis of memory usage.

The **svmon** command captures a snapshot of the current state of memory; however, it is not a true snapshot because it runs at the user level with interrupts enabled.

If an interval is indicated by the **-i** flag statistics will be displayed until the command is killed or until the number of intervals which is specified with the **-i** flag, is reached.

You can generate the following different reports to analyze the memory consumption of your machine:

- command report (-C)
- detailed report (-D)
- global report (-G)
- process report (-P)
- segment report (-S)
- user report (-U)
- workload management Class report (-W)
- workload management tier report (-T)
- XML report (-X)

For more information on the **svmon** command, see *Files Reference*.

## Security

Any user of the machine can run the **svmon** command. It uses two different mechanisms to allow two different views for a non-root user.

The following will create the views:

- When **RBAC** authorization is used, the user will have the same view as the root user if their role is defined with **aix.system.stat** authorization.
- When **RBAC** is not used or when the user does not have the **aix.system.stat** authorization, the user's reports are limited to its environment or processes.

You can view the complete details of the **RBAC** in *Files Reference*.

## The svmon configuration file

A configuration file named **.svmonrc**, containing a list of **svmon -O** option, can be defined to overwrite the default values of these options. This file must be defined in the home directory of the user running **svmon** command.

At start time, the **svmon** command does the following:

- Initializes the default values for each **-O** option.
- Reads the **.svmonrc** file and overwrites the default **-O** option values with these new users default values.
- Reads the command flag defined by the user.

For example, the following **.svmonrc** file sets **svmon** to generate the default report format before the **-O** option were introduced:

```
# cat .svmonrc
summary=basic
segment=category
pgsz=on
```

### Note:

- When an option is not recognized in the file, it is ignored.
- When an option is defined more than once, only the last value will be used.

## Summary report metrics

The command report (**-C** option), global report (**-G** option), process report (**-P** option), user report (**-U** option), and workload management class report (**-W** option) include the same set type of summary metrics.

The following are the summary metrics:

- The **-O summary=basic** option used alone produces compact reports for the command report (**-C**), the process report (**-P**), the user report (**-U**), and the workload management class report (**-W**).
- The **-O summary=longreal** option used alone produces a compact report of the global report (**-G**).

In a system with Active Memory Expansion enabled, two new summary report metrics are available for global report (**-G** option).

- The **-O summary=ame option** used alone produces detailed memory compression information for the global report (**-G**).
- The **-O summary=longame** option used alone produces a compact report of memory compression information for the global report (**-G**).

## Basic summary report metrics

This is the *compatibility* mode with the previous versions of **svmon** command (before the **-O** option was introduced). This format uses 80 columns.

In these summaries, the following columns are always displayed:

Item	Descriptor
Inuse	Number of frames containing pages (expressed in <unit>) used by the report entities.
Pin	Number of frames containing pinned pages (expressed in <unit>) used by the report entities.
Pin	Number of pages (expressed in <unit>) allocated in the paging space by the report entities.
Virtual	Number of pages (expressed in <unit>) allocated in the virtual space by the report entities.

## Report formatting options

Review the report formatting options for the **svmon** command.

The svmon configuration file can generate two types of reports for the **-G**, **-P**, **-U**, **-C**, and **-W** option:

- **Compact report**, which is a one-line-per-entity report.
- **Long report**, which uses several lines per entity.

For the **-G** option, you can switch from the standard report to the compact report with the option **-O summary=longreal**. For the **-P**, **-U**, **-C** and **-W** options, a compact report is reported when the option **-O summary=basic** is set and the option **-O segment=off** is set (default value).

The following **-O** options can be used in both compact or long reports:

- **-O format=[80,160,nolimit]**: This option sets the width of the report. The default width of most reports is 80 characters. But, some reports need 160 characters, in which case this option is implicitly set. You can always specify to display the reports with more columns, to eliminate truncated strings.
- **-O timestamp=[on | off]**: When this flag is set to **on**, a timestamp, recorded when the svmon command begins retrieving data, is displayed at the beginning of the report. Because the data collection can take some time, you can use the **-O timestamp=on** with the **-i** flag to specify timestamp intervals. The time specified with the **-i** flag is the interval between the end of one **svmon** command iteration and the start of the next one.

### Example:

In this example, the command line specifies to run svmon 3 times every 5 seconds. The timestamp and command line are set with the **.svmonrc** file.

- **-O commandline=[on|off]**: when set to on, this option adds the command line you use to produce the report in the report header.

```
# svmon -G -i 5 3
```

```
Command line : svmon -G -i 5 3
.svmonrc: -O timestamp=on,commandline=on
Unit: page
-----
memory      size      inuse     free      pin      virtual  available
pg space    262144   227471   34673    140246   223696   53801
-----
work        pers      clnt      other
pin         113676   0         0        10186
in use     189693   0        29586
Unit: page
-----
memory      size      inuse     free      pin      virtual  available
pg space    262144   227473   34671    140243   223697   53800
-----
work        pers      clnt      other
pin         113673   0         0        10186
in use     189694   0        29587
Unit: page
-----
memory      size      inuse     free      pin      virtual  available
pg space    262144   227475   34670    140244   223699   53799
-----
work        pers      clnt      other
pin         113674   0         0        10186
in use     189696   0        29587
-----
Timestamp: 11:23:02
Timestamp: 11:23:07
Timestamp: 11:23:12
```

### Example:

```
# svmon -G -O commandline=on
```

```
Command line : svmon -G -O commandline=on
Unit: page
-----
```

	size	inuse	free	pin	virtual	available
memory	262144	227312	34832	140242	223536	53961
pg space	131072	39091				
	work	pers	clnt	other		
pin	113672	0	0	10186		
in use	189533	0	29587			

- **-O unit=[auto,page,KB,MB,GB]**: this option is set to **page** by default. In this case, the reported metrics for each segment are in the segment page size:
  - s are 4 KB pages
  - m are 64 KB pages
  - L are 16 MB pages
  - S are 16 GB pages

When **auto**, **KB**, **MB**, or **GB** are used, only the 3 most significant digits are displayed. You should be careful when interpreting the results with a unit other than **page**. When the **auto** setting is selected, the abbreviated units are specified immediately after each metric (K for kilobytes, M for megabytes, or G for gigabytes).

### Examples:

This is the same report using different **unit** options:

```
# svmon -G -O unit=page
Unit: page
=====
memory      size      inuse     free      pin      virtual  available
pg space    131072   39091    34832    140242   223536   53961

pin         work      pers      clnt      other
in use     113672   0         0         10186

# svmon -G -O unit=GB
Unit: GB
=====
memory      size      inuse     free      pin      virtual  available
pg space    0.50     0         3.16     0.43     0.74     3.13

pin         work      pers      clnt      other
in use     0.30     0         0         0.13

# svmon -G -O unit=auto
Unit: auto
=====
memory      size      inuse     free      pin      virtual  available
pg space    512.00M  5.00M    3.16G    442.86M  758.29M  3.13G

pin         work      pers      clnt      other
in use     305.17M  0K       0K       137.68M
```

## Segment details and -O options

Review the segment details and -O options for the **svmon** command.

Segment details can be added to the user, command, process, and class reports after the summary when the **-O segment=on** or **-O segment=category** option is set to:

- **-O segment=on**, the list of segments is displayed for each entity.
- **-O segment=category**, the segments are grouped into the following three categories for each entity:
  - **system**: used by the system
  - **exclusive**: used only by one entity, except for shared memory (shm) segments

- **shared**: used by two or more entities, except for shared memory (shm) segments

The following table contains the description of the items that the svmon reports for segment information.

Segment type	Segment usage	Description
persistent	log files	IO space mapping
persistent	files and directories	device name : inode number
persistent	large files	large file device name : inode number
mapping	files mapping	mapped to sid source sid no longer mapped
working	data areas of processes and shared memory segments	dependent on the role of the segment based on the VSID and ESID
client	NFS and CD-ROM files	dependent on the role of the segment based on the VSID and ESID
client	JFS2 files	device name: inode number
rmapping	I/O space mapping	dependent on the role of the segment based on the VSID and ESID

When **-O segment=on** or **-O segment=category** is set, additional details can be added:

- **-O range=on**: each segment is followed by the ranges, within the segment, where pages have been allocated.

**Example:**

```
# svmon -P 1 -O range=on
Unit: page
-----
      Pid Command           Inuse   Pin   Pgps Virtual
      1  init                16874  8052   0    16858

      Vsid   Esid Type Description           PSize Inuse Pin Pgps Virtual
      0      0  work kernel segment           m     576 503 0    576
      d802d  d  work shared library text       m     467 0    0    467
      1001   2  work process private           s     98 4    0    98
      1c101d f  work shared library data       s     72 0    0    72
      1a101b 1  clnt code,/dev/hd2:531         s     11 0    -    -
      21023  -  clnt /dev/hd4:1236            s     5  0    -    -
      Addr Range: 0..4
```

- **-O pidlist=on** and **-O pidlist=number**: adds either the list of PIDs of processes or the number of processes using this segment. It also adds either the user name or the command name corresponding to each PID. When the **-@** flag is added, the WPAR name is also added.

**Example:**

```
# svmon -C yes -O pidlist=on
Unit: page
=====
Command           Inuse   Pin   Pgps Virtual
yes                16893  8112   0    16892

      Vsid   Esid Type Description           PSize Inuse Pin Pgps Virtual
      0      0  work kernel segment           m     579 506 0    579
```

```

d802d      System segment
           d work shared library text      m  468  0  0  468
111750    2 work process private           s   18  4  0  18
           pid(s)=348386
e174f     2 work process private           s   18  4  0  18
           pid(s)=340154
131752    2 work process private           s   18  4  0  18
           pid(s)=389352
1c171d    2 work process private           s   18  4  0  18
           pid(s)=360640
81749     f work shared library data             s   17  0  0  17
           pid(s)=340154
71726     f work shared library data             s   17  0  0  17
           pid(s)=360640
101751    f work shared library data             s   17  0  0  17
           pid(s)=348386
121753    f work shared library data             s   17  0  0  17
           pid(s)=389352
a172b     1 clnt code,/dev/hd2:338             s    1  0  -  -
           pid(s)=389352, 360640, 348386, 340154

# svmon -C yes -O pidlist=number
Unit: page
=====
Command      Inuse      Pin      Pgps  Virtual
yes          16893     8112      0     16892

  Vsid      Esid Type Description      PSize Inuse  Pin Pgps Virtual
    0        0 work kernel segment      m    579  506  0    579
           System segment
d802d      d work shared library text      m    468  0  0    468
           Shared library text segment
111750    2 work process private           s    18  4  0    18
           pid number=1
e174f     2 work process private           s    18  4  0    18
           pid number=1
131752    2 work process private           s    18  4  0    18
           pid number=1
1c171d    2 work process private           s    18  4  0    18
           pid number=1
81749     f work shared library data             s    17  0  0    17
           pid number=1
71726     f work shared library data             s    17  0  0    17
           pid number=1
101751    f work shared library data             s    17  0  0    17
           pid number=1
121753    f work shared library data             s    17  0  0    17
           pid number=1
a172b     1 clnt code,/dev/hd2:338             s     1  0  -    -
           pid number=4

```

- **-O filename=on:** Each persistent segment's complete, corresponding file name is shown. Note that because files can be deeply nested, running the **svmon** command with this flag, or with the **-S** and **-i** flags, can take significantly more time.

**Example:**

```

# svmon -P 266414 -O filename=on,format=nolimit
Unit: page
-----
  Pid Command      Inuse      Pin      Pgps  Virtual
266414 IBM.ServiceRmd  17227     8116      0     17174

  Vsid      Esid Type Description      PSize Inuse  Pin Pgps Virtual
    0        0 work kernel segment      m    579  506  0    579
d802d      d work shared library text      m    468  0  0    468
31322     2 work process private           s    202  4  0    202
171316    f work shared library data             s    167  0  0    167
1e133f    - work                               s     52  16  0     52
11320     1 clnt code,/dev/hd2:9929             s     51  0  -     -
           /opt/rsct/bin/IBM.ServiceRmd
b134a     - clnt /dev/hd9var:368                 s     1  0  -     -
           /var/ct/3394394444/registry/local_tree/IBM,ServiceEvent,Class
a134b     - clnt /dev/hd9var:372                 s     1  0  -     -
           /var/ct/3394394444/registry/local_tree/IBM,ServiceEvent,Resources
1341     4 work shared memory segment      s     1  0  0     1
121333    3 mmap maps 2 source(s)             s     0  0  -     -
131312    - clnt /dev/hd9var:360                 s     0  0  -     -

```

```

111310      - c1nt /var/ct/IBM.ServiceRM.stderr
              /dev/hd9var:418          s          0          0          -          -
              /var/ct/3394394444/lck/mc/RMIBM.ServiceRM

```

- **-O mapping=on**: adds information about the source segment and the mapping segment when a segment is used to map another segment. If this option is used, source segments not belonging to the process address space are listed in the report and marked with an asterisk (\*). Note that they are also taken into account in the process-level summary's number calculations.

**Example:**

```

# svmon -P 266414 -O mapping=off
Unit: page
-----
  Pid Command      Inuse   Pin    Pgpsp Virtual
 266414 IBM.ServiceRM  17227   8116     0    17174

# svmon -P 266414 -O mapping=on
Unit: page
-----
  Pid Command      Inuse   Pin    Pgpsp Virtual
 266414 IBM.ServiceRM  17231   8116     0    17174

# svmon -P 266414 -O mapping=on,segment=on
Unit: page
-----
  Pid Command      Inuse   Pin    Pgpsp Virtual
 266414 IBM.ServiceRM  17231   8116     0    17174

  Vsid   Esid Type Description          PSize Inuse Pin Pgpsp Virtual
    0     0 work kernel segment      m    579 506  0    579
  d802d  d work shared library text m    468  0  0    468
 31322   2 work process private  s    202  4  0    202
171316  f work shared library data s    167  0  0    167
1e133f  - work                  s    52  16  0    52
 11320   1 c1nt code,/dev/hd2:9929 s    51  0  -    -
191338 *   - c1nt /dev/hd9var:363 s    3  0  -    -
131332 *   - c1nt /dev/hd9var:361 s    1  0  -    -
 b134a   - c1nt /dev/hd9var:368 s    1  0  -    -
 a134b   - c1nt /dev/hd9var:372 s    1  0  -    -
 1341    4 work shared memory segment s    1  0  0    1
131312  - c1nt /dev/hd9var:360 s    0  0  -    -
121333  3 mmap maps 2 source(s) s    0  0  -    -
          source(s)=131332, 191338
111310  - c1nt /dev/hd9var:418 s    0  0  -    -

```

In these examples, the mapping option adds or removes the mapping source segments which are not in the address space of the process number 266414. There is a difference of four pages (three pages from segment 191338, and one page from segment 131332) in the Inuse consumption between **-O mapping=off** and **-O mapping=on**.

- **-O sortseg=[inuse | pin | pgsp | virtual]**: by default, , all segments are sorted in decreasing order of real memory usage (the Inuse metric) for each entity (user, process, command, segment). Sorting options for the report include the following:
  - Inuse: real memory used
  - Pin: pinned memory used
  - Pgpsp: paging space memory used
  - Virtual: virtual memory used

**Examples:**

```

# svmon -P 1 -O unit=KB,segment=on
Unit: KB
-----
  Pid Command      Inuse   Pin    Pgpsp Virtual
    1  init          67752   32400     0    67688

  Vsid   Esid Type Description          PSize Inuse Pin Pgpsp Virtual
    0     0 work kernel segment      m  37056 32384  0  37056
  d802d  d work shared library text m  29952  0  0  29952
 1001    2 work process private  s   392  16  0   392
1c101d  f work shared library data s   288  0  0   288

```

```

1a101b      1 clnt code,/dev/hd2:531      s      44      0      -      -
21023      - clnt /dev/hd4:1236      s      20      0      -      -

# svmon -P 1 -O unit=KB,segment=on,sortseg=pin
Unit: KB
-----
  Pid Command      Inuse      Pin      Pgpsp  Virtual
  1  init          67752     32400      0     67688

  Vsid      Esid Type Description      PSize Inuse      Pin Pgpsp Virtual
  0          0 work kernel segment      m 37056 32384 0 37056
  1001      2 work process private      s 392 16 0 392
  21023      - clnt /dev/hd4:1236      s 20 0 - -
  d802d      d work shared library text      m 29952 0 0 29952
  1a101b      1 clnt code,/dev/hd2:531      s 44 0 - -
  1c101d      f work shared library data      s 288 0 0 288

```

- **-O mpss=[on | off]**: breaks down the metrics for multiple page size segments, by page size.

**Examples:**

```

# svmon -P 1 -O segment=on,mpss=on
Unit: page
-----
  Pid Command      Inuse      Pin      Pgpsp  Virtual
  1  init          14557     5492      0     14541

  Vsid      Esid Type Description      PSize Inuse      Pin Pgpsp Virtual
  502d      d work shared library text      m 502 0 0 502
  2002      0 work kernel segment      m 396 343 0 396
  10001      2 work process private      s 100 4 0 100
  8019      f work shared library data      m 0 0 0 0
  8019      s 73 0 0 73
  8019      m 0 0 0 0
  6017      1 clnt code,/dev/hd2:532      s 11 0 - -
  e01f      - clnt /dev/hd4:893      s 5 0 - -

```

**sm** pages are separated into **s** and **m** pages. The metrics reported are in the unit of the page size: **s** pages are 4 KB and **m** pages are 64 KB.

- **-O shmid=[on | off]**: displays shared memory IDs associated with shared memory segments. This option does not work you run it in inside a WPAR.

**Examples:**

```

# svmon -P 221326 -O commandline=on,segment=on,shmid=on,filterprop=notempty
Command line : svmon -P 221326 -O commandline=on,segment=on,shmid=on,filterprop=notempty
Unit: page
-----
  Pid Command      Inuse      Pin      Pgpsp  Virtual
  221326 java          20619     6326     9612   27584

  Vsid      Esid Type Description      PSize Inuse      Pin Pgpsp Virtual
  502d      d work text or shared-lib code seg m 585 0 1 585
  0          0 work kernel segment      m 443 393 4 444
  14345      3 work working storage      sm 2877 0 7865 9064
  15364      e work shared memory segment      sm 1082 0 1473 1641
  15364      shmid:3
  1b36a      f work working storage      sm 105 0 106 238
  17386      - work      s 100 34 64 146
  1a38b      2 work process private      sm 7 4 24 31

```

## Additional -O options

Review the additional -O options for the **svmon** command.

The following additional options are:

- **-O process=on**: adds, for a given entity, the memory statistics of the processes belonging to the entity (user name or command name). If you specify the **-@** flag, each process report is followed by a line that shows the WPAR name. This option is only valid for the User and the Command reports.

All reports containing two or more entities can be filtered and/or sorted with the following options:

- **-O sortentity=[inuse | ...]**: specifies the summary metric used to sort the entities (process, user, and so on) when several entities are printed in a report.

The list of metrics permitted in the report depend on the type of summary (**-O** summary option) chosen. Any of the metrics used in a summary can be used as a sort key.

#### Examples:

```
# svmon -P -t 5 -O summary=off -O segment=off -O sortentity=pin
Command line : svmon -P -t 5 -O summary=off -O segment=off -O sortentity=pin
Unit: page
-----
  Pid Command      Inuse   Pin    Pgps Virtual
127044 dog           9443   8194     0    9443
   0  swapper       9360   8176     0    9360
  8196 wait         9360   8176     0    9360
 53274 wait         9360   8176     0    9360
237700 rpc.lockd      9580   8171     0    9580
```

- **-O filtercat=[off | exclusive | kernel | shared | unused | unattached]**: this option filters the output by segment category. You can specify more than one filter at a time.

**Note:** Use the **unattached** filter value with the **-S** report because unattached segments cannot be owned by a process or command.

#### Examples:

```
# svmon -P 1 -O unit=KB,segment=on,sortseg=pin,filtercat=off
Unit: KB
-----
  Pid Command      Inuse   Pin    Pgps Virtual
   1  init           58684  28348     0    58616

  Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
   0     0  work kernel segment      s  30948 28332  0  30948
 6902f   2  work process private    s   396   16   0   396
 6c10d   d  work shared library text s 26996   0   0 26996
 a9017   f  work shared library data s   276   0   0  276
 b9015   1  clnt code,/dev/hd2:531 s    44   0   -   -
 f101c   -  clnt /dev/hd4:824        s    24   0   -   -
```

```
# svmon -P 1 -O unit=KB,segment=on,sortseg=pin,filtercat=shared
Unit: KB
-----
  Pid Command      Inuse   Pin    Pgps Virtual
   1  init           58684  28348     0    58616

  Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
 6c10d   d  work shared library text s 26996   0   0 26996
 a9017   f  work shared library data s   276   0   0  276
```

- **-O filtertype=[off | working | persistent | client]**: this option allows you to filter on the **Type** column of the segment details. You can specify more than one filter at a time.

#### Examples:

```
# svmon -P 495618 -O segment=on,filtertype=client
Unit:page
-----
  Pid Command      Inuse   Pin    Pgps Virtual
495618 IBM.AuditRmd    308     0     0     0

  Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
1619f7   -  clnt /dev/fslv07:417    s   253   0   -   -
 31382   1  clnt code,/dev/hd2:9803 s    36   0   -   -
1319f2   -  clnt /dev/fslv07:400    s    16   0   -   -
1a19db   -  clnt /dev/fslv07:399    s     1   0   -   -
 a19cb   -  clnt /dev/fslv07:397    s     1   0   -   -
 919c8   -  clnt /dev/fslv07:398    s     1   0   -   -
 519c4   -  clnt /dev/fslv07:358    s     0   0   -   -
1f19de   -  clnt /dev/fslv07:325    s     0   0   -   -
```

Only the **client** segments for process number 495618 are displayed. Note that the summary only reports the sum of the metrics displayed in the entity details. This means that the summary numbers shown here do not represent the complete memory consumption for this process, only its consumption using client segments.

• **-O filterprop=[off | notempty | data | text]:**

This option allows filtering on the segment property:

- **Data:** Computational segments consisting of the pages belonging to working-storage segments or program text (executable files) segments.
- **Text:** Non-computational segments of *File memory* (or file pages), which are the remaining pages. These pages are usually from permanent data files in persistent storage.
- **Notempty:** Segments where the Inuse value is not 0.

You can specify more than one property at a time.

**Examples:**

```
# svmon -C yes -O segment=category,filterprop=notempty

Unit: page
=====
Command          Inuse   Pin   Pgps  Virtual
yes              16256  6300   80   16271
.....
SYSTEM segments  Inuse   Pin   Pgps  Virtual
                  7088   6288   64   7104
.....
      Vsid      Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
      0         0  work kernel segment          m     443   393  4    444
.....
EXCLUSIVE segments  Inuse   Pin   Pgps  Virtual
                  112    12    0     111
.....
      Vsid      Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
      851d      2  work process private      sm     19     4  0     19
      e6fb      2  work process private      sm     19     4  0     19
      1940f     2  work process private      sm     19     4  0     19
      1017      f  work shared library data    sm     18     0  0     18
      6f73      f  work shared library data    sm     18     0  0     18
      4a71      f  work shared library data    sm     18     0  0     18
      24626     1  clnt code,/dev/hd2:338      s      1     0  -     -
.....
SHARED segments    Inuse   Pin   Pgps  Virtual
                  9056   0     16   9056
.....
      Vsid      Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
      502d      d  work shared library text    m     566   0    1    566

# svmon -C yes -O segment=category,filterprop=text

Unit: page
=====
Command          Inuse   Pin   Pgps  Virtual
yes              1       0     0     0
.....
EXCLUSIVE segments  Inuse   Pin   Pgps  Virtual
                  1       0     0     0
.....
      Vsid      Esid Type Description          PSize  Inuse   Pin Pgps  Virtual
      24626     1  clnt code,/dev/hd2:338      s      1     0  -     -

# svmon -C yes -O segment=category,filterprop=data

Unit: page
=====
Command          Inuse   Pin   Pgps  Virtual
yes              16255  6300   80   16271
.....
SYSTEM segments    Inuse   Pin   Pgps  Virtual
                  7088   6288   64   7104
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
0	0	work	kernel segment	m	443	393	4	444
EXCLUSIVE segments				Inuse	Pin	Pgsp	Virtual	
				111	12	0	111	
Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
e6fb	2	work	process private	sm	19	4	0	19
851d	2	work	process private	sm	19	4	0	19
1940f	2	work	process private	sm	19	4	0	19
4a71	f	work	shared library data	sm	18	0	0	18
1017	f	work	shared library data	sm	18	0	0	18
6f73	f	work	shared library data	sm	18	0	0	18
SHARED segments				Inuse	Pin	Pgsp	Virtual	
				9056	0	16	9056	
Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	shared library text	m	566	0	1	566

- **-O filterpgsz=[off | s m | L | S]**: this option filters the segment based on their page size. Multiple page size segments can be selected using multiple code letters in the form <min\_size><max\_size>. **-O filterpgsz="sm s"** filters the small page segments and the multiple page size segments with small and medium pages.

For the **-P** report however, the behavior is slightly different. Indeed, the report contains all the processes having at least one page of the size specified with the **-O filterpgsz** option, and for these processes, svmon displays all their segments (whatever their page size).

**Examples:**

```
# svmon -P -O segment=on,filterpgsz=L
Unit: page
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
270450	ptxtst_shm_al	21674	17136	0	21658

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
10002	0	work	kernel segment	m	607	556	0	607
1b9b35	70000000	work	default shmat/mmap	L	2	2	0	2
28005	9ffffffd	work	shared library	s	1767	0	0	1767
188030	90000000	work	shared library text	m	110	0	0	110
1010a2	90020014	work	shared library	s	114	0	0	114
209b43	f00000002	work	process private	m	5	3	0	5
3c107a	9fffffff	clnt	USLA text,/dev/hd2:2774	s	13	0	-	-
7000e	9ffffffe	work	shared library	s	11	0	0	11
21b06	9001000a	work	shared library data	s	11	0	0	11
241b4a	80020014	work	USLA heap	s	5	0	0	5
281b52	8fffffff	work	private load data	s	4	0	0	4
131a24	10	clnt	text data BSS heap, /dev/hd2:2745	s	3	0	-	-
2a1b56	11	work	text data BSS heap	s	1	0	0	1
159a29	fffffff	work	application stack	s	1	0	0	1

Pid	Command	Inuse	Pin	Pgsp	Virtual
266262	ptxtst_shm_al	17578	13040	0	17562

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
10002	0	work	kernel segment	m	607	556	0	607
119ba1	70000000	work	default shmat/mmap	L	1	1	0	1
28005	9ffffffd	work	shared library	s	1767	0	0	1767
188030	90000000	work	shared library text	m	110	0	0	110
1010a2	90020014	work	shared library	s	114	0	0	114
3e19fe	f00000002	work	process private	m	5	3	0	5
3c107a	9fffffff	clnt	USLA text,/dev/hd2:2774	s	13	0	-	-
7000e	9ffffffe	work	shared library	s	11	0	0	11
c1a1a	9001000a	work	shared library data	s	11	0	0	11
2a9a57	80020014	work	USLA heap	s	5	0	0	5
149b2b	8fffffff	work	private load data	s	4	0	0	4
131a24	10	clnt	text data BSS heap, /dev/hd2:2745	s	3	0	-	-
1f9b3d	fffffff	work	application stack	s	1	0	0	1
2b1b54	11	work	text data BSS heap	s	1	0	0	1

Addr Range: 0..3012

In this example, all processes running large pages are reported. For these processes, all segments are displayed whatever their page size.

```
# svmon -U root -O filterpgsz=L,segment=on
Unit: page
=====
User          Inuse      Pin      Pgsz  Virtual
root          12288     12288     0     12288

  Vsid      Esid Type Description          PSize  Inuse  Pin  Pgsz  Virtual
1b9b35    70000000 work default shmat/mmap      L       2    2    0     2
119ba1    70000000 work default shmat/mmap      L       1    1    0     1
```

```
# svmon -C ptxtst_shm_alt_pgsz -O filterpgsz=L,segment=on
Unit: page
=====
Command          Inuse      Pin      Pgsz  Virtual
ptxtst_shm_alt_pgsz 12288     12288     0     12288

  Vsid      Esid Type Description          PSize  Inuse  Pin  Pgsz  Virtual
1b9b35    70000000 work default shmat/mmap      L       2    2    0     2
119ba1    70000000 work default shmat/mmap      L       1    1    0     1
```

The previous two examples illustrate the difference of behavior with *-P*. In these examples, for the given entity, only the pages of the given size are kept in the report.

## Reports details

Review the output for the **svmon** command reports.

To display compact report of memory expansion information (in a system with Active Memory Expansion enabled), enter:

```
# svmon -G -O summary=longame
```

```
Unit: page
-----
-----
Active Memory Expansion
-----
-----
Size      Inuse      Free      DXMSz     UCMInuse   CMInuse     TMSz     TMFr
CPSz
262144    152625     43055     67640     98217     54408     131072   6787
26068

CPFr    txf     cxf     CR
3888    2.00    1.48    2.45
```

## Global report

To print the Global report, specify the **-G** flag. The Global report displays a system-wide detailed real memory view of the machine. This report contains various summaries, only the memory and inuse summaries are always displayed.

When the **-O summary** option is not used, or when it is set to **-O summary=basic**, the column headings used in global reports summaries are:

### memory

Specifies statistics describing the use of memory, including:

#### size

Number of frames (size of real memory)

**Tip:** This does not include the free frames that have been made unusable by the memory sizing tool, the `rmss` command.

**inuse**

Number of frames containing pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools, even if they are not used.

**free**

Number of frames free in all memory pools. There may be more memory available depending on the file cache (see: available)

**pin**

Number of frames containing pinned pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools.

**virtual**

Number of pages allocated in the system virtual space

**available**

Amount of memory available for computational data. This metric is calculated based on the size of the file cache and the amount of free memory.

**stolen**

Displayed only when rmss runs on the machine. Number of frames stolen by **rmss** and marked unusable by the VMM

**mmode**

Indicates the memory mode the system is running.

Following are the current possible values for mmode.

**Ded**

Neither Active Memory Sharing nor Active Memory Expansion is enabled.

**Shar**

Only Active Memory Sharing is enabled, Expansion is not enabled.

**Ded-E**

Active Memory Sharing is not enabled but Expansion is enabled.

**Shar-E**

Both Active Memory Sharing & Active Memory Expansion are enabled.

**ucomprsd**

This gives a breakdown of expanded memory statistics in the uncompressed pool, including: **inuse** Number of uncompressed pages that are in use.

**comprsd**

This gives a breakdown of expanded memory statistics in the compressed pool, including: **inuse** Number of compressed pages in the compressed pool.

**pg space**

Specifies statistics describing the use of paging space.

**size**

Size of paging space

**inuse**

Number of paging space pages used

**ucomprsd**

This gives a breakdown of expanded memory statistics of working pages in the uncompressed pool, including: **inuse** Number of compressed pages in the compressed pool.

**comprsd**

This gives a breakdown of expanded memory statistics of working pages in the compressed pool, including: **inuse** Number of compressed pages in the compressed pool.

## **Pin**

Specifies statistics on the subset of real memory containing pinned pages, including:

### **work**

Number of frames containing working segment in use pages

### **pers**

Number of frames containing persistent segment in use pages

### **clnt**

Number of frames containing client segment in use pages

### **other**

Number of frames containing all memory pages that do not use segment control blocks. Examples for these memory pages are physical to virtual page tables (PVT), physical to virtual page lists (PVLIST), and kernel special purpose (KSP) region.

## **in use**

Specifies statistics on the subset of real memory in use, including:

### **work**

Number of frames containing working segment in use pages

### **pers**

Number of frames containing persistent segment in use pages

### **clnt**

Number of frames containing client segment in use pages

## **ucomprsd**

This gives a breakdown of expanded memory statistics of working pages in the uncompressed pool, including: **inuse** Number of uncompressed pages in the compressed pool.

## **comprsd**

This gives a breakdown of expanded memory statistics of working pages in the compressed pool, including: **inuse** Number of compressed pages in the compressed pool.

## **PageSize**

Displayed only if alternative page sizes (non-4KB) are available on the system and the option **-O pgsz=on** is set. It displays separate sets of statistics for each of the page sizes available on the system.

### **PageSize**

Page size for the following statistics

### **PoolSize**

Number of pages in the pool for a page size using reserved pools (such as the 16 MB page pool)

### **inuse**

Number of pages of this size that are used

### **pgsp**

Number of pages of this size that are allocated in the paging space

### **pin**

Number of pinned pages of this size

### **virtual**

Number of pages of this size that are allocated in the system virtual space

### **ucomprsd**

Number of pages of this size that are in uncompressed form.

## **Domain affinity**

Displays statistics per affinity domain. This is activated by the **-O affinity=on** option.

### **total**

Total memory in this affinity domain.

### **used**

Total memory used in this affinity domain.

**free**

Total remaining free memory in this affinity domain

**lcpus**

List of logical cpus in this affinity domain.

**Note:** The **ucomprsd** and **comprsd** metrics are available only in systems with Active Memory Expansion enabled. **-O summary=ame** option is needed to show these expanded memory statistics.

When the **-O summary=ame** option is used in a system with Active Memory Expansion enabled, the following memory information (true memory snapshot) is displayed in the global report summary at the end of the regular report.

**True Memory**

True memory size.

**ucomprsd**

Displays detailed information about the uncompressed pool, including

**CurSz**

Current size of the uncompressed pool.

**%Cur**

Percentage of true memory used by the uncompressed pool

**TgtSz**

Target size of the uncompressed pool needed to achieve the target memory expansion factor.

**% Tgt**

Percentage of true memory that will be used by the uncompressed pool when the target memory expansion factor is achieved.

**comprsd**

Displays detailed information about the compressed pool, including:

**CurSz**

Current size of the compressed pool

**%Cur**

Percentage of true memory used by the compressed pool.

**TgtSz**

Target size of the compressed pool needed to achieve the target memory expansion factor.

**% Tgt**

Percentage of true memory that will be used by the compressed pool when the target memory expansion factor is achieved

**% Max**

Percentage of true memory that will be used by the compressed pool when the compressed pool achieves maximum size.

**CRatio**

Compression ratio

**AME**

Displays the following information

**txf**

Target Memory Expansion Factor

**cxf**

Current Memory Expansion Factor

**dxm**

Deficit factor to reach the target expansion factor

**dxm**

Deficit memory to reach the target expansion

**Note:** The above true memory section of expanded memory statistics can be turned off using the option **-O tmem=off**.

When the **-O summary=longreal** option is set with **-G**, the compact report header contains the following metrics:

**Size**

Number of frames (size of real memory)

**Tip:** This includes any free frames that have been made unusable by the memory sizing tool, the `rmss` command.

**Inuse**

Number of frames containing pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools.

**Free**

Number of frames free in all memory pools. There may be more memory available depending on the file cache (see: available)

**Pin**

Number of frames containing pinned pages

**Tip:** On a system where a reserved pool is defined (such as the 16 MB page pool), this value includes the frames reserved for any of these reserved pools.

**Virtual**

Number of pages allocated in the system virtual space

**Available**

Amount of memory available for computational data. This metric is calculated based on the size of the file cache and the amount of free memory.

**Pgsp**

Number of pages allocated in the paging space

When **-G** is used in conjunction with **-@** the following additional column is displayed:

**WPAR**

WPAR name

**Note:**

- If you specify the **-@** flag without a list, the flag has no effect except when the **-O summary** option is used, then the WPAR name is added in the last column.  
If a list is provided after the **-@** flag, the **svmon** command report includes one section per WPAR listed. If **ALL** is specified, a system-wide and a global section will also be present. Any metric not available on a per WPAR basis is either replaced by the corresponding global value (in the case of **-@ WparList**) or by a "-" (in the case of **-@ ALL**).
- Global values are displayed instead of a per WPAR metrics. They are flagged by the presence of a **@** in the report.
- Some of the metrics are only available on a per WPAR basis if the **WLM** is used to restrict the WPAR memory usage.

When the **-O summary=longame** option is set with **-G**, the compact report header contains the following Active Memory Expansion metrics

**Size**

Expanded memory size

**Inuse**

Number of pages in use (expanded form).

**Free**

Size of freelist (expanded form).

**DXMSz**

Deficit memory to reach the target memory expansion

**UCMInuse**

Number of uncompressed pages in use.

**CMInuse**

Number of compressed pages in the compressed pool.

**TMSz**

True memory size

**TMFr**

True number of free page frames

**CPSz**

Size of Compressed pool.

**CPFr**

Size of Uncompressed pool.

**txf**

Target Memory Expansion Factor

**cxr**

Current Memory Expansion Factor

**CR**

Compression Ratio.

**Examples**

- To display the default svmon report, with automatic unit selection, enter:

```
# svmon -O summary=basic,unit=auto,pgsz=on
```

or

```
# svmon -G -O unit=auto,pgsz=on
```

```
Unit: auto
-----
```

	size	inuse	free	pin	virtual	available
memory	31.0G	2.85G	28.1G	1.65G	2.65G	27.3G
pg space	512.00M	13.4M				
	work	pers	clnt	other		
pin	688.57M	0K	0K	924.95M		
in use	2.65G	0K	124.55M			
PageSize	PoolSize	inuse	pgsp	pin	virtual	
s 4 KB	-	2.41G	13.4M	1.34G	2.29G	
m 64 KB	-	376.81M	0K	241.81M	376.81M	
L 16 MB	5	0K	0K	80.0M	0K	

The memory size of the system is 31GB. This size is split into the in-used frames for 2.85 GB and into the free frames for 28.1 GB. 1.65 GB are pinned in memory, 2.65 GB are allocated in the system virtual space and 27.3 GB are available to be used as computational data by new processes.

The inuse and pin values include the pages reserved for the 16 MB page memory pool (80 MB).

The size of the paging space is 512 MB, where 13.4 MB are used.

The pinned frames (1.65 GB) is composed of working segment pinned pages (688.57 MB) and 924.95 MB of other pin pages (can be used by the kernel for example), not counting the memory not used but pinned by the 16 MB page pool.

The number of frames containing pages (2.85 GB) is composed of working segment pages (2.65 GB) and client segment pages (124.55 MB), not counting the memory that is only reserved but counted inuse from the 16 MB pool.

Then statistics are displayed for each page size available on the system. For instance, the 16 MB page pool is composed of 5 pages of 16 MB. None of these are used, none are in the paging space (since they are all pinned), all of these are pinned, and none are in the system's virtual space.

- To also display the affinity domain information, enter:

```
# svmon -G -O unit=MB,pgsz=on,affinity=on
```

```
Unit: MB
-----
```

	size	inuse	free	pin	virtual	available
memory	31744.00	3055.36	28688.64	1838.84	2859.78	27911.33
pg space	512.00	14.7				
	work	pers	clnt	other		
pin	833.90	0	0	924.95		
in use	2859.78	0	163.59			
PageSize	PoolSize	inuse	pgsp	pin	virtual	
s 4 KB	-	1628.93	14.7	1291.47	1465.34	
m 64 KB	-	1346.44	0	467.38	1346.44	
L 16 MB	5	48.0	0	80.0	48.0	
Domain affinity		free	used	total	lcpus	
	0	14131.05	1475.13	15606.18	0 1 2 3	
	1	14589.65	1538.35	16128.00	4 5 6 7	

In this example taken on a dedicated LPAR partition, we added the domain affinity metrics. The 31744 MB of memory are split into 2 memory affinity domain:

- The domain 0 contains 15606.18 MB of memory with 1475.13 MB used, and 14131.05 MB free.
- The domain 1 contains 16128 MB of memory with 1538.35 MB used and 14589.65 MB free.

- To display detailed affinity domain information, enter:

```
# svmon -G -O unit=MB,pgsz=on,affinity=detail
```

```
Unit: MB
-----
```

	size	inuse	free	pin	virtual	available
memory	31744.00	3055.70	28688.30	1838.91	2860.11	27910.99
pg space	512.00	14.7				
	work	pers	clnt	other		
pin	833.96	0	0	924.95		
in use	2860.11	0	163.58			
PageSize	PoolSize	inuse	pgsp	pin	virtual	
s 4 KB	-	1629.26	14.7	1291.47	1465.68	
	Domain affinity	used				
	0	129735				
	1	44909				
m 64 KB	-	1346.44	0	467.44	1346.44	
	Domain affinity	used				
	0	12432				
	1	8512				
L 16 MB	5	48.0	0	80.0	48.0	
	Domain affinity	used				
	0	4096				
	1	8192				
Domain affinity		free	used	total	lcpus	
	0	14131.05	1475.13	15606.18	0 1 2 3	
	1	14589.65	1538.35	16128.00	4 5 6 7	

In this example, we can see that the breakdown by affinity domain is also shown in the per-page size report. This option takes some time to execute.

- On a shared partition, attempting to display affinity domain information, results in:

```
# svmon -G -O unit=MB,pgsz=on,affinity=on
```

```
Unit: MB
-----
```

memory	size	inuse	free	pin	virtual	available
pg space	4096.00	811.59	3284.41	421.71	715.08	3248.66
	512.00	6.23				
pin	work	pers	clnt	other		
in use	284.02	0	0	137.68		
	715.08	0	96.5			
PageSize	PoolSize	inuse	pgsp	pin	virtual	
s	4 KB	-	6.23	288.77	410.27	
m	64 KB	-	0	132.94	304.81	
Domain affinity	free	used	total	lcpus		
	*** not supported	in shared	pools	***		

Memory affinity domains only have meaning for dedicated partitions.

- To display the one line global report, enter:

```
# svmon -O summary=longreal
```

```
Unit: page
-----
Memory
-----
Size      Inuse    Free     Pin      Virtual  Available  Pgpsp
262144    187219  74925   82515   149067  101251    131072
```

The metrics reported here are identical to the metrics in the basic format. There is a memory size of 262144 frames with 187219 frames inuse and 74925 remaining frames. 149067 pages are allocated in the virtual memory and 101251 frames are available.

- To display global memory statistics in MB units at interval, enter:

```
# svmon -G -O unit=MB,summary=shortreal -i 60 5
```

```
Unit: MB
-----
Size      Inuse    Free     Pin      Virtual  Available  Pgpsp
1024.00   709.69  314.31  320.89  590.74  387.95    512.00
1024.00   711.55  312.39  320.94  592.60  386.02    512.00
1024.00   749.10  274.89  322.89  630.15  348.53    512.00
1024.00   728.08  295.93  324.57  609.11  369.57    512.00
1024.00   716.79  307.21  325.66  597.50  381.16    512.00
```

This example shows how to monitor the whole system by taking a memory snapshot every 60 seconds for 5 minutes.

- To display detailed memory expansion information (in a system with Active Memory Expansion enabled), enter:

```
# svmon -G -O summary=ame
```

```
Unit: page
-----
memory    size    inuse    free     pin      virtual  available  mmode
ucomprsd -      98216   -         -         154779   41340     Ded-E
comprsd  -      54403   -         -         -        -         -
pg space 131072  1212    -         -         -        -         -

pin      work    pers     clnt     other
in use  66195  0        0        7538
ucomprsd 93428
comprsd  54403
-----
True Memory: 131072

CurSz  %Cur  TgtSz  %Tgt  MaxSz  %Max  CRatio
ucomprsd 105004 80.11 37450 28.57 -      -
comprsd  26068 19.89 93622 71.43 45308 34.57 2.45
```

	txf	cxf	dx	dxm
AME	2.00	1.48	0.52	67641

- To display memory expansion information with true memory snapshot turned-off (in a system with Active Memory Expansion enabled), enter:

```
# svmon -G -O summary=ame,tmem=off
```

```
Unit: page
-----
```

	size	inuse	free	pin	virtual	available	mmode
memory	262144	152619	43061	73733	154779	41340	Ded-E
ucomprsd	-	98216	-				
comprsd	-	54403	-				
pg space	131072	1212					
	work	pers	clnt	other			
pin	66195	0	0	7538			
in use	147831	0	4788				
ucomprsd	93428						
comprsd	54403						

## User report

The User report displays the memory usage statistics for all specified login name or when no argument is specified for all users.

To print the user report, specify the **-U** flag. This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

### User

Indicates the user name

If processes owned by this user use pages of a size other than the base 4 KB page size, and the **-O pgsz=on** option is set, these statistics are followed by breakdown statistics for each page size. The metrics reported in this per-page size summary are reported in the page size unit by default.

### Note:

- If you specify the **-@** flag without an argument, these statistics will be followed by the users assignments to WPARs. This information is shown with an additional WPAR column displaying the WPAR name where the user was found.
- If you specify the **-O activeusers=on** option, users which do not use memory (Inuse memory is 0 page) are not shown in the report.

### Examples

- To display per user memory consumption statistics, enter:

```
# svmon -U
```

```
Unit: page
=====
```

User	Inuse	Pin	Pgsp	Virtual
root	56007	16070	0	54032
daemon	14864	7093	0	14848
guest	14705	7087	0	14632
bin	0	0	0	0
sys	0	0	0	0
adm	0	0	0	0
uucp	0	0	0	0
nobody	0	0	0	0

This command gives a summary of all the users using memory on the system. This report uses the default sorting key: the Inuse column. Since no **-O** option was specified, the default unit (page) is used. Each page is 4 KB.

The Inuse column, which is the total number of pages in real memory from segments that are used by all the processes of the *root* user, shows 56007 pages. The Pin column, which is the total number of

pages pinned from segments that are used by all the processes of the *root* user, shows 16070 pages. The *Pgsp* column, which is the total number of paging-space pages that are used by all the processes of the *root* user, shows 0 pages. The *Virtual* column (total number of pages in the process virtual space) shows 54032 pages for the *root* user.

2. To display per WPAR per active user memory consumption statistics, enter:

```
# svmon -U -O summary=basic,activeusers=on -@ ALL
```

```
Unit: auto
#####
##### WPAR : Global
#####
=====
User                Inuse      Pin       Pgsp      Virtual
root                155.49M   49.0M    0K        149.99M
daemon              69.0M     34.8M    0K         68.9M
#####
##### WPAR : wp0
#####
=====
User                Inuse      Pin       Pgsp      Virtual
root                100.20M   35.4M    0K         96.4M
#####
##### WPAR : wp1
#####
=====
User                Inuse      Pin       Pgsp      Virtual
root                100.20M   35.4M    0K         96.4M
#####
##### WPAR : wp2
#####
=====
User                Inuse      Pin       Pgsp      Virtual
root                100.14M   35.4M    0K         96.3M
```

In this case, we run in each WPAR context and we want some details about every users in all the WPARs running on the system. Since there are users that are not active, we want to keep only the active user by adding the **-O activeusers=on** option on the command line. Each WPAR has a root user, which in this example consumes the same amount of memory since each one runs the exact same list of processes. The root user of the Global WPAR uses more memory since more processes are running in the Global than in a WPAR.

## Command report

The Command report displays the memory usage statistics for the specified command names. To print the command report, specify the **-C** flag.

This report contains all the columns detailed in the common summary metrics as well as its own defined here:

### Command

Indicates the command name.

If processes running this command use pages of size other than the base 4KB page size, and the **-O pgsz=on** option is set, these statistics are followed by breakdown statistics for each page size. The metrics reported in this per-page size summary are reported in the page size unit by default.

### Examples:

1. To display memory statistics about the *yes* command, with breakdown by process and categorized detailed statistics by segment, enter:

```
# svmon -C yes -O summary=basic,pidlist=on,segment=category,process=on
```

```
Unit: page
=====
```

```

Command
yes
-----
      Pid Command          Inuse   Pin   Pgps Virtual
      217132 yes            14405 5492   0    14404
      397448 yes            14405 5492   0    14404
      372980 yes            14405 5492   0    14404
-----
SYSTEM segments
-----
      Inuse   Pin   Pgps Virtual
      6336   5488   0    6336

Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
2002   0 work kernel segment          m    396   343  0    396
-----
EXCLUSIVE segments
-----
      Inuse   Pin   Pgps Virtual
      37      4      0      36

Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
711    2 work process private          sm    19    4    0    19
126a3  f work shared library data      sm    17    0    0    17
1b70a  1 clnt code,/dev/hd2:338        s     1     0    -    -
-----
SHARED segments
-----
      Inuse   Pin   Pgps Virtual
      8032   0      0      8032

Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
502d   d work shared library text      m    502   0    0    502
      Shared library text segment

```

In this example, we are looking at the `yes` command. The report is divided in several sub-reports. The summary line for the command displays the Inuse memory, the Pin pages in memory, the paging space and virtual pages used by the command. The **-O process=on** option adds the process section, where we have the list of the processes for this command.

2. To display memory statistics about the `yes` command, with breakdown by process and statistics by segment including file names, enter:

```
# svmon -C yes -O summary=basic,segment=on,pidlist=on,filename=on
```

```

Unit: page
=====
Command
yes
-----
      Vsid   Esid Type Description          PSize Inuse   Pin Pgps Virtual
      502d   d work shared library text      m    502   0    0    502
      Shared library text segment
      2002   0 work kernel segment          m    396   343  0    396
      System segment
      13722  2 work process private          sm    19    4    0    19
      pid(s)=397566
      1a72b  f work shared library data      sm    17    0    0    17
      pid(s)=397566
      1b70a  1 clnt code,/dev/hd2:338        s     1     0    -    -
      /usr/bin/yes
      pid(s)=397566, 295038, 217212

```

This report displays for each segment its list of pids when the segment is in a process address space. It also displays the filename of all client and persistent segments.

3. To display memory statistics about the `init` command, with breakdown by process, enter:

```
# svmon -@ -C init -O commandline=on,segment=off,process=on
```

```

# svmon -@ -C init -O commandline=on,segment=off,process=on
Command line : svmon -@ -C init -O commandline=on,segment=off,process=on
Unit: page
=====
Command
init
-----
      Pid Command          Inuse   Pin   Pgps Virtual
      1 init            18494  8900   0    18477

```

```

WPAR=Global
159976  init          18484    8900     0    18469
        WPAR=wp1
233722  init          18484    8900     0    18469
        WPAR=wp2
180562  init          18484    8900     0    18469
        WPAR=wp0
-----

```

In a WPAR context, the **-@** flag combined with the **-O process=on** flag, adds WPAR information in the report. This example shows which init process belongs to which WPAR.

## Process report

The process report displays the memory usage statistics for all or the specified process names. To print the process report, specify the **-P** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

### Pid

Indicates the process ID.

### Command

Indicates the command the process is running.

If processes use pages of size other than the base 4KB page size, and the **-O pgsz=on** option is set, these statistics are followed by breakdown statistics for each page size. The metrics reported in this per-page size summary are reported in the page size unit by default.

After process information is displayed, **svmon** displays information about all the segments that the process used. Information about segments are described in the paragraph **Segment Report**.

### Note:

- If you specify the **-@** flag, the **svmon** command displays two additional lines that show the virtual pid and the WPAR name of the process. If the virtual pid is not valid, a dash sign (-) is displayed.
- The **-O affinity** flag supported by the **-P** option, gives details on domain affinity for the process when set to **on** and for each of the segments when set to **detail**. Note that the Memory affinity information is not available for the shared partitions.

### Examples:

1. To display the top 10 list of processes in terms of real memory usage in KB unit, enter:

```
# svmon -P -O unit=KB,summary=basic,sortentity=inuse -t 10
```

```

Unit: KB
-----
  Pid Command          Inuse    Pin    Pgsz  Virtual
344254 java             119792  22104    0    102336
209034 xmwlm             68612   21968    0     68256
262298 IBM.CSMAgentR    60852   22032    0     60172
270482 rmcld             60844   21996    0     60172
336038 IBM.ServiceRM   59588   22032    0     59344
225432 IBM.DRMd         59408   22040    0     59284
204900 sendmail          59240   21968    0     58532
266378 rpc.statd       59000   21980    0     58936
168062 snmpdv3ne        58700   21968    0     58508
131200 errdemon         58496   21968    0     58108

```

This example gives the top 10 processes consuming the most real memory. The report is sorted by the **inuse** count, 119792 KB for the **java** process, 68612 KB for the **xmwlm** daemon and so on. The other metrics are: KB pinned in memory, KB of paging space and virtual memory.

2. To display information about all the non empty segments of a process, enter:

```
# svmon -P 221326 -O cmdline=on,segment=on,filterprop=notempty
```

```
Command line : svmon -P 221326 -O cmdline=on,segment=on,filterprop=notempty
Unit: page
```

---

Pid	Command	Inuse	Pin	Pgsp	Virtual
221326	java	20619	6326	9612	27584

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	text or shared-lib code	seg m	585	0	1	585
0	0	work	kernel segment	m	443	393	4	444
14345	3	work	working storage	sm	2877	0	7865	9064
15364	e	work	shared memory segment	sm	1082	0	1473	1641
1b36a	f	work	working storage	sm	105	0	106	238
17386	-	work		s	100	34	64	146
1a38b	2	work	process private	sm	7	4	24	31

The detailed section displays information about each non empty segment used by process 221326. This includes the *virtual*, *Vsid*, and effective, *Esid*, segment identifiers. The type of the segment is also displayed along with its description that consists of a textual description of the segment, including the volume name and i-node of the file for persistent segments.

The report also details the size of the pages the segment is backed by (Psize column), where **s** denotes 4 KB pages and **L** denotes 16 MB pages, and **sm** a multi size page (small and medium page in this case) the number of pages in memory (Inuse column), the number of pinned pages (Pin column), the number of pages used in the paging space (Pgsp column), and the number of virtual pages (Virtual column).

- To display information about all the non empty segments used by a process, including the corresponding shared memory ids and affinity domain data, enter:

```
# svmon -P 221326 -O
cmdline=on,segment=on,affinity=on,shmid=on,filterprop=notempty
```

```
Command line : svmon -P 221326 -O
cmdline=on,segment=on,affinity=on,shmid=on,filterprop=notempty
Unit: page
```

---

Pid	Command	Inuse	Pin	Pgsp	Virtual
221326	java	20619	6326	9612	27584
		Domain affinity	0	Npages	
			1	29345	
				11356	

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	text or shared-lib code	seg m	585	0	1	585
			Domain affinity	Npages				
				0				
				1				
0	0	work	kernel segment	m	443	393	4	444
			Domain affinity	Npages				
				0				
				1				
14345	3	work	working storage	sm	2877	0	7865	9064
			Domain affinity	Npages				
				0				
				1				
15364	e	work	shared memory segment	sm	1082	0	1473	1641
			shmid:3					
			Domain affinity	Npages				
				0				
				1				
1b36a	f	work	working storage	sm	105	0	106	238
			Domain affinity	Npages				
				0				
				1				
17386	-	work		s	100	34	64	146
			Domain affinity	Npages				
				0				
				1				
1a38b	2	work	process private	sm	7	4	24	31
			Domain affinity	Npages				
				0				
				1				

The detailed section displays the list of all segments used by the process 221326. In this case, the **-O affinity=detail** option adds for each VsId, the Domain affinity breakdown. The VsId 15364 also shows the shared memory id (shmid: 3 in this case). This information can be matched with the results given by the **ipcs** command.

- To display memory statistics in the legacy format which includes a breakdown by segments, enter:

```
$ svmon -P 209034 -O segment=on
```

```
Unit: page
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
209034	xmwl	15978	5492	0	15929

VsId	EsId	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	shared library text	m	495	0	0	495
2002	0	work	kernel segment	m	396	343	0	396
19288	c	work	shared memory segment	sm	1477	0	0	1477
b27a	f	work	shared library data	sm	106	0	0	106
d27c	2	work	process private	sm	90	4	0	90
1b24a	-	clnt	/dev/hd4:15493	s	22	0	-	-
1f24e	1	clnt	code,/dev/hd2:2521	s	18	0	-	-
8079	3	clnt	file mapped read write, /dev/hd3:5	s	8	0	-	-
a27b	-	clnt	/dev/hd2:123146	s	1	0	-	-

- To only display non empty segments and add per page size breakdown for segments with multiple page sizes, enter:

```
$ svmon -P 209034 -O segment=on,filterprop=notempty,mpss=on
```

```
Unit: page
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
209034	xmwl	15977	5492	0	15929

VsId	EsId	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	shared library text	m	495	0	0	495
2002	0	work	kernel segment	m	396	343	0	396
19288	c	work	shared memory segment	s	5	0	0	1477
				m	92	0	0	0
b27a	f	work	shared library data	s	106	0	0	106
				m	0	0	0	0
d27c	2	work	process private	s	74	4	0	90
				m	1	0	0	0
1b24a	-	clnt	/dev/hd4:15493	s	21	0	-	-
1f24e	1	clnt	code,/dev/hd2:2521	s	18	0	-	-
8079	3	clnt	file mapped read write, /dev/hd3:5	s	8	0	-	-
a27b	-	clnt	/dev/hd2:123146	s	1	0	-	-

The 2 previous examples show the difference of the values reported in the **Inuse**, **Pin**, **Pgsp** and **Virtual** columns with MPSS pages. On this system **sm** pages are used by the process 209034, the metrics reported in the first report are in 4KB pages (in the smaller page size) while when the breakdown by page size is displayed with the **-O mpss=on** option, **s** pages are in 4KB page and **m** pages are in 64KB pages. So, for the segment 19288 this gives  $1477*4=5908\text{KB}$  in the first example, and  $5*4*1024 + 92*64*1024 = 5908\text{KB}$  in the second example. Dashes are put on the Pgsp and Virtual memory columns for the client segments because it is meaningless for this type of segment.

- To display detailed information about mapping segments for a process, in KB unit, enter:

```
$ svmon -P 340216 274676 -O segment=on,unit=KB,mapping=on
```

```
Unit: KB
-----
```

Pid	Command	Inuse	Pin	Pgsp	Virtual
274676	ptxtstmmmap	57276	21968	0	57256

VsId	EsId	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
502d	d	work	shared library text	m	31744	0	0	31744
2002	0	work	kernel segment	m	25344	21952	0	25344
10661	2	work	process private	sm	76	16	0	76
1a36b	f	work	shared library data	sm	52	0	0	52
14665	1	clnt	code,/dev/hd2:825	s	12	0	-	-
11660 *	-	work	mmap paging	sm	8	0	0	8

d65c *	- work mmap paging	sm	8	0	0	8
13662 *	- work mmap paging	sm	8	0	0	8
4655 *	- work mmap paging	sm	8	0	0	8
b2ba	- clnt /dev/hd3:13	s	8	0	-	-
1350 *	- work mmap paging	sm	8	0	0	8
18329	3 mmap maps 5 source(s)	sm	0	0	-	-
	source(s)=b2ba/13662, b2ba/d65c, b2ba/4655, b2ba/11660					
	source(s)=b2ba/1350					
-----						
Pid	Command	Inuse	Pin	Pgsp	Virtual	
340216	ptxtst mmap	57240	21968	0	57216	
Vsid	Esid	Type	Description	PSize	Inuse	Pin Pgsp Virtual
502d	d	work	shared library text	m	31744	0 0 31744
2002	0	work	kernel segment	m	25344	21952 0 25344
f65e	2	work	process private	sm	76	16 0 76
19668	f	work	shared library data	sm	52	0 0 52
1d66c	-	clnt	/dev/hd3:14	s	12	0 - -
14665	1	clnt	code,/dev/hd2:825	s	12	0 - -
1c66d	3	mmap	maps 3 source(s)	sm	0	0 - -
			source(s)=1d66c, 1d66c, 1d66c			

The mapping option is used in this case to also show mmaped segments which are not in the address space of the process. The process 274676 has created a shared memory file (client segment b2ba), this segment is used by mmap segments (11660, d65c, 13662, 4655, 1350) which are not in the address space of the process. The mmap segment of the process gives the list of all mmaped segment and their associated source (b2ba/13662, ...).

The process 340216 has created a private memory file, no extra mmap segments are displayed since all segments which are using this resource are private to the process and are already so shown by default.

## Workload management class report

To print the class report, specify the **-W** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

### Class or Superclass

Indicates the class or superclass name.

The **-O subclass=on** option can be added to display the list of subclasses.

### Examples:

1. To display memory statistics about all WLM classes in the system, enter:

```
# svmon -W -O unit=page,commandline=on,timestamp=on
```

```
Command line : svmon -W -O unit=page,commandline=on,timestamp=on
Unit: page                                         Timestamp: 10:41:20
=====
Superclass           Inuse      Pin      Pgsp  Virtual
System               121231    94597    19831  135505
Unclassified         27020     8576     67     8659
Default              17691     12      1641   16491
Shared               15871     0        0     13584
Unmanaged            0         0        0        0
```

In this example, all the WLM classes of the system are reported. Since no sort option was specified, the Inuse metric (real memory usage) is the sorting key. The class System uses 121231 pages in real memory. 94597 frames are pinned. The number of pages reserved or used in paging space is 19831. The number of pages allocated in the virtual space is 135505.

2. To display memory statistics about all WLM classes and subclasses in the system, enter:

```
# svmon -W -0 subclass=on -0 unit=page,commandline=on,timestamp=on
```

```
Command line : svmon -W -0 subclass=on -0 unit=page,commandline=on,timestamp=on
Unit: page
Timestamp: 10:43:18
=====
Superclass          Inuse      Pin      Pgps  Virtual
System              120928    94609    19831  135202
System.Default      120928    94609    19831  135202
System.Shared        0         0         0       0
Unclassified        27020     8576     67     8659
Default             17691     12       1641   16491
Default.Default     17691     12       1641   16491
Default.Shared      0         0         0       0
Shared              15871     0         0     13584
Shared.Default      15871     0         0     13584
Shared.Shared        0         0         0       0
Unmanaged           0         0         0       0
```

In this example, all the WLM classes and sub-classes of the system are reported. Since the no sort option was specified, the Inuse metric (real memory usage) is the sorting key. The class System uses 120928 pages in real memory, they are split into 120928 pages in the System Default sub-class, and no pages in the Shared sub-class.

## Workload management tier report

To print the tier report, specify the **-T** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

### Tier

Indicates the tier number

### Superclass

The optional column heading indicates the superclass name when tier applies to a superclass (when the **-a** flag is used).

The **-O subclass=on** option can be added to display the list of subclasses. The **-a <supclassname>** option allows reporting only the details of a given super class.

### Examples:

1. To display memory statistics about all WLM tiers and superclasses in the system, enter:

```
# svmon -T -0 unit=page
```

```
Unit: page
=====
Tier                Inuse      Pin      Pgps  Virtual
  0                  137187    61577    2282  110589
=====
Superclass          Inuse      Pin      Pgps  Virtual
System              81655     61181    2282   81570
Unclassified        26797     384      0     2107
Default             16863     12       0     15040
Shared              11872     0         0     11872
Unmanaged           0         0         0       0
  1                  9886     352      0     8700
=====
Superclass          Inuse      Pin      Pgps  Virtual
myclass             9886     352      0     8700
```

All the superclasses of all the defined tiers are reported. Each Tier has a summary header with the *Inuse*, *Pin*, *Paging space*, and *Virtual* memory, and then the list of all its classes.

2. To display memory statistics about all WLM tiers, superclasses and classes in the system, enter:

```
# svmon -T -0 subclass=on -0 unit=page,commandline=on,timestamp=on
```

```
Command line : svmon -T -0 subclass=on -0 unit=page,commandline=on,timestamp=on
Unit: page
Timestamp: 10:44:31
```

```

=====
Tier                                Inuse      Pin      Pgps  Virtual
  0                                181824    103185  21539 174250
=====
Superclass                          Inuse      Pin      Pgps  Virtual
System                              121242    94597   19831 135516
=====
Class                               Inuse      Pin      Pgps  Virtual
System.Default                      121242    94597   19831 135516
System.Shared                        0         0        0      0
Unclassified                         27020     8576    67     8659
=====
Superclass                          Inuse      Pin      Pgps  Virtual
Default                              17691     12      1641  16491
=====
Class                               Inuse      Pin      Pgps  Virtual
Default.Default                     17691     12      1641  16491
Default.Shared                       0         0        0      0
=====
Superclass                          Inuse      Pin      Pgps  Virtual
Shared                              15871     0        0     13584
=====
Class                               Inuse      Pin      Pgps  Virtual
Shared.Default                      15871     0        0     13584
Shared.Shared                        0         0        0      0
Unmanaged                            0         0        0      0
=====

```

Details at sub-class level can also be displayed for each class of each Tier.

- To display memory statistics about a particular WLM superclass in a tier, with segment and per page size details, enter:

```
# svmon -T 0 -a myclass2 -O segment=on,pgsz=on,pidlist=on
```

```

Unit: page
=====
Tier Superclass                    Inuse      Pin      Pgps  Virtual
  0 myclass2                        36         4        0     36
=====
      PageSize                    Inuse      Pin      Pgps  Virtual
      s      4 KB                  36         4        0     36
      m     64 KB                   0         0        0      0
=====
Class                               Inuse      Pin      Pgps  Virtual
myclass2.Default                    36         4        0     36
=====
      Vsid      Esid Type Description                    PSize  Inuse  Pin  Pgps  Virtual
      711          2 work process private                    sm     19   4   0    19
      pid(s)=372980
      126a3       f work shared library data                    sm     17   0   0    17
      pid(s)=372980
=====
Class                               Inuse      Pin      Pgps  Virtual
myclass2.Shared                     0         0        0      0
=====

```

The statistics of all the subclasses, in the tier 0, of the superclass *myclass2* are reported. The distribution between the different page sizes is displayed by the **-O pgsz=on** option. Then, as **-O segment=on** is specified, the subclass statistics are followed by its segments statistics. Finally, as **-O pidlist=on** is specified for each segment, the list of process which uses it, is displayed.

## Segment report

To print the segment report, specify the **-S** flag.

This report contains all the columns detailed in the **common summary metrics** as well as its own defined here:

### Vsid

Indicates the virtual segment ID. Identifies a unique segment in the VMM.

### Esid

Indicates the effective segment ID. The **Esid** is only valid when the segment belongs to only one process (i.e: only one address space). When provided, it indicates how the segment is used by the process. If the **Vsid** segment is mapped by several processes (i.e: several address spaces), then this

field contains - (hyphen). The exact Esid values can be obtained through the **-P** flag applied on each of the process identifiers using the segment. A - (hyphen) also displays for segments used to manage open files or multi-threaded structures because these segments are not part of the user address space of the process.

### Type

Identifies the type of the segment:

- *pers* indicates a persistent segment
- *work* indicates a working segment
- *clnt* indicates a client segment
- *mmap* indicates a mapped segment
- *rmap* indicates a real memory mapping segment

### Description

Gives a textual description of the segment. The content of this column depends on the segment type and usage.

If the segment is a persistent segment and is not associated with a log, then the device name and i-node number of the associated file are displayed, separated by a colon. The device name and i-node can be translated into a file name with the **ncheck** command or by using the **-O filename=on** flag. If the segment is the primary segment of a large file, then the words *large file* are prepended to the description.

### PSize

Indicates the size of the pages inside the segment.

### Note:

- Mapping device name and inode number to file names can be a lengthy operation for deeply nested file systems. Because of that, the **-O filename=on** option should be used with caution.
- If the segment is a persistent segment and is associated with a log, then the string *log* displays. If the segment is a working segment, then the **svmon** command attempts to determine the role of the segment. For instance, special working segments such as the kernel and shared library are recognized by the **svmon** command. If the segment is the private data segment for a process, then *private* prints out. If the segment is the code segment for a process, and the segment report prints out in response to the **-P** flag, then the string *code* is prepended to the description.
- If the segment is mapped by several processes and used in different ways (that is, a process private segment mapped as shared memory by another process), then the description is empty. The exact description can be obtained through **-P** flag applied on each process identifier using the segment.
- If a segment description is too large to fit in the description space, then the description is truncated. If you need to enlarge the output you can use the **-O format** flag. When set to **-O format=160**, the report is displayed in 160 columns, which means more room for the description field. When set to **-O format=nolimit**, the description will be fully printed even if it brakes the column alignment.

### Restriction:

- Segment reports can only be generated for primary segments.

### Examples:

1. To display information about a list of segments including the list of processes using them, enter:

```
# svmon -S 11c02 3393e5 2c10da 2c4158 1b1a34 -O pidlist=on
```

Unit: page

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
11c02	-	work	kernel heap System segment	s	65536	0	0	65536
3393e5	3	work	working storage pid(s)=168138	s	10143	0	0	10143
2c4158	-	work		s	5632	5632	0	5632

1b1a34	System segment - work	L	2	2	0	2
2c10da	Unattached segment - clnt /dev/hd2:4183 Unused segment	s	2110	0	-	-

Information about each segment in the list is displayed. The Esid column contains information only when **-O pidlist=on** is specified because the Esid has a meaning only in the address space of a process. In this case, since the segment **3393e5** belongs to the process **168138**, the Esid is reported, in all other cases no information is displayed. The segments **11c02** is the kernel pinned heap. The segment **2c4158** has no special characteristics. The segment **2c10da** is relative to a file whose device is **/dev/hd2** and whose inode number is **4183**. The Paging space and Virtual fields of the segment **2c10da** are not meaningful (because it is a client segment). The segment **1b1a34** is a 16 MB page segment which contains 2 pages of 16 MB (equivalent to 8192 pages of 4KB).

- To display information about all unattached segments in the system, enter:

```
# svmon -S -O filtercat=unattached
```

```
Unit: page
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
1b1a34	-	work		L	2	2	0	2
2618ce	-	work		s	1	0	0	1

In this example, the report contains all the segments coming from processes which have allocated shared memory areas, and which have exited without freeing these memory areas.

- To display the top 10 (in real memory consumption or sorted by the inuse field) text segments with their corresponding file name, enter:

```
# svmon -S -t 10 -O unit=auto,filterprop=text,filename=on
```

```
Unit: auto
```

Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual
1a0cb	-	clnt	/dev/hd2:4140	s	7.62M	0K	-	-
a37b	-	clnt	/usr/ccs/lib/libc.a	s	4.34M	0K	-	-
1150	-	clnt	/usr/java5/jre/bin/libj9jit23.so	s	3.77M	0K	-	-
16667	-	clnt	/dev/hd2:16394	s	3.10M	0K	-	-
14285	-	clnt	/usr/lpp/xlC/lib/aix61/libC.a	s	2.91M	0K	-	-
8159	-	clnt	/usr/bin/ptxtstoverflow_heap	s	2.52M	0K	-	-
1b2ca	-	clnt	/dev/hd2:2716	s	2.27M	0K	-	-
f23e	-	clnt	/usr/lib/drivers/nfs.ext	s	1.88M	0K	-	-
17026	-	clnt	/dev/hd2:65747	s	1.79M	0K	-	-
15104	-	clnt	/usr/java5/jre/lib/core.jar	s	1.41M	0K	-	-
	-	clnt	/dev/hd2:115081	s	1.88M	0K	-	-
	-	clnt	/usr/opt/perl5/lib/5.8.2/aix-thread-multi/CORE/libperl.	s	1.79M	0K	-	-
	-	clnt	/dev/hd2:8470	s	1.79M	0K	-	-
	-	clnt	/usr/lib/boot/unix_64	s	1.41M	0K	-	-
	-	clnt	/dev/hd2:2258	s	1.41M	0K	-	-
	-	clnt	/usr/lib/libdns_nonsecure.a	s	1.41M	0K	-	-

The **-O filename=on** option allows in this case to display the filename of each client text segment. The amount of memory used by every segment is put with the unit identifier because of the **-O unit=auto** option. The segment **1a0cb** holds 7.62MB of real memory and no pinned memory. The paging space and virtual memory are meaningless for client segments. The Description of the segment **f23e** is truncated because the default format of the report is 80 columns. The **-O format=180** or **-O format=nolimit** could be used to display the full path of this file.

## Named Shared Libraries

When the Named Shared Libraries (NSLA) areas are used, the segment description contains the name of the area.

When a WPAR was used during a checkpoint and restarted, some shared library areas might be local to the WPAR. The name of the WPAR is printed after the name of the area. Note that using Named Shared Library Areas in a WPAR does not mean that the area is for this WPAR only. For more information, see the documentation on NSLA.

In all other examples, the area is system-wide; therefore, the WPAR name is omitted.

The following is a list of possible examples:

- *myarea* means a system-wide area *myarea* is defined on the system.
- *@myarea* means an *unnamed* area is defined on the WPAR *mywpar*.
- *myarea@mywpar* means an area named *myarea* is defined on the WPAR *mywpar*.

### Examples:

System-wide Named Shared Library area:

```
# svmon -P 381050 -O pidlist=on,pgsz=on,segment=on,summary=basic or
# svmon -P 381050 -O pidlist=on,pgsz=on
```

Unit: page

Pid	Command	Inuse	Pin	Pgsp	Virtual				
381050	yes	11309	9956	0	11308				
PageSize		Inuse	Pin	Pgsp	Virtual				
s	4 KB	221	4	0	220				
m	64 KB	693	622	0	693				
Vsid	Esid	Type	Description	PSize	Inuse	Pin	Pgsp	Virtual	
0	0	work	kernel segment	m	693	622	0	693	
			System segment						
60006	d	work	shared library text	s	185	0	0	185	
			myshlarea						
			Shared library text segment						
91a08	2	work	process private	s	18	4	0	18	
			pid(s)=381050						
21a23	f	work	shared library data	s	17	0	0	17	
			pid(s)=381050						
11920	1	clnt	code,/dev/hd2:338	s	1	0	-	-	
			pid(s)=381050						

## Detailed report

The detailed report (-D) displays information about the pages owned by a segment and, on-demand, it can display the frames these pages are mapped to. To print the detailed report, specify the **-D** flag.

Several fields are presented before the listing of the pages used:

### Segid

The segment identifier.

### Type

The type of the segment.

### PSize

The type of the segment.

### Address Range

Ranges in which frames are used by this segment.

Ranges in which frames are used by this segment.

### Size of paging space allocation

**Virtual**

Number of pages used by this segment.

**Inuse**

Number of frames used by this segment.

**Column headings in a detailed report:****Page**

Relative page number to the virtual space. This page number can be higher than the number of frames in a segment (65535) if the virtual space is larger than a single segment (large file).

**Frame**

Frame number in the real memory. Since frames are always considered 4KB in size regardless of the page size of the segment, for any page size larger than 4 KB, a range of frames instead of a single frame is associated to one page. This range is noted as XXXXXXX..YYYYYYY, which means that the continuous range of frames between ID XXXXXXX and YYYYYYY is used for the given page.

**Pin**

Indicates if the frame is pinned or not.

**Ref**

Indicates if the frame has been referenced by a process.

**Mod**

Indicates if the frame has been modified by a process.

**ExtSegid**

Extended segment identifier. This field is only set when the page number is higher than the maximum number of frames in a segment.

**ExtPage**

Extended page number. This field is only set when the page number is higher than the maximum number of frames in a segment and indicates the page number within the extended segment.

**Note:**

- The `-@` flag has no effect on the `-D` option.
- This option only supports the additional **-O frame** option, which shows additional frame level details.
- The format used by this report is on 160 columns.

**Examples:**

```
#svmon -D b9015
```

```
Segid: b9015
Type: client
PSize: s (4 KB)
Address Range: 0..9 : 122070..122070
```

Page	Psize	Frame	Pin	Ref	Mod	ExtSegid	ExtPage
0	s	74870	N	N	N	-	-
1	s	11269	N	N	N	-	-
2	s	11270	N	N	N	-	-
3	s	11271	N	N	N	-	-
4	s	11272	N	N	N	-	-
5	s	11273	N	N	N	-	-
6	s	11274	N	N	N	-	-
7	s	11275	N	N	N	-	-
8	s	986106	N	N	N	-	-
9	s	4093	N	N	N	-	-
122070	s	78191	N	N	N	208831	dcd6

The segment `b9015` is a client segment with 11 pages. None of them are pinned.

The page 122070 is physically the page `dcd6` in the extended segment 208831.

```
# svmon -D 6902f -O frame=on
```

```

Segid: 6902f
Type: working
PSize: s (4 KB)
Address Range: 0..179 : 65309..65535
Size of page space allocation: 0 pages ( 0.0 MB)
Virtual: 99 frames ( 0.4 MB)
Inuse: 99 frames ( 0.4 MB)

```

Page	Psize	Frame	Pin	Ref	Mod	ExtSegid	ExtPage	Pincount	State	Swbits
65483	s	72235	Y	N	N	-	-	1/0	Hidden	88000000
65353	s	4091	Y	N	N	-	-	1/0	Hidden	88000000
65352	s	4090	Y	N	N	-	-	1/0	Hidden	88000000
65351	s	4089	Y	N	N	-	-	1/0	Hidden	88000000
65350	s	1010007	N	N	N	-	-	0/0	In-Use	88020000
65349	s	1011282	N	N	N	-	-	0/0	In-Use	88020000
65354	s	992249	N	N	N	-	-	0/0	In-Use	88020000
65494	s	1011078	N	N	N	-	-	0/0	In-Use	88020000
0	s	12282	N	N	N	-	-	0/0	In-Use	88820000
1	s	12281	N	N	N	-	-	0/0	In-Use	88820000
2	s	64632	N	N	N	-	-	0/0	In-Use	88a20000
3	s	64685	N	N	N	-	-	0/0	In-Use	88a20000
4	s	64630	N	N	N	-	-	0/0	In-Use	88a20000
5	s	64633	N	N	N	-	-	0/0	In-Use	88820000

The frame 72235 is pinned, not referenced and not modified, it is in the Hidden state, it does not pertain to an extended segment nor to a large page segment.

## XML report

To print the XML report, specify the **-X** option.

By default the report is printed to standard output. The **-o filename** flag allows you to redirect the report to a file. When the **-O affinity** option is used, affinity information is added to the report.

**Note:** The **-O affinity=detail** option can take a long time to compute.

The extension of XML reports is **.svm**. To prevent a report overwrite, the option **-O overwrite=off** option can be specified (by default this option is set to **on**).

This XML file uses a XML Schema Definition (XSD) which can be found in the file: **/usr/lib/perf/svmon\_measurement.xsd**. This schema is self-documented and thus can be used by anyone to build custom application using the XML data provided in these reports.

The data provided in this file is a snapshot view of the whole machine. It contains enough data to build an equivalent of the **-G, -P, -S, -W, -U, and -C** options.

## Remote Statistics Interface API Overview

The Remote Statistics Interface (RSI) is an application programming interface (API) that is available for developing programs that access the statistics available from one or more **xmtopas** daemons.

Learn the procedure to use the RSI Interface API through the sample programs. The sample programs, and others, are also provided in the machine-readable. The sample programs can be found in the **/usr/samples/perfmgr** directory.

Use the RSI Interface API to write programs that access one or more **xmtopas** daemons. It allows you to develop programs that print, post-process, or otherwise manipulate the raw statistics provided by the **xmtopas** daemons. Such programs are known as Data-Consumer programs.

## Makefile

The include files are based on the define directives, which must be properly set. They are defined with the **-D** preprocessor flag.

- **\_AIX** specifies the include files to generate code for AIX.
- **\_BSD** required for proper BSD compatibility.

An example of a Makefile that helps to build a sample program follows:

```
LIBS = -L./ -lbsd -lSpmi
CC = cc
CFLAGS = -D_BSD -DRSIv6 -D_AIX®
all:: RsiCons RsiCons1 chmon

RsiCons: RsiCons.c
$(CC) -o RsiCons RsiCons.c $(CFLAGS) $(LIBS)

RsiCons1: RsiCons1.c
$(CC) -o RsiCons1 RsiCons1.c $(CFLAGS) $(LIBS)

chmon: chmon.c $
$(CC) -o chmon chmon.c $(CFLAGS) $(LIBS) -lcurses
```

If the system that is used to compile does not support ANSI function prototypes, include the `-D_NO_PROTO` flag.

## Remote Statistics Interface list of subroutines

The **xmperf** interface is used to view the graphical display of statistics on all the hosts in a network.

The Remote Statistics Interface (RSI) application programming interface (API) is used to create data-consumer programs that helps to access statistics of any host's **xmtopas** daemon.

The RSI interface consists of the following groups of subroutines.

### Initialization and Termination

Item	Descriptor
RSiInitx	Allocates or changes the table of RSI handles.
RSiOpenx	Initializes the RSI interface for a remote host.
RSiClosex	Terminates the RSI interface for a remote host and releases all memory allocated.
RSiInvitex	Invites data suppliers on the network to identify themselves and returns a table of data-supplier host names.

### Instantiation and Traversal of Context Hierarchy

Item	Descriptor
RSiInstantiatex	Creates (instantiates) all subcontexts of a context object.
RSiPathGetCxx	Searches the context hierarchy for a context that matches a context path name.
RSiFirstCxx	Returns the first subcontext of a context.
RSiNextCxx	Returns the next subcontext of a context.
RSiFirstStatx	Returns the first statistic of a context.
RSiNextStatx	Returns the next statistic of a context.

### Defining Sets of Statistics to Receive

Item	Descriptor
RSiAddSetHotx	Adds a single set of peer statistics to a hotset.
RSiCreateHotSetx	Creates an empty hotset.

<b>Item</b>	<b>Descriptor</b>
RSiCreateStatSetx	Creates an empty statset.
RSiPathAddSetStatx	Adds a single statistic to a statset.
RSiDelSetHotx	Deletes a single set of peer statistics from a hotset.
RSiDelSetStatx	Deletes a single statistic from a statset.
RSiStatGetPathx	Finds the full path name of a statistic identified by an SpmiStatVals pointer.

## Starting, Changing, and Stopping Data Feeding

<b>Item</b>	<b>Descriptor</b>
RSiStartFeedx	Tells xmtopas to start sending data feeds for a statset.
RSiStartHotFeedx	Tells xmtopas to start sending hot feeds for a hotset.
RSiChangeFeedx	Tells xmtopas to change the time interval between sending data feeds for a statset.
RSiChangeHotFeedx	Tells xmtopas to change the time interval between sending hot feeds for a hotset.
RSiStopFeedx	Tells xmtopas to stop sending data feeds for a statset.
RSiStopHotFeedx	Tells xmtopas to stop sending hot feeds for a hotset.

## Receiving and Decoding Data Feed Packets

<b>Item</b>	<b>Descriptor</b>
RSiGetHotItemx	Returns the peer context name and data value for the first (next) SpmiHotItems element by extraction from data feed packet.
RSiMainLoopx	Allows an application to suspend execution and waits to be woken when data feeds arrive.
RSiGetValuex	Returns data value for a given SpmiStatVals pointer by extraction from data feed packet.
RSiGetRawValuex	Returns a pointer to a valid SpmiStatVals structure for a given SpmiStatVals pointer by extraction from data feed packet.

## RSI Interface Concepts and Terms

Learn about the structures and the commonalities of the library functions and important design concepts.

To start using the RSI interface API you must be aware of the format and use of the RSI interface data structures.

## RSI Interface data structures

The RSI interface is based upon control blocks (data structures) that describe the current view of the statistics on a remote host and the state of the interaction between a data consumer program and the remote host's **xmtopas** daemon.

The RSI interface supports the following data structures:

- RSI handle
- SpmiStatVals

### RSI handle

An RSI handle is a pointer to a data structure of type `RsiHandleStructx`. Prior to using any other RSI call, a data-consumer program must use the `RSiInit` subroutine to allocate a table of RSI handles. An RSI handle from the table is initialized when you open the logical connection to a host and that RSI handle must be specified as an argument on all subsequent subroutines to the same host. Only one of the internal fields of the RSI handle should be used by the data-consumer program, namely the pointer to received network packets, `pi`. Only in very special cases will you ever need to use this pointer, which is initialized by `RSiOpenx` and must never be modified by a data-consumer program. If your program changes any field in the RSI handle structure, results are highly unpredictable. The RSI handle is defined in `/usr/include/sys/Rsi.h`.

### SpmiStatVals

A single data value is represented by a structure defined in `/usr/include/sys/Spmidef.h` as struct `SpmiStatVals`. Be aware that none of the fields defined in the structure must be modified by application programs. The two handles in the structure are symbolic references to contexts and statistics and should not be confused with pointers. The last three fields are updated whenever a `data_feed` packet is received. These fields are as follows:

Item	Descriptor
<code>val</code>	The latest actual contents of the statistics data field.
<code>val_change</code>	The difference (delta value) between the latest actual contents of the statistics data field and the previous value observed.
<code>error</code>	An error code as defined by the enum <code>Error</code> included in the <code>/usr/include/sys/Spmidef.h</code> file.

**Note:** The two value fields are defined as union `Value`, which means that the actual data fields may be long or float, depending on flags in the corresponding `SpmiStat` structure. The `SpmiStat` structure cannot be accessed directly from the `StatVals` structure (the pointer is not valid, as previously mentioned). Therefore, to determine the type of data in the `val` and `val_change` fields, you must have saved the `SpmiStat` structure as returned by the **RSiPathAddSetStatx** subroutine. This is rather clumsy, so the `RSiGetValuex` subroutine does everything for you and you do not need to keep track of `SpmiStat` structures.

The `SpmiStat` structure is used to describe a statistic. It is defined in the `/usr/include/sys/Spmidef.h` file of type `SpmiStat` struct. If you ever need information from this data structure (apart from information that can be returned by the `RSiStatGetPathx` subroutine) be sure to save it as it is returned by the **RSiPathAddSetStatx** subroutine.

The `RSiGetValuex` subroutine provides another way of getting access to an `SpmiStat` structure but can only do so while a data feed packet is being processed.

The **xmtopas** daemon accepts the definition of sets of statistics that are to be extracted simultaneously and sent to the data-consumer program in a single data packet. The structure that describes such a

set of statistics is defined in the `/usr/include/sys/Spmidef.h` file of type `SpmiStatSet` struct. As returned by the **RSiCreateStatSetx**, the `SpmiStatSet` pointer must be treated as a handle whose only purpose is to identify the correct set of statistics to several other subroutines.

When returned in a data feed packet, the `SpmiStatSet` structure holds the actual time the data feed packet was created (according to the remote host's clock) and the elapsed time since the latest previous data feed packet for the same `SpmiStatSet` was created.

`SpmiHotSet` structure represents another set of access structures that allow an application program to define an alternative way of extracting and processing metrics. They are used to extract data values for the most or least active statistics for a group of peer contexts. For example, it can be used to define that the program wants to receive information about the two highest loaded disks, optionally subject to the load exceeding a specified threshold.

When the SPMI receives a read request for an `SpmiHotSet`, the SPMI reads the latest value for all the peer sets of statistics in the hotset in one operation. This action reduces the system overhead caused by access of kernel structures and other system areas, and ensures that all data values for the peer sets of statistics within a hotset are read at the same time. The hotset may consist of one or many sets of peer statistics.

`SpmiHotVals` One `SpmiHotVals` structure is created for each set of peer statistics selected for the hotset. When the SPMI executes a request from the application program to read the data values for a hotset, all `SpmiHotVals` structures in the set are updated. The RSi application program can then traverse the list of `SpmiHotVals` structures by using the **RSiGetHotItemx** subroutine call.

The `SpmiHotVals` structure carries the data values from the SPMI to the application program. Its data carrying fields are:

<b>Item</b>	<b>Descriptor</b>
error	Returns a zero value if the SPMI's last attempt to read the data values for a set of peer statistics was successful. Otherwise, this field contains an error code as defined in the <code>sys/Spmidef.h</code> file.
avail_resp	Used to return the number of peer statistic data values that meet the selection criteria (threshold). The field <code>max_responses</code> determines the maximum number of entries actually returned.
count	Contains the number of elements returned in the array items. This number is the number of data values that met the selection criteria (threshold), capped at <code>max_responses</code> .

<b>Item</b>	<b>Descriptor</b>
items	<p>The array used to return count elements. This array is defined in the <code>SpmiHotItems</code> data structure. Each element in the <code>SpmiHotItems</code> array has the following fields:</p> <p><b>name</b> The name of the peer context for which the values are returned.</p> <p><b>val</b> Returns the value of the counter or level field for the peer statistic. This field returns the statistic's value as maintained by the original supplier of the value. However, the <code>val</code> field is converted to an SPMI data format.</p> <p><b>val_change</b> Returns the difference between the previous reading of the counter and the current reading when the statistic contains counter data. When this value is divided by the elapsed time returned in the <code>SpmiHotSet</code> Structure, an event rate-per-time-unit can be calculated.</p>

## RSI Request-Response Interface

The RSI interface API has two distinctly different ways of operation.

The RSI request-response protocol that sends a single request to **xmtopas** daemon and waits for a response. A timeout occurs if no response has been received within a specified time limit and a single retry is attempted. If the retry also results in a timeout, the same is communicated to the caller by placing the `RSiTimeout` constant in the external integer `RSiErrno` field. If any other error occurred, the external integer field has some other non-zero value.

If neither a communication error nor a timeout error occurred, a packet is available in the receive buffer pointed to by the `pi` pointer in the RSI handle. The packet includes a status code that tells whether the subroutine was successful at the **xmtopas** daemon. You must check the status code in a packet if it matters what exactly it is because the `RSiBadStat` constant is placed in `RSiErrno` field to indicate to your program that a bad status code was received.

You can use the indication of error or success as defined for each subroutine to determine if the subroutine succeeded or you can test the external integer `RSiErrno`. If this field is `RSiOkay` the subroutine succeeded; otherwise it did not. The error codes returned in `RSiErrno` are defined in the `RSiErrorType` enum.

All the library functions use the request-response interface, except for `RSiMainLoop` (which uses a network driven interface) and `RSiInitx`, `RSiGetValuex`, and `RSiGetRawValuex` (that do not involve network traffic).

## RSI Network driven interface

The **xmquery** protocol defines three types of data packets that are sent from the data supplier of the **xmtopas** daemon without being solicited by a request packet.

The request packet types are the `still_alive`, the `data_feed`, and the `except_rec` packets. The `still_alive` packets are handled internally in the RSI interface and require no programming in the data-consumer program.

The `data_feed` packets are received asynchronously with any packets produced by the request-response type subroutines. If a `data_feed` packet is received when processing a request-response

function, control is passed to a callback function, which must be named when the RSI handle is initialized with the **RSiOpenx** subroutine.

When the data-consumer program is not using the request-response functions, it still needs to be able to receive and process `data_feed` packets. This is done with the **RSiMainLoopx** function, which invokes the callback function whenever a packet is received.

Actually, the data feed callback function is invoked for all packets received that cannot be identified as a response to the latest request sent, except if such packets are of type `i_am_back`, `still_alive`, or `except_rec`. Note that this means that responses to “request-response” packets that arrive after a timeout is sent to the callback function. It is the responsibility of your callback function to test for the packet type received.

The `except_rec` packets are received asynchronously with any packets produced by the request-response type subroutines. If an `except_rec` packet is received when processing a request-response function, control is passed to a callback function, which must be named when the RSI handle is initialized with the **RSiOpenx** subroutine.

When the data-consumer program is not using the request-response functions, it still needs to be able to receive and process `except_rec` packets. This is done with the **RSiMainLoopx** function which invokes the callback function whenever a packet is received.

**Note:** The API discards `except_rec` messages from a remote host unless a callback function to process the message type was specified on the **RSiOpenx** subroutine call for that host.

## Resynchronizing

Network connections can go bad, hosts can go down, interfaces can be taken down and processes can stop functioning.

In the case of the **xmtopas** protocol, such situations usually result in one or more of the following:

- Missing packets
- Resynchronizing requests

### Missing packets

Responses to outstanding requests are not received, which generate a timeout. That's fairly easy to cope with because the data-consumer program has to handle other error return codes anyway. It also results in expected data feeds not being received. Your program may want to test for this happening. The proper way to handle this situation is to use the **RSiClosex** function to release all memory related to the dead host and to free the RSI handle. After this is done, the data-consumer program may attempt another **RSiOpenx** to the remote system or may simply exit.

### Resynchronizing requests

Whenever an **xmtopas** daemon hears from a given data-consumer program on a particular host for the first time, it responds with a packet of `i_am_back` type, effectively prompting the data-consumer program to resynchronize with the daemon. Also, when the daemon attempts to reconnect to data-consumer programs that it talked to when it was killed or died, it sends an `i_am_back` packet.

It is important that you understand how the **xmtopas** daemon handles “first time contacted.” It is based upon tables internal to the daemon. Those tables identify all the data-consumers that the daemon knows about. Be aware that a data-consumer program is known by the host name of the host where it executes suffixed by the IP port number used to talk to the daemon. Each data-consumer program running is identified uniquely as are multiple running copies of the same data-consumer program.

Whenever a data-consumer program exits orderly, it alerts the daemon that it intends to exit and the daemon removes it from the internal tables. If, however, the data-consumer program decides to not request data feeds from the daemon for some time, the daemon detects that the data consumer has lost interest and removes the data consumer from its tables as described in Life and Death of **xmtopas**. If the

data-consumer program decides later that it wants to talk to the **xmtopas** daemon again, the daemon responds with an `i_am_back` packet.

The `i_am_back` packets are given special treatment by the RSI interface. Each time one is received, a resynchronizing callback function is invoked. This function must be defined on the **RSiOpenx** subroutine.

**Note:** All data-consumer programs can expect to have this callback invoked once during execution of the **RSiOpenx** subroutine because the remote **xmtopas** does not know the data consumer. This is usual and should not cause your program to panic. If the resynchronize callback is invoked twice during processing of the **RSiOpenx** function, the open failed and can be retried, if appropriate.

## Specifying port range for RSI communication

A random communication port is required between the **xmtopas** or **xmtopas** interface and the consumers. The `Rsi.hosts` configuration file is used to set the ports within a specified range.

To set the port range, complete these steps:

1. Locate the `Rsi.hosts` file in the `$HOME` or the `/etc/perf` directory. If the file does not exist in either of the directories, search the file in the `/usr/lpp/perfmgr` directory.
2. Specify the start and the end port in the acceptable range as mentioned in the `Rsi.hosts` file. If the `Rsi.hosts` file cannot be located in directories or the port range is specified incorrectly, the RSI communication uses random ports.

To specify the port range in the `Rsi.hosts` file, use the following command:

```
portrange <start_port> <end_port>
```

Example:

```
portrange 3001 3003
```

When the RSI communication starts, it uses 3001, 3002 or 3003 ports in the specified range. Only 3 RSI agents can listen to the ports and the subsequent RSI communication fails.

## A Simple Data-Consumer Program

The use of the application programming interface (API) is illustrated by creating a small data-consumer program to produce a continuous list of statistics from a host.

The first version accesses only CPU-related statistics. It assumes that you want to get your statistics from the local host unless you specify a host name on the command line. The program continues to display the statistics until it is killed. The source code for the sample program can be found in the `/usr/samples/perfmgr/RsiCons1.c` file.

## Initializing and terminating the program

The main function of the sample program uses the three subroutines as shown in the following code segment. The lines 12 through 15 use any command line argument to override the default host name obtained by the `uname` function. Then lines 17 through 28 initialize the RSI interface using the **RSiInitx** and **RSiOpenx** subroutines. The program exits if the initialization fails.

```
[01] extern char  RSiEMsg[];
[02] extern int  RSiErrno;
[03] char  host[64], apath[256], head1[24][10], head2[24][10];
[04] char  *nptr, **navn = &nptr, *dptr, **desc = &dptr;
[05] struct utsname  uname_struct;
[07] RsiHandlex  rsh;
[08] struct SpmiStatVals *svp[24];
[09] int  lct = 99, tix = 0;
[10] [11] main(int argc, char **argv)
[12] {
[13]     uname(&uname_struct);
[14]     strcpy(host, uname_struct.nodename);
[15]     if (argc > 1)
[16]         strcpy(host, argv[1]);
```

```

[17]     if (!(rsh = RSiInitx(1)))
[18]     {
[19]         fprintf(stderr, "Unable to initialize RSI interface\n");
[20]         exit(98);
[21]     }
[22]     if (RSiOpenx(rsh, 100, 2048, host, feeding, resync, NULL))
[23]     {
[24]         if (strlen(RSiEMsg))
[25]             fprintf(stderr, "%s", RSiEMsg);
[26]         fprintf(stderr, "Error contacting host \"%s\"\n", host);
[27]         exit(-99);
[28]     }
[29]     signal(SIGINT, must_exit);
[30]     signal(SIGTERM, must_exit);
[31]     signal(SIGSEGV, must_exit);
[32]     signal(SIGQUIT, must_exit);
[33]
[34]     strcpy(aphath, "hosts/");
[35]     strcat(aphath, host);
[36]     strcat(aphath, "/");
[37]     lststats(aphath);
[38]     RSIClosex(rsh);
[39]     exit(0);
[40] } The following lines (29-32) make sure that the program detects any attempt to kill or
terminate it.
If this happens, the function must_exit is invoked. This function has the sole purpose of
making sure the
association with the xmtopas daemon is terminated. It does this as shown in the following piece
of code:
void must_exit() {     RSIClosex(rsh);     exit(-9); }

```

Finally, lines 34 through 36 prepare an initial value path name for the main processing loop of the data-consumer program. This is the method followed to create the value path names. Then, the main processing loop in the internal **lststats** function is called. If this function returns, issue an **RSIClosex** call and exit the program.

## Defining a Statset

Eventually, you want the sample of the data-consumer program to receive data feeds from the **xmtopas** daemon. Thus, start preparing the **SpmiStatSet**, which defines the set of statistics with which you are interested. This is done with the **RSiCreateStatSetx** subroutine.

```

[01] void lststats(char *basepath)
[02] {
[03]     struct SpmiStatSet *ssp;
[04]     char    tmp[128];
[05]
[06]     if (!(ssp = RSiCreateStatSetx(rsh)))
[07]     {
[08]         fprintf(stderr, "RsiCons1 can't create StatSet\n");
[09]         exit(62);
[10]     }
[11]
[12]     strcpy(tmp, basepath);
[13]     strcat(tmp, "CPU/cpu0");
[14]     if ((tix = addstat(tix, ssp, tmp, "cpu0")) == -1)
[15]     {
[16]         if (strlen(RSiEMsg))
[17]             fprintf(stderr, "%s", RSiEMsg);
[18]         exit(63);
[19]     }
[20]
[21]     RSiStartFeedx(rsh, ssp, 1000);
[22]     while(TRUE)
[23]         RSiMainLoopx(499);
[24] }

```

In the sample program, the **SpmiStatSet** is created in the local **lststats** function shown previously in lines 6 through 10.

Lines 12 through 19 invoke the local function **addstat** (Adding Statistics to the Statset), which finds all the CPU-related statistics in the context hierarchy and initializes the arrays to collect and print the information. The first two lines expand the value path name passed to the function by appending CPU/cpu0. The resulting string is the path name of the context where all CPU-related statistics for cpu0 are

held. The path name has the `hosts/hostname/CPU/cpu0` format without a terminating slash, which is what is expected by the subroutines that take a value path name as an argument. The `addstat` function is shown in the next section. It uses three of the traversal functions to access the CPU-related statistics.

## Data-Consumer initialization of data feeds

The only part of the main processing function in the main section yet to explain consists of lines 21 through 23. The first line simply tells the **xmtopas** daemon to start feeding observations of statistics for an **SpmiStatSet** by issuing the **RSiStartFeedx** subroutine call. The next two lines define an infinite loop that calls the **RSiMainLoopx** function to check for incoming `data_feed` packets.

There are two more subroutines concerned with controlling the flow of data feeds from **xmtopas** daemon. Neither is used in the sample program. The subroutines are described in **RSiChangeFeedx** and **RSiStopFeedx** structures.

## Adding Statistics to the Statset

```
[01] int addstat(int ix, struct SpmiStatSet *ssp, char *path, char *txt)
[02] {
[03]     cx_handle    *cxh;
[04]     int          i = ix;
[05]     char         tmp[128];
[06]     struct SpmiStatLink *statlink;
[07]
[08]     if (!(cxh = RSiPathGetCxx(rsh, path)))
[09]     {
[10]         fprintf(stderr, "RSiPathGetCxx can't access host %s (path %s)\n", host, path);
[11]         exit(61);
[12]     }
[13]
[14]     if ((statlink = RSiFirstStatx(rsh, cxh, navn, desc)))
[15]     {
[16]         while (statlink)
[17]         {
[18]             if (i > 23)
[19]                 break;
[20]             strcpy(head1[i], txt);
[21]             strcpy(head2[i], *navn);
[22]             strcpy(tmp, path);
[23]             strcat(tmp, "/");
[24]             strcat(tmp, *navn);
[25]             if (!(svp[i] = RSiPathAddSetStatx(rsh, ssp, tmp)))
[26]                 return(-1);
[27]             i++;
[28]             statlink = RSiNextStatx(rsh, cxh, statlink, navn, desc);
[29]         }
[30]     }
[31]     return(i);
[32] }
```

The use of **RSiPathGetCxx** by the sample program is shown in lines 8 through 12. Following that, in lines 14 through 30, two subroutines are used to get all the statistics values defined for the CPU context. This is done by using **RSiFirstStatx** and **RSiNextStatx** subroutines.

In lines 20-21, the short name of the context ("`cpu0`") and the short name of the statistic are saved in two arrays for use when printing the column headings. Lines 22-24 construct the full path name of the statistics value by concatenating the full context path name and the short name of the value. This is necessary to proceed with adding the value to the **SpmiStatSet** with the **RSiPathAddSetStatx**. The value is added by using the lines 25 and 26.

## Data-Consumer decoding of data feeds

Whenever a `data_feed` is detected by the RSI interface, the data feed callback function defined in the **RSiOpenx** subroutine is invoked, passing the RSI handle as an argument to the callback function. The sample program's callback function for data feeds is shown in the following example. Most of the lines

in the function are concerned with printing headings after each 20 detail lines printed. This is in line numbers 9 through 19 and 26.

```
[01] void feeding(RSiHandlex rsh, pack *p)
[02] {
[03]     int i;
[04]     float f;
[05]     long v;
[06]
[07]     if (p->type != data_feed)
[08]         return;
[09]     if (lct > 20)
[10]     {
[11]         printf("\n\n");
[12]         for (i = 0; i < tix; i++)
[13]             printf("%08s", head1[i]);
[14]         printf("\n");
[15]         for (i = 0; i < tix; i++)
[16]             printf("%08s", head2[i]);
[17]         printf("\n");
[18]         lct = 0;
[19]     }
[20]     for (i = 0; i < tix; i++)
[21]     {
[22]         v = RSiGetValuex(rsh, svp[i]) * 10.0;
[23]         printf("%6d.%d", v/10, v%10);
[24]     }
[25]     printf("\n");
[26]     lct++;
[27] }
```

Actual processing of received statistics values is done by the lines 20-24. It involves the use of the library **RSiGetValuex** subroutine. The following is an example of output from the sample program **RsiCons1**:

```
$ RsiCons1 umbra
      cpu0      cpu0      cpu0      cpu0      cpu0      cpu0      cpu0      cpu0
      user      kern      wait      idle      uticks      kticks      wticks      iticks
      0.0        0.0        0.0      100.0        0.0        0.0        0.0      100.0
      0.0        0.0        0.0      100.0        0.0        0.0        0.0      99.9
      0.2        3.1        0.0      96.5        0.2        3.2        0.0      96.6
      3.5        5.5        1.5      89.1        3.5        5.5        1.5      89.1
      5.8        3.4        0.0      90.8        5.8        3.4        0.0      90.8
      8.8        8.3        0.1      82.5        8.8        8.3        0.2      82.5
      67.5       2.4        3.0      27.0        67.5       2.3        2.9      26.9
      16.0       0.6        0.8      82.5        16.0       0.6        0.8      82.6
      67.5       5.0        0.0      27.3        67.5       5.0        0.0      27.3
      19.0       6.1        0.9      73.8        19.1       6.1        0.9      73.8
      22.5       0.8        1.6      75.0        22.5       0.8        1.6      74.9
      60.2       6.1        0.0      33.5        60.2       6.1        0.0      33.5
$
```

## An Alternative way to decode data feeds

To know more about the data received in `data_feed` packets than what can be obtained by using the **RSiGetValuex** subroutine, you can use the library **RSiGetRawValuex** subroutine.

## Expanding the data-consumer program

A slightly more capable version of the sample program discussed in the previous sections is provided as the `/usr/samples/perfmgr/RsiCons.c` file. This program also lists the statistics with the short name `xfer` for all the disks found in the system where the daemon runs. To do so, the program uses some additional subroutines to traverse contexts.

## Traversing contexts

The `adddisk` function in the following list shows how the `RSiFirstCxx`, `RSiNextCxx`, and the `RSiInstantiatex` subroutines are combined with `RSiPathGetCxx` to make sure all subcontexts are accessed. The sample program's `addstat` internal function is used to add the statistics of

each subcontext to the SpmiStatSet structure. A programmer who wanted to traverse all levels of subcontexts below a start context could easily create a recursive function to do this.

```

01] int adddisk(int ix, struct SpmiStatSet *ssp, char *path)
02] {
03]     int    i = ix;
04]     char   tmp[128];
05]     cx_handle *cxh;
06]     struct SpmiStatLink *statlink;
07]     struct SpmiCxLink *cxlink;
08]
09]     cxh = RSiPathGetCxx(rsh, path);
10]     if ((!cxh) || (!cxh->cxt))
11]     {
12]         if (strlen(RSiEMsg))
13]             fprintf(stderr, "%s", RSiEMsg);
14]         fprintf(stderr, "RSiPathGetCxx can't access host %s (path %s)\n",
15]             host, path);
16]         exit(64);
17]     }
18]     if (rsh->pi->data.getcx.context.inst_freq == SiContInst)
19]     {
20]         if ((i = RSiInstantiatex(rsh, cxh)))
21]             return(-1);
22]     }
23]     if ((cxlink = RSiFirstCxx(rsh, cxh, navn, desc)))
24]     {
25]         while (cxlink)
26]         {
27]             strcpy(tmp, path);
28]             if (strlen(tmp))
29]                 strcat(tmp, "/");
30]             if (*navn)
31]                 strcat(tmp, *navn);
32]             if ((i = addstat(i, ssp, tmp, *navn)) == -1)
33]             {
34]                 if (strlen(RSiEMsg))
35]                     fprintf(stderr, "%s", RSiEMsg);
36]                 exit(63);
37]             }
38]             cxlink = RSiNextCxx(rsh, cxh, cxlink, navn, desc);
39]         }
40]     }
41]     return(i);
42] }

```

The output from the RsiCons program when run on the **xmtopas** daemon on an AIX operating system host is shown in the following example.

```

$ RsiCons encee

```

CPU	CPU	CPU	CPU	hdisk3	hdisk1	hdisk0	cd0
uticks	kticks	wticks	iticks	xfer	xfer	xfer	xfer
19.6	10.0	4.1	67.1	2.7	4.1	0.0	0.0
10.9	15.3	8.2	65.3	0.0	8.2	0.0	0.0
0.5	2.0	0.0	97.5	0.0	0.0	0.0	0.0
10.5	4.0	0.0	85.5	0.0	0.0	0.0	0.0
55.4	8.9	0.0	35.4	2.4	0.0	0.0	0.0
19.0	5.5	0.0	75.5	0.0	0.0	0.0	0.0
5.9	6.4	0.0	87.4	0.0	0.0	0.0	0.0
10.5	7.0	0.0	82.5	0.0	0.0	0.0	0.0
7.9	7.4	0.0	84.4	0.0	0.0	0.0	0.0
88.5	8.5	3.0	0.0	9.5	4.5	0.0	0.0
89.4	8.9	1.4	0.0	5.9	0.0	0.0	0.0
92.5	5.5	2.0	0.0	9.0	8.5	0.0	0.0
71.0	6.0	23.0	0.0	44.0	41.0	0.0	0.0
37.9	2.4	58.9	0.4	67.9	61.4	0.0	0.0
17.5	4.5	0.0	78.0	1.5	3.0	0.0	0.0
0.5	1.5	10.0	88.0	7.5	1.5	0.0	0.0

```

$

```

## Inviting data suppliers

The **RSiInvitex** subroutine allows to design programs that can present the end user with a list of potential data-supplier hosts rather than requiring the user to specify which host to monitor.

### Identifying data suppliers

The **RSiInvitex** subroutine uses one or more of the following methods to obtain the Internet Protocol (IP) addresses to which an `are_you_there` message can be sent.

The last two methods depend on the presence of the `$HOME/Rsi.hosts` file. PTX also has alternative locations of the `Rsi.hosts` file. The three ways to invite data-supplier hosts are:

1. Unless instructed not to by the user, the broadcast address corresponding to each of the network interfaces of the local host is found. The invitational message is sent on each network interface using the corresponding broadcast address. Broadcasts are not attempted on the Localhost (loopback) interface or on point-to-point interfaces such as X.25 or Serial Line Interface Protocol (SLIP) connections.
2. If a list of Internet broadcast addresses is supplied in the `$HOME/Rsi.hosts` file, an invitational message is sent on each such broadcast address. Note that if you specify the broadcast address of a local interface, broadcasts are sent twice on those interfaces. You may want to use this as a feature in order to minimize the likelihood of the invitation being lost.
3. If a list of host names is supplied in the `$HOME/Rsi.hostsfile`, the host IP address for each host in the list is looked up and a message is sent to each host. The look-up is done through a `gethostbyname()` call, so that whichever name service is active for the host where the data-consumer application runs is used to find the host address.

The `$HOME/Rsi.hosts` file has a simple layout. Only one keyword is recognized and only if placed in column one of a line. That keyword is:

`nobroadcast` and means that the `are_you_there` message should not be broadcast using method 1 shown previously. This option is useful in situations where a large number of hosts are on the network and only a well-defined subset should be remotely monitored. To say that you don't want broadcasts but want direct contact to three hosts, your `$HOME/Rsi.hosts` file might look like this:

```
nobroadcast
birte.austin.ibm.com
gatea.almaden.ibm.com
umbra
```

This example shows that the hosts to monitor do not necessarily have to be in the same domain or on a local network. However, doing remote monitoring across a low-speed communications line is unlikely to be popular; neither with other users of that communications line nor with yourself.

Be aware that whenever you want to monitor remote hosts that are not on the same subnet as the data-consumer host, you must specify the broadcast address of the other subnets or all the host names of those hosts in the `$HOME/Rsi.hosts` file. The reason is that IP broadcasts do not propagate through IP routers or gateways.

The following example illustrates a situation where you want to do broadcasting on all local interfaces, want to broadcast on the subnet identified by the broadcast address `129.49.143.255`, and also want to invite the host called `umbra`. (The subnet mask corresponding to the broadcast address in this example is `255.255.240.0` and the range of addresses covered by the broadcast is `129.49.128.0 - 129.49.143.255`.)

```
129.49.143.255
```

If the **RSiInvitex** subroutine detects that the name server is inoperational or has abnormally long response time, it returns the IP addresses of hosts rather than the host names. If the name server fails after the list of hosts is partly built, the same host may appear twice, once with its IP address and once with its host name.

The execution time of the **RSiInvitex** subroutine depends primarily on the number of broadcast addresses you place in the \$HOME/Rsi.hosts file. Each broadcast address increases the execution time with roughly 50 milliseconds plus the time required to process the responses. The minimum execution time of the subroutine is roughly 1.5 seconds, during which time your application only gets control if callback functions are specified and if packets arrive that must be given to those callback functions.

## A Full-Screen, character-based monitor

This program uses the API and the curses programming interface to create a screen full of statistics.

Another sample program written to the data-consumer API is the chmon program. Source code to the program is in /usr/samples/perfmgr/chmon.c file. The chmon program is also stored as an executable during the installation of the Manager component. An example program follows:

```
Data-Consumer API      Remote Monitor for host      Tue Apr 14 09:09:05
1992
CHMON Sample Program      ***  birte  ***      Interval:      5 seconds

% CPU
Kernel  13.3  |####|
User    23.7  |#####|
Wait    6.5   |##|
Idle    56.1  |#####|

EVENTS/QUEUES  FILE/TTY
Pswitch 1295  Readch 24589
Syscall 6173  Writech 1646
Reads   487   Rawin   0
Writes  143   Ttyout 106
Forks   1     Igets  1763
Execs   1     Namei  809
Runqueue 1   Dirblk 174
Swapqueue 0  Reads  48
Writes  143

PAGING counts  PAGING SPACE  REAL MEM  48MB
Faults  131   % Used  33.7  % Comp  68.0
Steals   0   % Free  66.2  % NonComp 15.0
Reclaim  0   Size,MB  96   % Client  4.0

NETWORK  Read  Write
ACTIVITY KB/sec KB/sec
lo0      1.1  1.1
tr0      1.1  0.0

PAGING page/s  DISK      Read  Write  %
Pgspin  0     ACTIVITY KB/sec KB/sec Busy
Pgspout 0     hdisk0   0.0   35.1  15.7
Pagein  0     hdisk1   0.0   0.0   0.0
Pageout 11    hdisk2   0.0   9.5   3.5
Sios    10    cd1      0.0   0.0   0.0

Process wait      (514)  %cpu 63.2, PgSp: 0.0mb, uid:
Process xlcentry  (12657) %cpu 58.0, PgSp: 1.1mb, uid: birte
Process make      (21868) %cpu 15.0, PgSp: 0.2mb, uid: birte
Process make      (5998)  %cpu 15.0, PgSp: 0.1mb, uid: birte
```

The chmon command line is:

```
chmon[-iseconds_interval][-pno_of_processes][hostname>]
```

Item	Descriptor
seconds_interval	Is the interval between observations. Must be specified in seconds. No blanks must be entered between the flag and the interval. Defaults to 5 seconds.
no_of_processes	Is the number of “hot” processes to be shown. A process is considered “hotter” the more CPU it uses. No blanks must be entered between the flag and the count field. Defaults to 0 (no) processes.
hostname	Is the host name of the host to be monitored. Default is the local host. The sample program exits after 2,000 observations have been taken, or when you type the letter “q” in its window.

## List of RSI Error Codes

All RSI subroutines use constants to define error codes.

The RSI Error Code table lists the error descriptions.

<b>Symbolic Name</b>	<b>Number</b>	<b>Description</b>
RSiTimeout	280	A time-out occurred while waiting for a response to a request.
RSiBusy	281	An RSiOpenx subroutine was issued, but another is already active.
RSiSendErr	282	An error occurred when the library attempted to send a UDP packet with the sendto() system call.
RSiPollErr	283	A system error occurred while issuing or processing a poll() or select() system call.
RSiRecvErr	284	A system error occurred while attempting to read an incoming UDP packet with the recvfrom() system call.
RSiSizeErr	285	A recvfrom() system call returned a UDP packet with incorrect length or incorrect source address.
RSiResync	286	<p>While waiting for a response to an outgoing request, one of the following occurred and cause an error return to the calling program:</p> <ol style="list-style-type: none"> <li>1. An error occurred while processing an exception packet.</li> <li>2. An error occurred while processing an i_am_back packet.</li> <li>3. An i_am_back packet was received in response to an output request other than are_you_there.</li> <li>4. While waiting for a response to an outgoing request, some asynchronous function closed the handle for the remote host.</li> </ol> <p>The code may also be set when a success return code is returned to the caller, in which case it shows that either an exception packet or an i_am_back packet was processed successfully while waiting for a response.</p>
RSiBadStat	287	A bad status code was received in the data packet received.

<b>Symbolic Name</b>	<b>Number</b>	<b>Description</b>
RSiBadArg	288	An argument that is not valid was passed to an RSi subroutine.
RSiBadHost	289	A valid host address cannot be constructed from an IP address or the nameservice doesn't know the hostname.
RSiDupHost	290	An <b>RSiOpenx</b> call was issued against a host but a connection is already open to a host with this IP address and a different hostname.
RSiSockErr	291	An error occurred while opening or communicating with a socket.
RSiNoPort	292	The RSi is unable to find the port number to use when inviting remote suppliers. The likely cause is that the xmquery entry is missing from the /etc/services file or the NIS (Yellow Pages) server.

Symbolic Name	Number	Description
RSiNoMatch	293	<p>One of the following occurred:</p> <ol style="list-style-type: none"> <li>1. The <code>SpmiStatVals</code> argument on the <b>RSiStatGetPathx</b> call is not valid.</li> <li>2. On an <b>RSiPathAddSetStatx</b> call, the <code>SpmiStatSet</code> argument is not valid or the path name given in the last argument does not exist.</li> <li>3. On an <b>RSiAddSetHotx</b> call, the <code>SpmiHotSet</code> argument is not valid, the grand parent context doesn't exist or none of its subcontexts contain the specified statistic.</li> <li>4. On an <b>RSiDelSetStatx</b> call, the <code>SpmiStatSet</code> or the <code>SpmiStatVals</code> argument is not valid.</li> <li>5. On an <b>RSiDelSetHotx</b> call, the <code>SpmiHotSet</code> or the <code>SpmiHotVals</code> argument is not valid.</li> <li>6. On an <b>RSiPathGetCxx</b> call, the path name given does not exist. On an <b>RSiGetValuex</b> or <b>RSiGetRawValuex</b> call, the <code>SpmiStatVals</code> argument is not valid.</li> <li>7. On an <b>RSiGetHotItemx</b> call, the <code>SpmiHotSet</code> argument was not valid.</li> </ol>
RSiInstErr	294	An error was returned when attempting to instantiate a remote context.
RSiNoFeed	295	When extracting a data value with the <b>RSiGetValuex</b> call, the data value was marked as not valid by the remote data supplier.
RSiTooMany	296	An attempt was made to add more values to a statset than the current buffer size permits.
RSiNoMem	297	Memory allocation error.
RSiNotInit	298	An <b>RSi</b> call was attempted before an <b>RSiInitx</b> call was issued.
RSiNoLicense	299	License expired or no license found.

Symbolic Name	Number	Description
RSiNotSupported	300	The subroutine call requires a later protocol version that is the one supported by the remote system's <b>xmtopas</b> daemon.

## The nmon recording tool

---

The nmon recording tool can record various performance metrics that are related to the logical partition (LPAR) and the Virtual I/O Server (VIOS).

You can use nmon tool to enable or disable recording of the performance metrics depending on the requirements. In the recording mode, the **nmon** command generates the nmon files. You can view these files directly by opening them or by using post processing tools such as the nmon analyzer. After the recording starts in the nmon tool, the tool disconnects from the shell that initiated the recording and ensures that the tool continues to run even if you log out of the AIX user session.

### Asynchronous I/O statistics

The PROCAIO section of the nmon recording file contains the asynchronous I/O process statistics for the background processes.

The section that has the prefix PROCAIO provides the asynchronous I/O statistics. You can use the **-A** option to enable recording of this statistics. When synchronous I/O occurs, the application cannot be processed until the I/O operation is complete. In contrast, asynchronous I/O operations are run as the background processes and do not block user applications. The asynchronous I/O operations and application processing can run in parallel. Therefore, the performance is improved.

The PROCAIO section contains the following fields:

**aioprocs**

Total number of asynchronous I/O processes that are running.

**aiorunning**

Number of asynchronous I/O processes that are using more than 0.1% of CPU.

**aiocpu**

Total CPU consumption by Asynchronous I/O processes per second.

### nmon recording tool commands

This section contains the command outputs of different AIX commands that are run by the nmon tool during the recording.

These values are recorded only once during the first iteration of the nmon recording. The BBB\* sections are available in the memory, network, processor, and I/O statistics. The following sections in the nmon recording file are used to identify the command execution details:

**BBBB**

This section provides disk configuration details for all the disks in the partition. This section contains the following fields:

**name**

Hard disk name.

**Size**

Size of the hard disk in GB.

**Disk attach type**

Type of disk. The disk type can be serial-attached SCSI (SAS), virtual SCSI (vSCSI), or Fibre Channel (FC) disk.

**BBBC**

This section provides detailed configuration information about each hard disk by executing the following command:

```
lspv -l hdisk*
```

**BBBV**

This section provides volume group configuration details. This section displays the output of the following command:

```
lsvg -L |lsvg -Li
```

**BBBP**

This section provides configuration details and performance statistics by displaying the output of set of commands that are executed during a time interval. The commands are executed in the following format: *<command name> <Parameters>*. This format represents the command that was run to get the output for this section. For details about the fields that are displayed in the command output, refer to the corresponding command man pages. The list of commands that are run by the nmon tool follows:

<i>Table 11. List of commands</i>	
<b>Command</b>	<b>Description</b>
/usr/bin/uptime	Recorded always.
/usr/sbin/lscconf	Recorded always.
/usr/sbin/lspcs -a	Recorded always.
/usr/bin/lparstat -i	Recorded always.
/usr/bin/emstat -a 1 2	Recorded always.
/usr/bin/mpstat -d	Recorded always.
/usr/sbin/lssrad -av	Recorded always.
/usr/sbin/vmo -F -L	Recorded always.
/usr/sbin/iao -F -L	Recorded only for AIX 6.1.
/usr/sbin/schedo -F -L	Recorded only for AIX 6.1.
/usr/sbin/no -F -L	Recorded only for AIX 6.1.
/usr/sbin/nfso -F -L	Recorded only when the following conditions are met: <ul style="list-style-type: none"> <li>• Network File System (NFS) data collection is enabled.</li> <li>• Recorded only for AIX 6.1, and later.</li> </ul>

<i>Table 11. List of commands (continued)</i>	
<b>Command</b>	<b>Description</b>
<code>/usr/sbin/vmo -L</code>	Recorded only for AIX operating system version other than 6.1.
<code>/usr/sbin/ioo -L</code>	Recorded for AIX operating system version other than 6.1.
<code>/usr/sbin/schedo -L</code>	Recorded for AIX operating system version other than 6.1.
<code>/usr/sbin/nfso -L</code>	Recorded only when the following conditions are met: <ul style="list-style-type: none"> <li>• Network File System (NFS) data collection is enabled.</li> <li>• Recorded only for AIX 6.1, and later.</li> </ul>
<code>/usr/bin/ipcs -a</code>	Recorded always.
<code>/usr/bin/vmstat -v</code>	Recorded always.
<code>/usr/bin/vmstat -s</code>	Recorded always.
<code>/usr/bin/vmstat -i</code>	Recorded only when NFS data collection is enabled.
<code>/usr/sbin/nfsstat -n</code>	Recorded only when NFS data collection is enabled.
<code>/usr/sbin/wlmcntrl -q</code>	Recorded always.
<code>cat /etc/wlm/current/classes</code>	Recorded always.
<code>cat /etc/wlm/current/rules</code>	Recorded always.
<code>cat /etc/wlm/current/limits</code>	Recorded always.
<code>cat /etc/wlm/current/shares</code>	Recorded always.
<code>/usr/sbin/mount</code>	Recorded always.
<code>/usr/sbin/lsattr -El aio0</code>	Recorded always.
<code>/usr/bin/oslevel -rq</code>	Recorded always.
<code>/usr/bin/oslevel -s</code>	Recorded always.
<code>/usr/bin/ps v</code>	Recorded always.

Table 11. List of commands (continued)	
Command	Description
<code>/usr/bin/df -m</code>	Recorded only when Journaled File System (JFS) data collection is disabled.
<code>/etc/ifconfig -a</code>	Recorded always.
<code>/usr/bin/netstat -rn</code>	Recorded always.

### BBBP\*\* continued

Commands that are related to shared storage pool (SSP) are executed if SSP data collection is not enabled explicitly. You can use the **-ysub=ssp** option to enable SSP data collection. This section contains the following fields:

#### **/usr/sbin/lscluster -m**

Displays the output of the **lscluster -m** command that provides the details of the cluster and the nodes that belong to the cluster.

#### **/usr/ios/cli/ioscli lssp -clustername**

Displays the output of the **lssp -clustername <clustername>** command that provides the details of the shared storage pool that belong to the cluster.

**Note:** Complete I/O server command line interface (ioscli) path of the command is specified in the root mode of VIOS.

#### **/usr/ios/cli/ioscli lssp -clustername -sp -bd**

Provides the logical unit (LU) details of the shared storage pool. An example command follows:

```
lssp -clustername <clustername> -sp <SSP_name> -bd
```

**Note:** Complete I/O server command line interface (ioscli) path of the command is specified in the root mode of VIOS.

#### **Physical location <-> PartitionNumber:MTM**

Provides the following details for all backing devices of the VIOS:

- Physical location of the backing device.
- Virtual I/O client partition ID to which the device is mapped to.
- Machine Type Model (MTM) number of that device.

#### **Client-Id : MTM <-> VTD**

Provides the following mapping information for all virtual target devices:

- VIOS client partition ID.
- MTM number.
- Virtual Target Device (VTD) name.

#### **VTD <-> BACKING DEVICE**

Provides the following mapping information for all virtual target devices:

- Virtual target device name.
- *<Backing device name>.<unique device identifier>*

### BBBP, Disk Statistics

This section indicates the beginning of the section for the list of SSP disks. This section is the continuation of the SSP section that is recorded by default when the **-y sub=ssp** option is not specified explicitly. This section contains the following fields:

#### **Disk Name**

SSP disk name.

**Capacity**

Size of the SSP disk in bytes.

**Udid**

Unique device identifier for the SSP disk.

**BBBBP, Disk Name Capacity Udid**

This section is recorded separately for each SSP disk in the NMON recording file. This section contains the following fields:

**Disk Name**

SSP disk name.

**Capacity**

Size of the SSP disk in bytes.

**Udid**

Unique device identifier for the SSP disk.

**/usr/sbin/emgr -l**

Lists the interim fixes that are installed.

## I/O statistics

The I/O statistics section in the nmon recording file contains statistics about disk, disk adapter, Enterprise Storage Server (ESS) disks, disk groups, and file system.

The following sections in the nmon recording file are used to identify the I/O statistics:

<i>Table 12. Sections for I/O statistics</i>	
<b>Section</b>	<b>Description</b>
FILE	<p>Records statistics for different file I/O operations. This statistics is recorded by default. This section contains the following fields:</p> <p><b>iget</b> Number of inode lookup operations per second.</p> <p><b>namei</b> Number of vnode operations by using the path name per second.</p> <p><b>dirblk</b> Number of 512-byte block read operations by the dictionary search routine to locate an entry for a file per second.</p> <p><b>readch</b> Number of characters that are transferred by using read system calls per second.</p> <p><b>writetech</b> Number of characters that are transferred by using write system calls per second.</p> <p><b>tttyrawch</b> Number of raw input characters.</p> <p><b>tttycanch</b> Number of canonical input characters.</p> <p><b>tttyoutch</b> Number of raw output characters.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
DISK	<p>Records I/O statistics for each disk. This statistics is recorded by default. For every disk , the same set of tags on DISK* are repeated. Disk metrics are displayed in the following generic format:</p> <pre data-bbox="641 352 1166 384">DISK*,&lt;Description&gt; &lt;runname&gt;, &lt;diskname&gt;</pre> <p>A sample DISK metric might be similar to the below example:</p> <pre data-bbox="641 468 1242 499">&lt;runname&gt;, &lt;diskname&gt; &lt;diskname1&gt;,...&lt;disknameN&gt;</pre> <p>Where &lt;diskname1&gt;...&lt;disknameN&gt; represents the list of disk names present in the LPAR or VIOS. This section contains the following metrics:</p> <p><b>DISKBUSY, Disk %Busy</b> Percentage of time during which the disk is active.</p> <p><b>DISKREAD, Disk Read KB/s</b> Total read operations from the disk in KBs per second.</p> <p><b>DISKWRITE, Disk Write KB/s</b> Total write operations to the disk in KBs per second.</p> <p><b>DISKXFER, Disk transfers per second</b> Number of transfers per second.</p> <p><b>DISKRXFER, Transfers from disk (reads) per second</b> Number of read transfers per second.</p> <p><b>DISKBSIZE, Disk Block Size</b> Total number of disk blocks that are read and written over the interval.</p> <p><b>DISKRIO, Disk IO Reads per second</b> Number of disk read I/O transfers per second.</p> <p><b>DISKWIO, Disk IO Writes per second</b> Number of disk write I/O transfers per second.</p> <p><b>DISKAVGRIO, Disk IO Average Reads KBs/xfer</b> Average number of KBs that are read from the disk per read I/O operation.</p> <p><b>DISKAVGWIO, Disk IO Average Writes KBs/xfer</b> Average number of KBs that are written to the disk per write I/O operation.</p> <p><b>DISKSERV Disk Service Time msec/xfer</b> Average disk I/O service time per transfer in milliseconds.</p> <p><b>DISKREADSERV, Disk Read Service Time msec/xfer</b> Average read disk service time per transfer in milliseconds.</p> <p><b>DISKWRITESERV, Disk Write Service Time msec/xfer</b> Average write disk service time per transfer in milliseconds.</p> <p><b>DISKWAIT, Disk Wait Queue Time msec/xfer</b> Average time spent in the disk wait queue per transfer in milliseconds.</p> <p>If the number of service requests are greater than disk queue depth, then the requests are moved to the wait queue. This metric provides the time taken by the I/O requests in the wait queue.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
IOADAPT	<p>Records disk adapter statistics. This statistics is based on the average of all the disks connected to the adapter and the MPIO links connected to this adapter. This statistics is recorded by default. This section contains the following fields:</p> <p><b>&lt;AdapterName&gt;_read-KB/s</b> Total read operations from the adapter in KBs per second.</p> <p><b>&lt;AdapterName&gt;_write-KB/s</b> Total writes to the adapter in KBs per second.</p> <p><b>&lt;Adaptername&gt;_xfer-tps</b> Total I/O transfers on the adapter per second.</p>
BBBD	<p>Records disk adapter configuration details. An example recording configuration information follows:</p> <pre data-bbox="621 688 1469 829"> BBBD,0000, Disk Adapter Information : &lt;Description of BBBD&gt;. BBBD,000, Disk Adapter Information, &lt;hostname&gt; BBBD,001, Adapter_number, Name, Disks, Description BBBD,002, &lt;values corresponding to the header in BBBD 001&gt; </pre> <p>This section is displayed only once in the nmon recording file.</p> <p><b>Note:</b> Dynamic configuration changes are not displayed in this section.</p> <p>This statistics is recorded by default. You can use the <b>-D</b> option to disable the recording of the BBBD section. This section contains the following fields:</p> <p><b>Adapter_number</b> Index created by the nmon tool for the adapter.</p> <p><b>Name</b> Name of the disk adapter.</p> <p><b>Number</b> Number of disks attached to the disk adapter including MPIO disks.</p> <p><b>Description</b> Description of the adapter as specified in the Object Data Manager(ODM), catalog.</p>
ESS	<p>Records IBM TotalStorage® ESS device statistics. This statistics is recorded by default if ESS disks are present. This sections contains following fields:</p> <p><b>ESSREAD, ESS Logical Disks read KB/s</b> Total KBs of data that is read from ESS virtual paths per second.</p> <p><b>ESSWRITE, ESS Logical Disks write KB/s</b> Total KBs of data written to ESS virtual paths per second.</p> <p><b>ESSXFER, ESS Logical Disks Transfers</b> Total number of transfers per second on the ESS paths.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
BBBE	<p>Records ESS configuration details for all ESS virtual paths. An example of this section follows:</p> <p><b>BBBE, 000, ESS vpath Logical Disks</b> Records ESS virtual path.</p> <p><b>BBBE, 001, &lt;Config details&gt;</b> This provides configuration detail for each and every ESS virtual path. This is recorded by default and can be skipped with option -E.</p> <p>This section is recorded only once in the ESS statistics recording. This section provides configuration details for every ESS virtual path. This statistics is recorded by default. You can use the <b>-E</b> option to disable the recording of this section. This section contains the following fields:</p> <p><b>Number</b> Index of virtual path.</p> <p><b>SizeMB</b> Size of the ESS virtual path.</p> <p><b>Name</b> Name of the virtual path.</p> <p><b>Disks</b> Number of disks that belong to this ESS virtual path.</p> <p><b>hdisks</b> List of disk names that belong to this ESS path.</p>
BBBSSP	<p>Records shared storage pool (SSP) information. SSP information is recorded only if SSP statistic collection is enabled. You can use the <b>-y sub=ssp</b> option to enable this statistics.</p> <p><b>Note:</b> SSP provides distributed storage access to all VIOS logical partitions in a cluster. All the VIOS logical partitions within a cluster must have access to all the physical volumes in a shared storage pool.</p> <p>This section contains the following fields:</p> <p><b>Cluster Name</b> Name of the SSP cluster.</p> <p><b>Pool Name</b> SSP name of the partition number of the VIOS client.</p> <p><b>Pool Size</b> SSP size in MBs.</p> <p><b>Pool Used</b> Percentage of SSP usage over the total shared storage size.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
BBBSSP_CLIENT	<p>Records the SSP client and logical unit mapping statistics. This section contains the following fields:</p> <p><b>PoolName_ClientId</b> SSP name and partition number of the VIOS client joined by delimiter _.</p> <p><b>Machine Type Model (MTM)</b> Machine type and model of the SSP client.</p> <p><b>LU Size Used</b> Physical usage of logical unit in MBs.</p> <p><b>Note:</b> Logical unit is a file-backed storage device that is located in the cluster file system of the shared storage pool.</p>
BBBSSP Fibre Channel adapter	<p>Records Fibre Channel adapter statistics in the following format:</p> <pre data-bbox="641 714 1079 819">BBBF, FC Adapter stats, FCs found, &lt;number of Fiber channel Adapters&gt; &lt;List of all the Fiber Channel adapters names&gt;</pre> <p>You can use ^ option to enable recording of this statistics. Following are fields displayed in this section:</p> <p><b>BBBF, FC_&lt;index&gt;, &lt;FC Adapter Name&gt;, fcstat command output</b> This field is listed for each and every Fibre Channel adapters.</p>
BBBSSP Fibre Channel adapter utilization	<p>Records the utilization statistics of the Fibre Channel adapter. This section contains the following fields:</p> <p><b>FCREAD, Fibre Channel Read KB/s, &lt;FCNAMES&gt;</b> Total data in KB that is read on the adapter per second.</p> <p><b>FCWRITE, Fibre Channel Write KB/s</b> Total amount of data in KB that is written to the adapter per second.</p> <p><b>FCXFERIN, Fibre Channel Transfers In/s</b> Total number of read requests per second on the adapter.</p> <p><b>FCXFEROUT, Fibre Channel Transfers Out/s</b> Total number of write requests per second on the adapter.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
BBBVFC, Virtual Fiber Channel Adapter Information	<p>Records N_Port ID Virtualization (NPIV) configuration details. The NPIV is an industry-standard technology that configures an NPIV capable Fibre Channel adapter with multiple, virtual worldwide port names (WWPNs). This technology is also called as virtual Fibre Channel. Virtual Fibre Channel is a method to securely share a physical Fibre Channel adapter among multiple Virtual I/O Servers.</p> <p>The metrics of this section have following suffix:</p> <pre>BBBVFC,&lt;Metrics list&gt;</pre> <p>Run the following command to print all these configuration details:</p> <pre>lsmap -all -npiv</pre> <p>If the Fiber Channel statistics are enabled by using the <b>^</b> option, this section is also recorded. This section contains the following fields:</p> <p><b>vfchost name</b> Virtual Fibre Channel host adapter name.</p> <p><b>client name</b> Name of the client partition that has the virtual Fibre Channel adapter.</p> <p><b>WWPN</b> Worldwide port number.</p> <p><b>FC Adapter Name</b> Fibre Channel port name.</p>
NPIV, Virtual FC Adapter, <metrics list>	<p>Records NPIV utilization statistics. This section contains the following fields:</p> <p><b>&lt;NPIV_Name&gt;_ read-KB/s</b> Total amount of data in KB that is read per second on this adapter.</p> <p><b>&lt;NPIV_Name&gt;_ write-KB/s</b> Total amount of data in KB that is written to this adapter.</p> <p><b>&lt;NPIV_Name&gt;_ reads/s</b> Number of read requests per second on this adapter.</p> <p><b>&lt;NPIV_Name&gt;_ writes/s</b> Number of write requests per second on this adapter.</p> <p><b>&lt;NPIV_Name&gt;_ port_speed</b> Speed of this adapter in GB per second.</p>
BBBVG	<p>Records volume group configuration details in the following format: BBBVG, 000, &lt;Volume group name&gt;, &lt;number of disks&gt;. This section is recorded for each volume group. You can use the <b>-V</b> option to enable the recording of these statistics. This section contains the following fields:</p> <p><b>Volume Group Name</b> Name of the volume group.</p> <p><b>Number of Disks</b> Number of disks or physical volumes that belong to the volume group.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
VG*	<p>Records volume group statistics. Each metric is recorded for all volume groups that are present on the LPAR. This section contains the following fields:</p> <p><b>VGBUSY, Disk Busy Volume Group, &lt;list of volume groups&gt;</b> Average busy time of all disks in the volume group.</p> <p><b>VGREAD, Disk Read KB/s Volume Group, &lt;list of volume groups&gt;</b> Total data in KB that is read per second by all disks in the volume group.</p> <p><b>VGWRITE, Disk Write KB/s Volume Group, &lt;list of volume groups&gt;</b> Total data in KB written per second by all disks in the volume group.</p> <p><b>VGXFER, Disk Xfer Volume Group, &lt;list of volume groups&gt;</b> Total amount of transfer of data in KB/s by all the disks that belong to this volume group.</p> <p><b>VGSIZE, Disk Size KB Volume Group, &lt;list of volume groups&gt;</b> Block size that is read or written to the disk per transfer in KB per second.</p>
DG*	<p>Records disk group statistics. Multiple disks can be monitored by grouping them. You must create a group configuration file that contains the following information:</p> <pre data-bbox="641 1123 1453 1197"> &lt;Group_name1&gt; &lt;disk_name1&gt; &lt;disk_name2&gt; .... &lt;Group_name2&gt; &lt;disk_nameA&gt; &lt;disk_nameB&gt; ... </pre> <p>In the example, &lt;Group_name1&gt; is the name of the first disk in the group; &lt;disk_name1&gt; and &lt;disk_name2&gt; are the first and second disks in the group.</p> <p>You can use <b>-g</b> option to enable the recording of these statistics. This section contains the following fields:</p> <p><b>BBBG, &lt;number&gt;, diskgroupname, &lt;disknames&gt;</b> The disk group name for which the statistics is recorded and all the disks that belong to this disk group.</p>

Table 12. Sections for I/O statistics (continued)

Section	Description
Disk Group	<p>Records disk group utilization statistics. Following are the fields in this section:</p> <p><b>DGBUSY, Disk Group Busy, &lt;hostname&gt;, &lt;disk group name&gt;</b> Average busy time of all disks in the disk group.</p> <p><b>DGREAD, Disk Group Read KB/s, &lt;hostname&gt;, &lt;disk group name&gt;</b> Total data in KB that is read per second by all disks that belong to the disk group.</p> <p><b>DGWRITE, Disk Group Write KB/s, &lt;hostname&gt;, &lt;disk group name&gt;</b> Total data in KB that is written per second by all disks that belong to the disk group.</p> <p><b>DGSIZE, Disk Group Block Size KB, &lt;hostname&gt;, &lt;disk group name&gt;</b> Block size that is read or written to the disk per transfer in KB per second.</p> <p><b>DGXFER, Disk Group Transfers/s, &lt;hostname&gt;, &lt;disk group name&gt;</b> Total transfers per second by all disks that belong to this volume group.</p>
JFS*	<p>Records the Journaled File System (JFS) statistics. The proc file system is not recorded because it is a pseudo file system. JFS statistics are recorded by default. This section contains the following fields:</p> <p><b>JFSFILE, JFS Filespace %Used, JFS names</b> Percentage of file space used by this JFS over the total space allocated to it.</p> <p><b>JFSINODE, JFS Inode %Used, JFS list</b> Percentage of inode usage by the JFS over the total inode files present on the LPAR.</p>

## Kernel statistics

The PROC section of the nmon recording file contains kernel statistics.

Kernel statistics is enabled by default. Following fields are available in the kernel statistics section:

### Runnable

Number of runnable processes that are ready to run per second in the run queue. The run queue is maintained by the process scheduler and contains the list of threads that are ready to be dispatched.

### Swap-in

Length of the swap queue per second, which means the number of ready processes that are waiting to be paged-in per second. The swap queue contains the list of processes that are ready to run but are swapped out with the currently running processes.

### pswitch

Number of process context switches per second.

### syscall

Number of system calls that are run per second.

**read**

Number of read system calls that are run per second.

**write**

Number of write system calls that are run per second.

**fork**

Number of fork system calls that are run per second.

**exec**

Number of exec system calls that are run per second.

**sem**

Number of Inter Process Communication (IPC) semaphore operations that are run per second.

**msg**

Number of IPC message operations that are run per second.

**asleep\_bufio**

Number of processes that are in sleep state and are waiting for buffered I/O operation to complete at a particular time.

**asleep\_rawio**

Number of processes that are sleeping and waiting for raw I/O operations at a particular time. Raw I/O operation allows applications to perform a direct write operation to the Logical Volume Manager (LVM) layer.

**asleep\_diocio**

Number of processes that are in sleep state and are waiting for direct file system I/O operations and concurrent I/O operations at a particular time.

## Memory statistics

The memory statistics contain the memory-specific information and metrics.

The following sections in the nmon recording file are used to identify the memory statistics:

**MEM**

Provides statistics on the global memory utilization. This statistic is recorded by default. This section contains the following fields:

**Real free %**

Percentage of available physical RAM as against the total available RAM.

**Virtual free %**

Percentage of available paging space as against the total paging space that is allocated.

**Real free (MB)**

Available RAM space in MB.

**Virtual free (MB)**

Available paging space in MB.

**Real total (MB)**

Total physical RAM in MB.

**Virtual total (MB)**

Total paging space size in MB.

**Physical (MB)**

Physical memory, in MB, that is allocated to the shared memory partitions from the shared memory pool at a specific time.

**Note:** This field is displayed only for an Active Memory Sharing (AMS) partition.

**Size of the compressed pool (MB)**

Size of the compressed pool.

**Note:** This field is displayed only for the Active Memory Expansion (AME)-enabled partition.

**Size of true memory (MB)**

Size of physical memory in MBs without applying the expansion factor.

**Note:** This field is displayed only in the Active Memory Expansion (AME)-enabled partition.

**Expanded memory size (MB)**

Logical memory size with expansion factor that is applied on the physical memory. The value of this field is the product of physical memory and expansion factor.

**Note:** This field is displayed only in the Active Memory Expansion (AME)-enabled partition.

**Size of the uncompressed pool (MB)**

Size of the uncompressed memory pool in MB.

**Note:** This field is displayed only in the Active Memory Expansion (AME)-enabled partition.

**MEMAMS**

Provides AMS-specific statistics.

**Pool id**

Shared memory pool ID.

**Weight**

Memory weight that is assigned to each LPAR. This field helps hypervisor to assign memory to each LPAR when the physical memory is over-committed. Memory weight is the amount of memory assigned to a LPAR.

**Hypervisor Page-in/s**

Number of hypervisor page-in operations per second. A hypervisor page-in operation occurs if a page is referenced and is not available in the real memory because the page is paged-out by the hypervisor previously.

**HypervisorTime**

Time spent in hypervisor paging operations in seconds.

**I/O Memory Entitlement(MB)**

Minimum amount of physical memory that must remain available when the partition requires it for the I/O operations irrespective of physical memory requirements by the partitions.

**I/O Memory Use(MB)**

Used I/O memory entitlement in MB.

**I/O Memory HighWater(MB)**

Highest usage of I/O memory entitlement in MB.

**Physical Memory(MB)**

Physical memory that is available for the partition's logical memory in bytes. The physical memory field is the physical memory in MB that is allocated to shared memory partitions from the shared memory pool at a specific time.

**Page Size(MB)**

Page size that is used by the hypervisor to virtualize the partition's memory.

**Page Coalesced(MB)**

Page size of the calling partitions' logical real memory in MB that is merged because the page contained duplicate data.

**Mempool Page Coalesced (MB)**

If the calling partition is authorized to access pool-wide statistics of the memory pool, this field contains the amount of logical real memory in MB that is merged. Memory is merged because the page contains duplicate data in the calling partitions' memory pool. If duplicate data is not present, this field is set to zero.

**Fraction of CPU consumed in Coalescing pages**

If the calling partition is authorized to access pool-wide statistics, the Processor Utilization Resource Register (PURR) cycles are used to merge duplicate data. If duplicate data is not present, this field is set to zero.

## MEMNEW

Provides new set of memory metrics. These details are recorded by default.

### **Process %**

Percentage of real memory that is used by the process as against the total real memory that is available in the system.

### **FScache%**

Percentage of real memory that is used by the file system cache as against the real memory.

### **System%**

Percentage of memory that is used by system segments as against the real memory.

**Note:** System segment is part of the memory segment that is accessed by the AIX kernel and kernel extensions. System segment can not be accessed by AIX processes (applications).

### **Free%**

Percentage of RAM available as against total RAM.

### **Pinned%**

Percentage of pinned memory as against the available memory. This pinned memory is the sum of the following memory segments:

- Pinned working segments.
- Pinned persistent segments.
- Pinned client segments.

### **User%**

Non-system pages are categorized as user segments. `user%` is the percentage of user segments as against the real memory.

**Note:** Non-system pages are categorized as user segments.

### **Compressed pool%**

Percentage of real memory that is used by compressed pages as against the total expanded memory available in the system.

## MEMUSE

Provides memory usage metrics. This statistics is recorded by default. This section contains the following fields:

### **%numperm**

Percentage of frames of non-computatable pages as against the real memory size.

### **%minperm**

Specifies the time until which the page-stealer steals file or computational pages regardless of repaging rates. The page-stealer targets minimum amount of memory to cache non-computational pages.

### **%maxperm**

Specifies the time after which the page-stealing algorithm steals only file pages.

### **minfree**

Specifies the minimum number of frames on the free list after which the Virtual Memory Manager (VMM) starts to steal pages to refill the free list.

### **maxfree**

Specifies the number of frames on the free list after which page-stealing stops.

### **%numclient**

Percentage of number of client frames as against the total real memory available.

### **%maxclient**

Percentage of maximum amount of memory that must be used to cache non-computational client pages.

**Note:** The `maxClient` tunable parameter specifies a limit on the maximum amount of memory that must be used to cache non-computational client pages.

**lrutable pages**

Number of pages available for processing by the Least Recently Used (LRU) algorithm.

**PAGE**

Provides paging specific metrics. This statistics is recorded by default.

**faults**

Number of page faults per second.

**pgin**

Number of page-in operations per second.

**pgout**

Number of page-out operations per second.

**pgsin**

Number of page-in operations from paging spaces per second. These values are related to the pages that are paged out.

**pgsout**

Number of page out operations from paging space per second.

**reclaims**

Number of page steals per second.

**scans**

Number of page scans per second.

**cycles**

Number of clock cycles that are used by page replacement algorithm per second.

**compressed pool pgins**

Number of page-in operations to the compressed pool per second. This metric is recorded only if active memory expansion (AME) is enabled.

**compressed pool pgouts**

Number of page-out operations from compressed pool per second.

**Note:** This metric is recorded only if AME is enabled.

**PAGING PagingSpace MB Free, <Paging SpaceName>**

Provides statistics about the amount of free paging space in MB. You can use the **-P** option to enable the recording of this section in the `nmon` recording file.

**LARGEPAGE, LARGEPAGE, Large Page Use**

Provides statistics about the large page utilization. Large pages, which have 16 MB size, are used in high-performance environments. The **-L** option enables these statistics collections in the `nmon` recording.

**Freepages**

Number of large pages on the large page free list.

**Usedpages**

Number of large pages that are in use on the system.

**Pages**

Total number of large pages on the system.

**Note:** Total number of pages is the sum of `FreePages` and `Used Pages`.

**HighWater**

Large page high water mark. High water mark is the maximum number of pages that a process had in memory at a point of time.

**SizeMB**

Size of the large memory page in MB.

## Network statistics

The network statistics section of the nmon recording file contains details on different network configurations and utilization-specific data.

The following sections in the nmon recording file are used to identify the network statistics:

### BBBN

Records the network configuration details for different network interfaces. This section contains the following fields:

#### Network Name

Name of the network interface.

#### MTU

Network frame size.

#### Mbits

Adapter rating in Mbits per second that indicates the speed of the interface. Adapter bit rate is reported as 10240 Mbits/s if the speed of the adapter is more than 10 Gb

#### Name

Description of the interface. This field value is similar to the output of the **lscfg** command.

### NET

Records the network I/O statistics. This statistic is present in every iteration and for every network interface. This section contains the following fields:

#### <interface>-read-KB/s

Amount of data in KB that is received on the interface per second.

#### <interface>-write-KB/s

Amount of data in KB that is sent on the network interface per second.

### NETPACKET

Records the network packet statistics per interface. This section contains the following fields:

#### <interface>-reads/s

Number of packets received on the interface per second.

#### <interface>-writes/s

Number of packets sent on the interface per second.

### NETSIZE

Average transfer size of the packets per interface. This section contains the following fields:

#### <interface>-readsize

Average size of the packets received on the interface. This field is the ratio of total bytes received on that interface to the total number packets received on that interface.

#### <interface>-writesize

Average size of the packets that is transmitted on that interface. This field is the ratio of total bytes transmitted on an interface to the total number packets transmitted on the interface.

### NETERROR

Provides error statistics per network interface and is similar to the data provided by the **netstat -in** command. This section contains the following fields:

#### <interface>-ierrs

Number of errors that occurred per second when data is received on the interface.

#### <interface>-oerrs

Number of errors that occurred per second when data is sent on the interface.

#### <interface>-collisions

Number of collisions per second on the interface.

**Note:** A network collision can occur when more than one interface tries to send packet on the same network segment. If you are using an Ethernet adapter, this value is always 0.

## SEA

Records the Shared Ethernet Adapter (SEA) statistics and configuration details. This section contains the following fields:

### Note:

1. If some SEAs are not available after the start of recording, those values will be recorded as 0.
2. The field is not recorded if SEA does not exist.

If errors occur, this section contains error messages. This section contains the following fields:

**BBBS, <line no >, Shared Ethernet Adapter stats, SEAs found, <#/number of SEAs>**  
Number of Shared Ethernet Adapters in the VIOS.

**BBBS, <line no>, SEA#, <seaname>**

SEA # value indicates SEA index number. Local indexing is used to identify the SEA.

**BBBS, <line no>, SEA#, <seaname>, <o.p of lsattr -Eol <seaname>>**

You can refer to the man page of the **lsattr** command to understand the detailed output of the command.

## SEA : utilization

Records SEA utilization statistics. This section contains the following fields:

**<SEA-Name>\_ read-KB/s**

Amount of data in KB that is received per second on the SEA.

**<SEA-Name>- write-KB/s**

Amount of data in KB that is transmitted per second on the SEA.

## SEAPACKET

Records utilization statistics that are related to SEA Packet. This section contains the following fields:

**<SEA -Name> -reads/s**

Number of packets that are received per second on the SEA adapter.

**<SEA -Name> -writes/s**

Number of packets that are transmitted per second on the SEA adapter.

## BBBSEA,001, <sea List>

Records list of SEAs in the VIOS. <sea list>- is a comma separated list of SEA names.

## BBBSEACONF, <line no>

Records SEA configuration Information. This section is present only once in the nmon recording file. This section contains the following fields:

**<sea\_name>\_ Large\_send**

This flag indicates the large data send option for the adapter.

**<sea\_name>\_ Large\_receive**

This flag indicates the large data receive option for the adapter.

**<sea\_name>\_Thread**

This flag indicates the threading mode for this adapter.

**<sea\_name>\_ha\_mode**

You can refer this flag to see whether high availability mode is enabled.

## BBBSEACHEC,000, Ether Channel Adapter Names BBBSEACHEC,001, <Etherchannel Names>

Records Ethernet Channel adapter names. This section is present only once in the recording file. This section contains the following fields:

### EtherChannel Names

List of ether channel adapter names.

**BBBSEACHECCONF, <line no>**

Records Etherchannel Adapter Configuration Information

**BBBSEACHECONF, <lineno>, <etherchannelname\_hash\_mode>**

Records hash mode value. This value is used by the algorithm to determine the outgoing adapter.

**BBBSEACHECONF, <line no>**

Records ether channel adapter configuration information. This section contains the following fields:

**BBSEACHECONF, <lineno>, <etherchannelname\_hash\_mode>**

The data value that will be used by the algorithm to determine the outgoing adapter.

**<sea\_name>\_Thread**

Indicates that the threading mode for this adapter.

**<sea\_name>\_ha\_mode**

Indicates that the high availability mode flag is enabled in a shared Ethernet failover setup.

**BBBSEACHPHY, 000**

Records physical adapter names. Physical adapters are used to create shared Ethernet adapters. This section is present only once in the recording file.

**BBBSEACHPHY, 001**

Physical adapters that are used to bridge at the time of creation of shared Ethernet adapters.

**BBBSEACHPHYCONF, <Line no>**

Records physical adapter configuration information. This section is recorded when `-y sub=sea` option is enabled. This section is present only once in the nmon recording file. This section contains the following fields:

**<Physical Adapter name>\_Large\_Send**

This field is used to indicate whether the option to send large data on the adapter is enabled or disabled.

**<Physical Adapter name>\_Large\_receive**

This flag is used to indicate whether the option to receive large data on the adapter is enabled or disabled.

**Note:** When this flag is set and if the adapter supports the flag, packets received by the adapter is aggregated before they are passed to the upper network layer, to achieve better performance.

**<Physical Adapter name>\_DMA\_Errors**

The number of incoming packets dropped by the hardware due to no resource error.

**Note:** This error usually occurs because the receive buffers of the adapter were exhausted. Some adapters might have the size of the receive buffer as a configurable parameter.

**<Physical Adapter name>\_Speed**

Provides media speed attribute of this adapter.

**<Physical Adapter name>\_Flow\_control**

Specifies whether the adapter must enable transmit and receive flow control.

**BBBSEACHVIR, 000**

Records virtual adapter names. You can use the `-y sub=sea` option to enable recording of this section in the nmon recording file. This will be present only once in the recording file. This section contains the following fields:

**BBBSEACHVIR, 001, <Virtual Adapter Names>**

List of virtual adapter names. Virtual Ethernet adapters allow logical partitions within the same system to communicate without having to use physical Ethernet adapters. Within the system, these adapters are connected to a virtual Ethernet switch in the hypervisor. TCP/IP communications over these adapters are routed through the server firmware. The system transmits packets by copying the packet directly from the memory of the sender LPAR to the receive buffers of the receiver LPAR without any intermediate buffering of the packet.

### **BBBSEACHVIRCONF, <line no>**

Records virtual adapter configuration Information. You can use the **-y sub=sea** option to enable recording of this section in the nmon recording file. This will be present only once in the recording file. This section contains the following fields:

#### **<Virtual Adapter Name>\_Snd\_Errors**

Number of send errors at hypervisor level.

#### **<Virtual Adapter Name>\_RscErrors**

Number of receive errors at the hypervisor level.

#### **<Virtual Adapter Name>\_invalid\_vid\_packets**

Number of packets that have invalid virtual LAN (VLAN) ID.

### **SEACHPHY**

Records the physical adapter network traffic. You can use the **-y sub=sea** option to enable recording of this section in the nmon recording file. This section contains the following fields:

#### **<physical adaptername>\_read-KB/s**

Total amount of data in KB that is received per second on the interface.

#### **<physical adaptername>\_write-KB/s**

Amount of data in KB transmitted per second on this interface.

**Note:** Value of this field is sum of total number of packets sent from the interface configured over the SEA, and total packets sent from the virtual network to the physical network.

#### **<physical adaptername>\_reads/s**

Total bytes of data received per second on the interface.

#### **<physical adaptername>\_writes/s**

Total bytes of data sent per second on the interface.

#### **<physical adaptername>\_Transmit\_Errors**

Number of errors per second during transmission on the interface.

#### **<physical adaptername>\_Receive\_Errors**

Number of errors occurred during receive operation on the interface.

#### **<physical adaptername>\_Packets\_Dropped**

Total number of packets dropped during the communication between virtual adapters and the physical adapter. This packet drop includes drops occurred while receiving the packets on the physical network and while transmitting the packets over the physical network.

#### **<physical adaptername>\_No\_ResErrors**

The number of incoming packets dropped by the hardware due to no resource error.

**Note:** This error occurs if the receive buffers on the adapter were exhausted. Some adapters have receive buffer with configurable size.

#### **<physical adaptername>\_No\_Mbuf\_Errors**

Number of incoming packets with collision errors during reception. A network collision can occur when more than one interface tries to send packet on the same network segment.

**Note:** If you are using Ethernet adapter this is always 0. Because the adapter is set to full duplex mode. If we set the adapter to auto negotiation mode, it might set the adapter to half duplex mode which leads to network collision and causes network performance issues.

### **BBBSEAC,000**

Records statistics about SEA active client adapters. This section is recorded only once in the nmon recording file.

### **BBBSEAC,001, <Sea client adapters>**

List of MAC addresses of the SEA client adapters.

### **SEACLITRAFFIC**

Records network traffic statistics of the SEA client adapters. If any specific client adapters are deleted from the list of configured adapters after the headers are written to the recording file, value for those adapters are recorded as 0. This section contains the following fields:

**<sea\_client\_mac\_name> \_read-KB/s**

Total amount of data in KB that is received per second on the adapter.

**<sea\_client\_mac\_name> \_write-KB/s**

Total amount of data in KB that is transmitted per second on the adapter.

**<sea\_client\_mac\_name> \_reads/s**

Total amount of data in bytes received per second on the adapter.

**<sea\_client\_mac\_name> \_writes/s**

Total amount of data in bytes that is transmitted per second on the adapter.

**NFS\***

Records Network File System (NFS) statistics. The NFS is a mechanism for storing files on a network. It is a distributed file system that allows users to access files and directories located on remote computers and use those files and directories as if they are local files.

**NFSSVRV2**

Records statistics related to NFS version 2 (NFSv2). This section contains the following fields:

**null**

Number of null requests to the NFSv2 server. These requests are made for checking the connectivity to a server.

**getattr**

Number of `getattr()` requests to the NFSv2. These requests are made to determine what type of file was called.

**setattr**

Number of `setattr()` requests to NFSv2 server. These calls are made to set the attributes of a file over an interval.

**root**

The number of NFS calls made to the server by the `root` user during a monitored interval.

**Lookup**

The number of filename lookup requests made by an NFS server during a monitored interval.

**readlink**

Number of `readlink()` requests to NFSv2 server. The number of calls received by a NFS server during the monitored interval.

**read**

The number of `read()` calls by a server during a monitored interval.

**wrcache**

The number of `wrcache()` calls made to a server during a monitored interval.

**write**

The number of `write()` calls made to a server during a monitored interval.

**create**

The number of file `create()` calls made to a server during the monitored interval.

**remove**

The number of `remove()` file calls made to a server during a monitoring interval.

**rename**

The number of `rename()` file calls made to a server during a monitoring interval.

**link**

The number of hard link reports made by a server during a monitored interval.

**symlink**

The number of `symlink()` calls made to a server during a monitoring interval.

**mkdir**

The number of `mkdir()` calls made to a server during a monitoring interval.

**rmdir**

The number of `rmdir()` calls made to a server during a monitoring interval.

**readdir**

The number of `readdir()` calls made to a server during a monitoring interval.

**fsstat**

The number of file statistics calls made during the monitored interval.

**NFSSVRV3**

Records statistics related to NFS version 3 (NFSv3). This section contains the following fields:

**null**

Number of null requests to the NFSv3 server. These requests are made for checking the connectivity to a server.

**getattr**

Number of `getattr()` requests to the NFSv3 server. These requests are made to determine what type of file was called.

**setattr**

Number of `setattr()` requests to NFSv3 server. These calls are made to set the attributes of a file over an interval.

**Lookup**

The number of filename lookup requests made by an NFS server during a monitored interval.

**access**

Number of file access requests made to NFS Server during monitoring interval.

**readlink**

Number of `readlink()` requests to NFSv3 server. The number of calls received by a NFS server during the monitored interval.

**read**

The number of `read()` calls by a server during a monitored interval.

**write**

The number of `write()` calls made to a server during a monitored interval.

**create**

The number of file `create()` calls made to a server during the monitored interval.

**mkdir**

The number of `mkdir()` calls made to a server during a monitoring interval.

**symlink**

The number of `symlink()` calls made to a server during a monitoring interval.

**mknod**

Number of `mknod()` calls made to a server during the monitoring interval remove The number of remove file calls made to a server during a monitoring interval.

**remove**

The number of `remove()` calls made to a server during a monitoring interval.

**rmdir**

Number of `rmdir()` calls made to a server during a monitoring interval.

**rename**

Number of `rename()` calls made to a server during a monitoring interval.

**link**

Number of hard link reports made by a server during a monitoring interval.

**readdir**

The number of `readdir()` calls made to a server during a monitoring interval.

**readdirp**

The number of `readdirp()` calls made to a server to get the the name, the file ID, attributes, and file handle.

**fsstat**

The number of file statistics calls made during the monitored interval.

**fsinfo**

The number of file system information calls made to the NFS server.

**pathconf**

The number of pathconf() calls made to the NFS server.

**commit**

The number of file commit calls made to the NFS server.

**NFSCLI2**

Records NFS client version 2 statistics. This section contains the following fields:

**null**

The number of calls generated for checking connectivity to a server.

**getattr**

The number of calls made to determine what type of file is being called.

**setattr**

The number of NFS calls made to set the attributes of a file during a monitored interval.

**root**

The number of NFS calls made to the server by the root user during a monitoring interval.

**lookup**

Number of NFS client file lookup names request.

**readlink**

Number of readlink() calls NFS client.

**read**

Number of NFS client read directory requests.

**wrcache**

Number of NFS client wrcache() calls requests.

**write**

Number of NFS client write call requests.

**create**

Number of NFS client file create call requests.

**remove**

Number of NFS client file remove requests.

**rename**

Number of NFS client file rename requests.

**link**

Number of NFS client hard link creation requests.

**link****symlink**

Number of NFS client symbolic link creation requests.

**mkdir**

Number of NFS client directory creation requests.

**rmdir**

Number of NFS client directory removal requests.

**readdir**

Number of NFS client directory read requests.

**fsstat**

Number of NFS file statistics call requests.

**NFSCLI3**

Records NFS Client Version 3 statistics. This section contains the following fields:

**null**

The number of calls generated for checking connectivity to a server.

**getattr**

The number of calls made to determine what type of file is being called.

**setattr**

The number of NFS calls made to set the attributes of a file during a monitored interval.

**lookup**

Number of NFS client file lookup names request.

**access****readlink**

Number of readlink() calls NFS client.

**read**

Number of NFS client read directory requests.

**write**

Number of NFS client write call requests.

**create**

Number of NFS client file create call requests.

**mkdir**

Number of NFS client directory creation requests.

**symlink**

Number of NFS client symbolic link creation requests.

**mknod**

Number of NFS client directory creation requests.

**remove**

Number of NFS client file remove requests.

**rmdir**

Number of NFS client directory removal requests.

**rename**

Number of NFS client file rename requests.

**link**

Number of NFS client hard link creation requests.

**readdir**

Number of NFS client directory read requests.

**readdirp**

Number of NFS client readdir plus call requests.

**fsstat**

Number of NFS file statistics call requests.

**fsinfo**

Number of NFS Client file information call requests.

**pathconf**

The number of calls by NFS client that involved path configuration (pathconf) calls to obtain configuration values for files.

**commit**

The number of file commit calls made by the NFS client.

**NFSSVRV4**

Records the NFS Version 4 statistics. This section contains the following fields:

**access**

The number of access calls made to the NFS server.

**clientid\_confirm**

The number of set clientid confirm operations on the NFS server.

**close**

Number of file close requests on the NFS Server.

**commit**

The number of file commit calls made to the NFS server.

**compound**

Number of compound calls requests to NFS server. The compound procedure consists of one or more NFS operations that were typically defined as separate RPC procedures in the previous NFS versions. This change might result in requiring fewer Remote Procedure Calls (RPCs) to perform logical file system operations over the network.

**create**

The number of file creates calls made to a server during the monitoring interval.

**delempurge**

Number of NFSv4 server purge delegation operations that are awaiting recovery.

**getattr**

Number of getattr() requests to NFS server. This call determines what type of file is used.

**delegreturn**

Number of delegreturn() operations on the NFS Server.

**getfh**

Number of get file handle requests made to the NFS server.

**link**

The number of hard link create requests made to a server during a monitoring interval.

**lock**

Number of file lock or record lock requests made to NFS server during the monitored interval.

**lockt**

Number of requests for testing specific lock on the NFS server.

**locku**

Number of requests to unlock file requests made to NFS server.

**lookup**

The number of filename Lookup requests made by an NFS server during a monitoring interval.  
lookupp Number of parent directory lookup requests made by NFS server.

**lookupp**

Number of parent directory lookupp() requests made by NFS Server

**null**

The number of calls generated for checking connectivity to a server.

**nverify**

The number of nverify operations made on the NFS Server.

**open**

Number of file open requests made to NFS Server.

**openattr**

Number of open attr operations made on NFS Server.

**open\_confirm**

Number of open confirm operations made on NFS server.

**open\_downgrade**

Number of NFS downgrade access operation done to open files on NFS server.

**operations**

Number of NFS server operations.

**putfh**

Number of put filehandle operation requests made on NFS server.

**putpubfh**

Number of requests to replace the current filehandle with the filehandle that represents the public filehandle of the name space of the server.

**putrootfh**

Number of requests to replace the current filehandle with the filehandle that represents the root of the server's name space.

**read**

Number of read operations made on NFS Server.

**readdir**

Number of directory read operations made on NFS Server.

**readlink**

Number of read symbolink read operations made on NFS server.

**release\_lock**

Number of release lock operations made on NFS Server.

**remove**

The number of Remove File calls made to a server during a monitoring interval.

**rename**

The number of Rename File calls made to a server during a monitoring interval.

**renew**

Number of renew operations made to the NFS server to renew leases which are hold.

**restorefh**

Number of restore file handle requests made to NFS server.

**savefh**

Number of requests to save file handle on NFS Server. These handles can be later restore and will be accounted as restorefh requests.

**secinfo**

Number of secinfo requests made to the server to obtain a valid RPC authentication flavors for a specific file handle, file name pair.

**setattr**

Number of setattr requests made to a NFS server to set attributes of a file.

**verify**

Number of verify requests made on NFS server. The verify operation is used to verify that attributes have a value assumed by the client before proceeding with following operations in the compound request.

**write**

Number of write requests made to NFS Server.

**NFSCLIV4**

Records NFS Client version 4 statistics. This section contains the following fields:

**access**

Number of check access right requests made by NFS client.

**acl\_read**

Number of access control list read operations made by NFS Client.

**acl\_stat\_l**

Number of access control list retrieve operations made by NFS client.

**acl\_write**

Number of write access control list operations made by NFS client.

**client\_confirm**

Number of client confirm operations made by NFS Client.

**close**

Number of Close operation request made by NFS client.

**commit**

Number of commit request made by NFS client. The COMMIT operation forces or flushes data to stable storage for the file specified by the current file handle.

**create**

Number of file create requests made by NFS client.

**delegreturn**

Number of delegation return requests made by NFS client.

**finfo**

Number client info requests for file made by NFS client.

**getattr**

Number of file get attributes requests made by NFS client.

**link**

The number of hard link create requests made by NFS client during a monitoring interval

**lock**

Number of lock requests made by NFS Client.

**lock\_test**

Number of lockT operation requests made by NFS client.

**lookup**

Number of file name lookup operation requests made by NFS client.

**mkdir**

Number of create directory operations made by NFS Client.

**mknod**

Number of mknod operations made by client.

**null**

The number of calls generated for checking connectivity to a server.

**open**

Number of open file requests made by NFS client.

**open\_confirm**

Number of open\_confirm requests made by NFS Client.

**open\_downgrade**

Number of downgrade file requests access made by NFS client.

**operations**

Number of operations requests made by NFS Client.

**pcl\_read**

Number of pcl\_read requests made by NFS client. Here client extracts numeric data from printer control language (PCL) file.

**pcl\_stat**

Number of requests to get stats on PCL files by NFS client.

**pcl\_stat\_l**

Number of requests to retrieve long PCL attributes by NFS client.

**pcl\_write**

Number of write requests on PCL made by NFS Client.

**read**

Number of read requests made by NFS client.

**readdir**

Number of directory read requests made by NFS link.

**readlink**

Number of symbolic link reqd requests made by NFS client.

**release\_lock**

Number of file lock release operations made by NFS client.

**remove**

Number of file remove requests made by NFS Client.

**rename**

Number of file rename requests made by NFS client.

**renew**

Number of renew operations made by NFS client to renew leases which are hold.

**replicate**

Number of replicate operations requests made by NFS client.

**rmdir**

Number of directory remove operation requests made by NFS client.

**secinfo**

Number of secinfo requests made by NFS Client to obtain a valid RPC authentication flavors for a specific file handle, file name pair.

**setattr**

Number of setattr operation requests made by NFS Client.

**set\_clientid**

Number of Client Negotiation requests made by NFS Client.

**set\_clientid**

Number of Client confirm requests made by NFS Client.

**statfs**

Number of statfs calls made by NFS client.

**symlink**

Number of symlink create requests made by NFS Client.

**unlock**

Number of file unlock requests made by NFS client.

**write**

Number of file write requests made by NFS client.

## Process statistics

The process statistics contain the statistics of the top processes that are running on the logical partition. A *top process* is a process that has higher CPU consumption. By default, the threshold for CPU consumption is 0.1%. You can configure this threshold value. Processes that have CPU consumption more than or equal to the threshold value are recorded in the nmon recording tool.

The following sections in the nmon recording file are used to identify the process statistics:

Table 13. Sections for process statistics

Sections	Description
UARG	<p>Records the process argument details. You can use the <b>-T</b> option to enable these recording details. The <b>-T</b> option automatically enables the <b>-t</b> option that records top process statistics.</p> <p><b>Note:</b> The UARG tag is displayed only once for all the processes in the recorded file.</p> <p>The following fields are displayed in the UARG section:</p> <p><b>Time</b> Specifies the time at which a specific process data was recorded.</p> <p><b>PID</b> Specifies the Process ID of the process for which statistics is recorded.</p> <p><b>PPID</b> Specifies the Parent Process ID of the process for which the process statistics is recorded.</p> <p><b>THCOUNT</b> Specifies the number of threads that are associated with the process for which the process statistics is collected.</p> <p><b>USER</b> Indicates the effective user ID of the process. The textual user ID is displayed. If the textual user ID cannot be obtained, a decimal representation is used.</p> <p><b>GROUP</b> Indicates the effective group ID of the process. The textual group ID is displayed. If the textual group ID cannot be obtained, a decimal representation is used</p> <p><b>Full Command</b> Specifies the full command name and the parameters that are associated with the process.</p>

Table 13. Sections for process statistics (continued)

Sections	Description
TOP	<p>Records the utilization statistics of top process.</p> <p><b>Note:</b> You can use the <b>-t</b> option to collect top process utilization statistics during the recording.</p> <p>The following fields are displayed in TOP section:</p> <p><b>+PID</b> Process ID of the process for which CPU utilization statistics is collected.</p> <p><b>Time</b> Time duration for which the statistics is collected. Time duration is specified in the format <code>T&lt;sample number&gt;</code>.</p> <p><b>%CPU</b> Percentage of CPU time that is consumed by the process during the specified monitoring interval. This percentage is related to the single processor usage.</p> <p><b>%Sys</b> Percentage of CPU time that is spent by the process that is running in the system mode.</p> <p><b>%Usr</b> Percentage of CPU time spent by the process running in user mode.</p> <p><b>Threads</b> Number of kernel threads that belong to the process.</p> <p><b>Size</b> Paging space that is allocated for the data section of the process. This field is specified in KB.</p> <p><b>ResText</b> Amount of real memory that is used for text segments of the process. This field is specified in KB.</p> <p><b>ResData</b> Amount of physical memory that is used for data segments of the process. This field is specified in KB.</p> <p><b>Note:</b> Sum of the ResData and ResText values give total memory that is used by the process for any instance of the process.</p> <p><b>CharIO</b> Number of I/O bytes that are transferred per second for the process.</p> <p><b>Note:</b> The I/O operations can be any of the following types: read or write system calls, inputs from terminals, sockets, and pipes.</p> <p><b>%RAM</b> Percentage of real memory that is used as against the total real memory that is used by the LPAR.</p> <p><b>Paging</b> Total number of page faults per second for the process for which statistics are recorded. Page faults can have the following types: I/O, non-I/O, and repage faults.</p> <p><b>Command</b> Command name of the process.</p> <p><b>WLM class</b> Class name of the workload manager or workload partition to which the process belongs.</p>

## Processor statistics

Processor statistics contain the utilization statistics of logical partition (LPAR), which is recorded in the nmon recording file.

The following sections in the nmon recording file are used to identify the processor statistics:

### CPU\_ALL

Records the overall LPAR processor utilization based on the Processor Utilization Resource register (PURR) entries. This section is recorded by default. This section contains the following fields:

#### User %

Average percentage of processor utilization as against the total processor utilization of the LPAR, when the LPAR is in user mode.

#### System %

Average percentage of processor utilization as against the total processor utilization of the LPAR, when the LPAR is in kernel mode. This percentage includes donated PURR and stolen PURR values.

- Donated PURR is the number of processor cycles that are donated by the LPAR to any other LPAR.
- Stolen PURR is the number of processor cycles that are used by the hypervisor from the LPAR.

#### Wait %

Average percentage of processor utilization against the overall processor utilization of the LPAR when the LPAR is in I/O wait mode. This recording information contains following scenarios:

- In a shared LPAR, if the total dispatch time is less than the entitlement units assigned to the LPAR, the unused PURR value is added to the value of the `Wait %` field.
- In a dedicated LPAR, if the LPAR is capable of giving idle processor cycles to other LPARs, the `busy stolen PURR` value and the `donated PURR` values are added to the `sys PURR` value. Idle, stolen, and the `donated PURR` values are added to either the `wait PURR` value or the `idle PURR` value.

#### Idle%

Average percentage of the processor utilization as against the overall processor utilization of the LPAR in idle mode. This recording information contains following scenarios:

- In a shared LPAR, if the total dispatch time is less than the entitlement units assigned to the LPAR, the unused PURR value is added to the `Wait%` value.
- In a dedicated LPAR, if the LPAR is capable of giving idle processor cycles to other LPARs, then the `busy stolen PURR` value and the `donated PURR` values are accounted to `sys PURR` value. Idle, stolen, and `donated PURR` are accounted to either the `wait PURR` value or the `idle PURR` values.

#### Busy

Percentage of physical processor that is used for the actual processing.

#### Physical CPUs

Total number of logical CPUs that are available.

#### User

Total physical processing units that are used in the user mode.

#### System

Total physical processing units that are used in the kernel mode.

#### Wait

Total physical processing units that are used in the wait mode.

#### Idle

Total physical processing units that are used in the idle mode.

#### Entitled capacity

Physical processing units that are allocated to the LPAR.

## **SCPU\_ALL**

Records the overall CPU utilization of the LPAR in the Scalable Processor Utilization Resource register (SPURR). This recording is performed only for shared partitions. The SCPU\_ALL and PCPU\_ALL sections are same on LPARs that are running in nominal frequency. This section contains the following fields:

### **User**

Total physical processing units that are used in the user mode based on SPURR metrics.

### **System**

Total physical processing units that are used in the system mode based on SPURR metrics.

### **Wait**

Total physical processing units that are used in the wait mode based on SPURR metrics.

### **Idle**

Total physical processing units that are used in the idle mode based on SPURR metrics.

## **CPU\* metrics**

Records the utilization statistics per logical processor level.

### **Notes**

- Default logical processor utilization in percentage based on clock ticks.
- Logical processor utilization in percentage based on PURR ticks.

This metric does not completely determine the logical processor utilization. This metric provides an overview of ratio of processor utilization in each of the following modes: user mode, system mode, wait mode and idle mode. This section contains the following fields:

### **User%**

Logical processor utilization in the user mode contains the following scenarios:

- Average percentage of logical processor utilization in user mode as against the total clock ticks used.
- Average percentage of logical processor utilization in user mode as against the total time that is spent by the LPAR in the CPU.

### **System%**

System utilization percentage contains the following scenarios:

- Average percentage of logical processor utilization in wait mode as against the total clock ticks used.
- Average percentage of logical processor utilization in wait mode as against the total time that is spent by the LPAR in the CPU.

### **Wait%**

Logical processor utilization in wait mode contains the following scenarios:

- Average percentage of logical processor utilization in idle mode as against the total clock ticks used.
- Average percentage of logical processor utilization in idle mode as against the total time that is spent by the LPAR in the CPU.

### **Idle%**

Logical processor utilization in idle mode contains the following scenarios:

- Average percentage of logical processor utilization in idle mode as against the total clock ticks used.
- Average percentage of logical processor utilization in idle mode as against the total by the LPAR in the CPU.

## **PCPU\* metric**

Records the statistics of utilization in physical processing units per logical CPU.

### **Notes:**

- Sum of `user`, `sys`, `wait`, and `idle` values of the PCPU metric is equal to the PCPU\_ALL value.
- Sum of `User` and `sys` values of each physical CPU is equal to the `Physb` value of the logical CPU.

This section contains the following fields:

**User**

Physical processing units that are used in user mode by the logical CPU.

**system**

Physical processing units that are used in kernel mode by the logical CPU.

**wait**

Physical processing units that are used in wait mode by the logical CPU.

**idle**

Physical processing units that are used in idle mode by the logical CPU.

**SCPU\* metric**

Records utilization statistics for each logical CPU based on Scaled Processor Utilization Resource Register (SPURR) value.

**Notes:**

- Sum of `user`, `sys`, `wait`, `idle` values must match with the SCPU\_ALL value of each logical CPU.
- Sum of `User` and `sys` values of each physical CPU is equal to the `Physb` value of the logical CPU.
- The SCPU values must match with the PCPU values when the logical CPUs run in nominal frequency.

This section contains the following fields:

**User**

Physical processing units that are used in user mode based on the SPURR value.

**Sys**

Physical processing units that are used in kernel mode based on the SPURR value.

**Wait**

Physical processing units that are used in wait mode based on the SPURR value.

**Idle**

Physical processing units that are used in idle mode based on the SPURR value.

**BBBL**

Records logical partition configuration details. This section is recorded only once in the recording file. This section contains the following fields:

**BBBL,01,lparno**

Partition ID.

**BBBL,02,lparname**

Partition name that is assigned in the Hardware Management Console (HMC).

**BBBL,03,CPU in sys**

Number of active licensed physical CPUs in the system (CEC).

**Note:** This number is same across all partitions of the same server.

**BBBL,04,Virtual CPU**

Number of current online virtual CPUs in the LPAR.

**BBBL,05,Logical CPU**

Number of online logical CPUs in the LPAR.

**BBBL,06,smt threads**

Number of Symmetric Multi Threading (SMT) threads that are enabled when the recording started.

**BBBL,07,capped**

Flag to indicate whether a partition is capped or uncapped. A value of 1 indicates that the partition is capped and a value of 0 indicates that the partition is uncapped. Capped partitions are not allowed to exceed the entitlement capacity. Uncapped partitions are allowed to exceed the entitlement capacity.

**BBBL,08,min Virtual**

Minimum number of virtual CPUs in the LPAR definition.

**BBBL,09,max Virtual**

Maximum number of virtual CPUs the LPAR can support.

**BBBL,10,min Logical**

Minimum number of logical CPUs in the LPAR.

**Note:** This value is based on number of virtual CPUs and each virtual CPU is running minimum one thread.

**BBBL,11,max Logical**

Maximum number of Logical CPUs the LPAR can support.

**BBBL,12,min Capacity**

The minimum unit at which you can change the entitled capacity. A value in multiples of a whole number indicates a dedicated LPAR.

**BBBL,13,max Capacity**

The maximum unit at which you can change the entitled capacity. This value is based on the maximum virtual processors of the LPAR.

**BBBL,14,Entitled Capacity**

The number of processing units that are entitled to the LPAR.

**BBBL,15,min Memory MB**

Minimum memory in MB configured in the LPAR definition.

**BBBL,16,max Memory MB**

Maximum memory in MB supported for the LPAR.

**BBBL,17,online Memory**

Amount of Memory in MB that is currently online.

**BBBL,18,Pool CPU**

Number of physical CPUs in the shared processor pool of the LPAR.

**BBBL,19,Weight**

Variable processor capacity weight.

**Note:** Variable processor capacity weight is the priority weight assigned to the LPAR using the `lparstat` command which controls how idle capacity is allocated to it. A weight of -1 indicates a soft cap is in place.

This parameter is used to determine the share of extra capacity that is provided to uncapped partitions. Uncapped partitions can only use the processor cycles based on its variable capacity weight and virtual processors. This value is a number in the range 0 - 255 and represents the share of extra capacity that the LPAR is eligible to receive. A partition's share is computed by dividing its variable capacity weight by the sum of the variable capacity weights of all uncapped partitions. Therefore, a value of 0 might be used to prevent a partition from receiving extra capacity. This method is also called as *soft cap*.

**BBBL,20,pool id**

Shared processor pool ID of the LPAR.

**LPAR**

Records logical partition processor utilization statistics. This statistics is recorded only for the shared partitions. This section contains the following fields:

**PhysicalCPU**

Amount of CPU used by the LPAR in physical processing units.

**virtualCPUs**

Number of current online virtual CPUs in the LPAR.

**logicalCPUs**

Number of online logical CPUs in the LPAR.

**poolCPUs**

Number of physical CPUs in the shared processor pool of the LPAR.

**Entitled**

The number of processing units the LPAR is entitled to receive.

**Weight**

Variable processor capacity units. This parameter is used to determine the share of extra capacity that is provided to uncapped partitions.

**PoolIdle**

Available physical processor units in the shared processor pool.

**usedAllCPU%**

Percentage of physical processors that are used as against the physical processors that are available in the server.

**usedPoolCPU%**

Percentage of physical processors that are used as against the available physical processors in the shared pool. This value is always 0 for dedicated partitions.

**SharedCPU**

This value is 1 for shared partitions and 2 for dedicated partitions.

**Capped**

A value of 1 for this field indicates a capped partition and a value of 2 for this partition indicates an uncapped partition.

**EC\_User%**

Physical processor consumption in the user mode contains the following cases:

1. Physical processor consumption is less than the entitlement percentage of entitlement that is used in user mode.
2. Physical processor consumption is greater than the entitlement percentage of physical processor that is used in user mode.

**Note:** Sum of EC\_User %, EC\_Sys%, EC\_Wait% fields, and EC\_Idle % fields is equal to following values: In the first case, it is equal to the percentage of entitlement used and in the second case, it is equal to 100%.

**EC\_Sys%**

Physical processor consumption in system mode contains the following scenarios:

1. Physical processor consumption is less than the entitlement percentage of entitlement that is used in system mode.
2. Physical processor consumption is greater than the entitlement percentage of physical processor that is used in system mode.

**Note:** Sum of EC\_User %, EC\_Sys%, EC\_Wait%, and EC\_Idle % is equal to following values: In the first case, it is equal to the percentage of entitlement used and in the second case, it is equal to 100%.

**EC\_Wait%**

Physical processor consumption in wait mode contains the following cases:

1. Physical Processor consumption is less than the entitlement percentage of entitlement that is used in the wait mode.
2. Physical processor consumption is greater than the entitlement percentage of physical processor that is used in the wait mode.

**Note:** Sum of EC\_User %, EC\_Sys%, EC\_Wait%, and EC\_Idle % is equal to following values: In the first case, it is equal to the percentage of entitlement used and in the second case, it is equal to 100%.

**EC\_Idle%**

Physical processor consumption in idle mode contains the following cases:

1. Physical Processor consumption is less than the entitlement percentage of entitlement that is used in the idle mode.
2. Physical processor consumption is greater than the entitlement percentage of physical processor that is used in the idle mode.

**Note:** Sum of EC\_User %, EC\_Sys%, EC\_Wait%, and EC\_Idle % is equal to following values: In the first case, it is equal to the percentage of entitlement used and in the second case, it is equal to 100%.

**VP\_User%**

Percentage of virtual CPU consumption in user mode.

**VP\_Sys%**

Percentage of virtual CPU consumption in system mode.

**VP\_Wait%**

Percentage of virtual CPU consumption in I/O wait mode.

**VP\_Idle%**

Percentage of virtual CPU consumption in idle mode.

**Folded**

Number of virtual processors that are folded. Folding virtual processor means that moving idle virtual processors into a hibernation state to conserve physical processor resources.

**Pool\_id**

Shared processor pool ID of the LPAR.

**POOLS**

Records multiple shared processor pool statistics. This section is recorded for partitions of POWER6 processor-based systems.

**shcpus\_in\_sys**

Number of physical processors that are allocated for shared processor use, across all shared processors pools.

**max\_pool\_capacity**

Maximum processor capacity of shared processor pool of the partition.

**entitled\_pool\_capacity**

Entitled processor capacity of shared processor pool of the partition.

**pool\_max\_time**

Sum of the maximum time, in seconds, that is used by the shared processor pool of the partition.

**pool\_busy\_time**

Sum of busy time, in seconds, accumulated across all partitions in the shared processor pool of the partition.

**shcpu\_tot\_time**

Total time, in seconds, accumulated across all physical processors that are allocated to the shared processor pools.

**shcpu\_busy\_time**

Total busy time, in seconds, that is accumulated across all physical processors that are allocated to shared processors pools.

**Pool\_id**

ID of the shared processor pool of the partition.

**entitled**

The number of processing units the LPAR is entitled to receive.

**DONATE**

Records Donate statistics of the logical partition from a dedicated partition with capable of donating its resources. This section is recorded only if the partition is dedicated and is capable of donating its resources.

**Note:** The processing capacity is fixed in the dedicated processing mode and the capacity gets wasted during low workload processing.

For enhanced use of dedicated processing capacity, donating of processor units started with POWER6 technology. Optionally dedicated partitions can be configured as processor donors. In this mode, the unused cycles are donated to the physical shared-processor pool associated with the Micro-Partitioning value. Maximum processor utilization throughout the system is achieved because of the utilization of unused cycles. The power hypervisor ensures that the only spare CPU cycles are donated. This feature increases system utilization, without affecting the critical partitions configured in a dedicated processor mode.

When the CPU utilization of the CPU core goes below a threshold, and all the Symmetric Multi Threading (SMT ) threads of the CPU are idle from a hypervisor perspective, the CPU is donated to the shared processor pool. The donated processor is returned within micro-seconds to the dedicated processor partition when the timer of one of the SMT threads on the donated CPU receives an instruction to run.

**pUser**

Total Physical processing units that are used in the user mode.

**pSys**

Total Physical processing units that are used in the system mode.

**pWait**

Total Physical processing units that are used in the wait I/O mode.

**pIdle**

Total Physical processing units that are used in the Idle mode.

**pDonateIdle**

Idle physical processing units that are donated to the shared processor pool.

**pDonateBusy**

Busy physical processing units that are donated to the shared processor pool.

**pStolenIdle**

Idle processing units that are stolen by hypervisor from the dedicated partitions. The hypervisor might forcibly steal cycles from the dedicated partition to perform hypervisor activity. Though the hypervisor might generally steal cycles when the processors in the partition are idle, it might also steal cycles when the processors in the partition are waiting for some hypervisor activity to complete.

In cases where stealing idle cycles is not sufficient for hypervisor to complete activity, it can also borrow cycles when processor is in busy state. This stealing of cycles is orthogonal to donation enablement on the processor and any partition settings.

**pStolenBusy**

Busy physical processing units that are stolen by the hypervisor from the dedicated partitions.

**RAWLPAR**

Records raw LPAR statistics that is memory dump of the `perfstat_partition_total_t` structure that is defined in the `libperfstat.h` header file. You can use the **-K** flag to enable the recording of these statistics. This statistics provides the flexibility to the you to utilize the statistics as per your requirement.

**Name**

Name of the LPAR.

**Type**

Bits representing partition details. This field is of the `perfstat_partition_type` type.

**lpar\_id**

Partition ID.

**cpu\_group\_id**

ID of the LPAR group to which the partition belongs.

**cpu\_pool\_id**

Shared processor pool ID of the partition.

**online\_cpus**

Number of current online virtual CPUs in the LPAR.

**max\_cpus**

Maximum number of virtual CPUs the LPAR can support.

**min\_cpus**

Minimum number of Virtual CPUs in the LPAR definition.

**online\_memory**

Amount of memory, in MB, that is online.

**max\_memory**

Maximum memory, in MB, supported by the LPAR.

**min\_memory**

Minimum memory, in MB, configured for the LPAR definition.

**entitled\_proc\_capacity**

The number of processing units this LPAR is entitled to receive.

**max\_proc\_capacity**

The maximum unit at which you can change the entitled capacity. This value is based on the maximum virtual processors of the LPAR.

**min\_proc\_capacity**

The minimum unit at which you can change the entitled capacity. A whole number indicates a dedicated LPAR.

**proc\_capacity\_increment**

Unit at which you can change entitled processor capacity.

**unalloc\_proc\_capacity**

Deallocated processor units in the shared processor pool of the partition.

**var\_proc\_capacity\_weight**

Variable processor capacity weight. This parameter is used to determine the share of extra capacity that is provided to uncapped partitions.

**unalloc\_var\_proc\_capacity\_weight**

Number of variable processor capacity weight currently deallocated in the shared processor pool of this partition.

**online\_phys\_cpus\_sys**

Number of active licensed physical CPUs in the system.

**max\_phys\_cpus\_sys**

Maximum number of physical CPUs in the system that includes unlicensed and hot-pluggable CPUs.

**phys\_cpus\_pool**

Number of physical CPUs in the shared processor pool of the LPAR.

**Puser**

Number of physical processor tics in the user mode.

**Psys**

Number of physical processor tics in the system mode.

**Pidle**

Number of physical processor tics in the idle mode.

**Pwait**

Number of physical processor tics in the wait I/O mode.

**pool\_idle\_time**

Idle time of shared processor pool in nanoseconds.

**phantintrs**

Number of phantom interrupts that are received by this partition.

**Note:** Phantom interrupts are interrupts that are targeted for a different partition but are sharing physical processor of the LPAR.

**invol\_virt\_cswitch**

Number of involuntary virtual CPU context switches. Involuntary context switches occur when the time slot allocated to the LPAR on the physical processor is exhausted and it must be allocated to the next LPAR.

**vol\_virt\_cswitch**

Number of voluntary virtual CPU context switches.

**Note:** Voluntary virtual CPU context switches occur when virtual processor voluntarily provides the processor cycles to hypervisor after it completes the work of the processor.

**timebase\_last**

Total number of clock ticks.

**Note:** This clock ticks every time irrespective of whether the LPAR is running on the actual physical processor.

**RAWCPUTOTAL**

Records the `perfstat_cpu_total_t` memory dump from the `libperfstat.h` header file without performing any calculations on the memory dump. You can use the **-K** flag to enable the recording of this statistics in the nmon recording file. This section contains the following fields:

**ncpus**

Number of active logical processors.

**ncpus\_cfg**

Number of configured processors.

**description**

Description of the processor in the format `<type_official name>`. For POWER7 processor-based systems, the description is `POWERPC_POWER7`.

**processorHZ**

Speed of the processor in Hertz.

**user**

Number of processor clock ticks in the user mode.

**sys**

Raw number of processor clock ticks in the system mode.

**idle**

Raw number of processor clock ticks in the idle mode.

**wait**

Raw number of processor clock ticks in the I/O wait mode.

**pswitch**

Number of processor context switches that occur when a new process is dispatched.

**Note:** Context switch preempts the current running thread, saves its machine state in the `mstsave` structure, restores the machine state of another thread, and resumes the execution of the newly dispatched thread.

**syscall**

Number of system calls that are run.

**sysread**

Number of read system calls that are run.

**syswrite**

Number of write system calls that are run.

**sysfork**

Number of fork system calls that are run.

**sysexec**

Number of exec system calls that are run.

**readch**

Number of characters that are transferred by using the read system call.

**writetech**

Number of characters that are transferred by using the write system call.

**devintrs**

Number of device interrupts.

**softintrs**

Number of software interrupts. A software interrupt is similar to a hardware interrupt that saves the current state of the machine and runs another subroutine that has interrupted. Software interrupt instruction calls the system call handler routine.

**lbolt**

Average number of runnable processes during the last 1 minute.

**loadavg5**

Average number of runnable processes during the last 5 minutes.

**loadavg15**

Average number of runnable processes during the last 15 minutes.

**runque**

Length of the current run queue.

**swpque**

Number of ready processes that are waiting to be paged-in currently.

**bread**

Total number of blocks that are read by the LPAR.

**bwrite**

Total number of blocking write operations by the LPAR.

**lread**

Number of logical read requests sent to the LPAR. When a logical read or write operation to a block device is performed, a logical transfer size of less than a full block size can be requested. The system accesses the physical device units of complete blocks and saves the accessed blocks in the kernel buffers. These buffers are called the *block I/O cache*. This cache area is managed by the kernel so that multiple logical read and write operations to the block device can access previously buffered data from the cache. These read and write operations does not involve real I/O operation on the device.

Read and write operation requests to the block devices by the application are reported statistically as logical read and write operations. The block I/O operations that are performed by the kernel to the block device are reported as block read and write operations.

**lwrite**

Number of logical write requests.

**phread**

Number of physical read operations. These operations are performed on raw devices.

**Note:** Requested I/O to raw character devices is not buffered as it is for block devices. The I/O operation is performed by the device directly.

**phwrite**

Number of physical write operations. These write operations are made to raw devices.

**runocc**

Counter that is incremented when run queue is occupied.

**Note:** This counter is used to calculate the average number of ready processes.

**swpocc**

Counter that is incremented when the swap queue is occupied. This counter is used to calculate the average number of processes that are waiting to be paged-in.

**iget**

Number of inode lookup calls performed to search a file or directory associated with an inode.

**namei**

Number of vnode lookup calls performed to search a file or directory associated with a path name.

**dirblk**

Number of 512-byte blocking read operations performed by the directory search routine to locate an entry for a file.

**msg**

Number of interprocess communication (IPC) message operations.

**Note:** Message queue structurally passes small amounts of information between processes. Information that must be communicated is placed in a predefined message structure.

**sema**

Number of IPC semaphore operations.

**Note:** Semaphores are specialized data structures that are used to coordinate access to a non-sharable resource.

**rcvint**

Number of tty interrupts that are received by the process.

**xmtint**

Number of tty transmission interrupts that are received by the process.

**mdmint**

Number of tty modem interrupts that are received by the process.

**tty\_rawinch**

Number of tty input queue characters.

**tty\_caninch**

Number of tty canonical input queue characters.

**tty\_rawoutch**

Number of tty output queue characters.

**ksched**

Number of kernel processes created.

**koverf**

Number of times kernel processes are not created because of the process threshold limit is crossed. Reasons for reaching threshold limit follow:

- The user has run fork system call to a maximum limit.
- The configuration limit of processes is reached.

**kexit**

Number of kernel processes that became zombie processes.

**rbread**

Number of remote read requests.

**rcread**

Number of cached remote read operations.

**rbwrt**

Number of remote write operations.

**rcwrt**

Number of cached remote write operations.

**traps**

Number of asynchronous *trap* notifications.

**nopus\_high**

Maximum number of active processors that are online during boot time.

**puser**

Raw number of physical processor tics in the user mode.

**psys**

Raw number of physical processor tics in system mode.

**pidle**

Raw number of physical processor tics in the idle mode.

**pwait**

Raw number of physical processor tics in the I/O mode.

**decrintrs**

Number of decremter tic interrupts.

The decremter is a binary counter that generates a clock interrupt each time the clock moves to zero. The tic is the value of a decrement. On few systems, time is decremented in nanoseconds. Therefore each tick is equal to 1 nanosecond. On other systems, the value of the decrement depends on the system.

**mpcintrs**

Numbers of MPC interrupts that are received.

**Note:** The kernel proactively generates an extra interrupt to ensure rapid response to a cross-CPU preemption request when the preempting thread is considered as real-time thread. Without this extra interrupt (called an MPC), the preempted thread might continue to run without interruption until the next regularly scheduled timer tick, or up to 10 ms. MPC interrupts reduce preemption latency.

**mpcsintrs**

Number of MPC send interrupts.

The kernel proactively generates an extra interrupt to provide a rapid response to a cross-CPU preemption request by a real-time thread. The preempted thread continues to run until the next regularly scheduled timer tick, or up to 10 milliseconds unless interrupted by an MPC interrupt. MPC interrupts reduce preemption latency.

**phantintrs**

Number of phantom interrupts that are received by this partition.

**Note:** Phantom interrupts are interrupts that are targeted for a different partition but are sharing the physical processor of the LPAR.

## Recording configuration details

Recording configuration details are logged for each recorded file with a time stamp. The details include different tags and each tag has its own specification.

All tags that have prefix AAA represent recording configuration details. These configuration details are recorded initially when the recording begins. The tags that have prefix ZZZZ represent the end of each record in the recording file. This tag also represents the time stamp of that sample.

The recording configuration can have the following fields:

**progname**

Name of the binary that is executed.

**command**

Full command name with arguments that are specified during the start of the recording.

**version**

For the AIX operating system, the version is TOPAS\_NMON.

**build**

Build level of the AIX operating system. In TOPAS\_NMON, this field has the value AIX.

**disks\_per\_line**

Number of disks per line that must be recorded by the nmon tool. 150 lines are recorded by default. You can use the `-l` option to configure this field.

**host**

Host name of the logical partition (LPAR).

**user**

User name of the user by whom the recording was initiated.

**VIOS**

VIOS build level. This field is logged only when the recording is started in a Virtual I/O Server.

**AIX**

Provides AIX version details in the format `version.technology level.service pack`.

**TL**

Technology level of the base operating system.

**runname**

Name of the nmon recording session that is running. By default, the `runname` field indicates the host name of the LPAR that has initiated the recording session. You can use the `-r` option to configure the `runname` field.

**time**

Start time of the recording. By default, time is set to the local time. The `-G` option is used to configure the recording time in Greenwich Meridian Time (GMT).

**gmt**

Indicates that GMT is enabled for this recording. This field is not displayed if GMT is not enabled. You can use `-G` option to configure the `gmt` field.

**date**

Start date of the recording.

**interval**

Interval duration of the recording in seconds. This field is the interval between two consecutive recording snapshots. You can use the `-s` option to enable the interval field.

**snapshots**

Number of snapshots that must be recorded. You can use the `-c` option to configure the snapshots field.

**hardware**

Processor architecture. This field can have one of the following values: POWER, PowerPC, and unknown.

**Implementation**

Processor on which the LPAR is running. This field can have one of the following values: POWER6, POWER6\_COMPAT\_MODE, POWER7, POWER7+, POWER7\_COMPAT\_MODE, POWER8.

**Bit**

32-bit or 64-bit.

**subprocessorMode**

Mode of the subprocessor.

**cpus**

Current number of logical CPUs.

**Kernel**

Version of the kernel.

**HW-Type**

The model architecture of this platform.

**Bus**

The model implementation of this platform.

**LPAR**

Type of the LPAR, mode of the kernel, and type of the kernel.

**Serial Number**

System ID number.

**MachineType**

Machine type and mode number.

**LPARNumberName**

Partition ID of the LPAR and LPAR name.

**NodeName**

Name of the system that is determined by using Unix-to-Unix Copy (UUCP) communications network.

**timestampsize**

Specifies the size of the time stamp parameter in the **T**<sample number> format. The value of this field is in the range 4 - 16. By default, the configured value is 4.

**T**<sample number>

Timestamp Identifier. This field is used to uniquely identify samples that are collected by the nmon tool for a specific time stamp. The corresponding time stamp is mentioned in ZZZZ tab. This field is represented in Tnnnn format. The value of the number parameter is in the range 4 - 16. For nmon analyzer, you can either use 4 or 8 as the value for the identifier. The timestamp field is present for each tag of the nmon recording.

**Note:** The timestamp field is not represented as AAA, T <sample number>. This field is present in each sample of the recording after the AAA section is completed.

## WLM statistics

The WLM section in the recorded file contains the workload manager (WLM) statistics. The WLM statistics are related to CPU, memory, I/O.

You can use the **-W** option to enable the Workload Manager statistics collection in the nmon recording. Workload Manager (WLM) is designed to provide increased control to the system administrator on how the process scheduler, virtual memory manager (VMM), and the disk I/O subsystem allocate resources to the processes.

The different tags that represent WLM statistics follow:

**WLMCPU, CPU percent for <WLMCount> Classes, < WLMClasses>**

```
<WLMCount> : Total number of WLM Classes
<WLMClasses> : This is a comma separated list form of WLM Classes.
```

If WLM classes WLMClass1 and WLMClass2 exist in the LPAR, an nmon recording for WLMCPU section is displayed, which is similar to the following example:

```
WLMCPU, CPU percent for 2 Classes, WLMClass1, WLMClass2
```

For each sample, percentage of CPU used by corresponding WLM class is recorded.

**WLMEM, Memory percent for <WLMCount> Classes, <WLMClasses>**

Percentage of real memory that is used by corresponding WLM class.

**WLM BIO, Block IO percent for <WLMCount> Classes, <WLMClasses>**

Percentage of disk I/O bandwidth that is used by the corresponding WLM class.

## Workload partition statistics

Statistics of CPU and memory utilization of workload partition.

Workload partitions are virtualized operating system environments within a single instance of the AIX operating system. WPARs secure and isolate the environment for the processes and signals that are used by the enterprise applications. Different tags that represent WPAR statistics follow:

**WPARCPU, Physical CPU by WPAR, <WPAR list>**

<WPAR list> is a comma-separated list of WPAR names. Each sample recording contains data about the physical processing units that are consumed by the corresponding WPAR per second.

**WPARMEM Memory MB by WPAR, <WPAR list>**

Total real memory that is used by the corresponding WPAR.

## Notices

---

This information was developed for products and services offered in the US.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing  
Legal and Intellectual Property Law  
IBM Japan Ltd.  
19-21, Nihonbashi-Hakozakicho, Chuo-ku  
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing  
IBM Corporation  
North Castle Drive, MD-NC119  
Armonk, NY 10504-1785  
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

#### COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year).

Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. \_enter the year or years\_.

## Privacy policy considerations

---

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as the customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

## Trademarks

---

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at [Copyright and trademark information at www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

UNIX is a registered trademark of The Open Group in the United States and other countries.



# Index

## A

### API calls

#### basic

- [pm\\_delete\\_program 69](#)
- [pm\\_get\\_data 69](#)
- [pm\\_get\\_program 69](#)
- [pm\\_get\\_tdata 69](#)
- [pm\\_get\\_Tdata 69](#)
- [pm\\_reset\\_data 69](#)
- [pm\\_set\\_program 69](#)
- [pm\\_start 69](#)
- [pm\\_stop 69](#)
- [pm\\_tstart 69](#)
- [pm\\_tstop 69](#)

## B

[bos.perf.libperfstat 5.2.0 file set 204](#)

## C

### commands

- [gprof 228](#)
- [prof 227](#)
- [tprof 230](#)

### counter multiplexing mode

- [pm\\_get\\_data\\_mx 71](#)
- [pm\\_get\\_program\\_mx 71](#)
- [pm\\_get\\_tdata\\_mx 71](#)
- [pm\\_set\\_program\\_mx 71](#)

### CPU Utilization Reporting Tool

see [curt 2](#)

### curt

- [Application Pthread Summary \(by PID\) Report 14](#)
- [Application Summary \(by process type\) Report 13](#)
- [Application Summary by Process ID \(PID\) Report 13](#)
- [Application Summary by Thread ID \(Tid\) Report 12](#)
- [default reports 7](#)
- [Event Explanation 3](#)
- [Event Name 3](#)
- [examples 5](#)
- [FILH Summary Report 20](#)
- [flags 2](#)
- [FLIH types 21](#)
- [General Information 7](#)
- [Global SLIH Summary Report 21](#)
- [Hook ID 3](#)
- [Kproc Summary \(by Tid\) Report 13](#)
- [measurement and sampling 3](#)
- [parameters 2](#)
- [Pending Pthread Calls Summary Report 19](#)
- [Pending System Calls Summary Report 16](#)
- [Processor Summary Report 10](#)
- [Pthread Calls Summary Report 19](#)
- [report overview 5](#)
- [sample report](#)

### curt (continued)

#### sample report (continued)

- [-e flag 22](#)
- [-p flag 27](#)
- [-P flag 30](#)
- [-s flag 24](#)
- [-t flag 24](#)

#### syntax 2

[System Calls Summary Report 15](#)

[System Summary Report 7](#)

## E

### event list

[POWERCOMPAT 59](#)

### examples

[performance monitor APIs 72](#)

## G

[gennames utility 37](#)

### global interfaces

- [perfstat\\_cpu\\_util interface 119](#)
- [perfstat\\_process 164](#)
- [perfstat\\_process\\_util 167](#)
- [perfstat\\_processor\\_pool\\_util 169](#)

## K

### kernel tuning

#### commands

- [flags 209](#)
- [tundefault 215](#)
- [tunrestore 213](#)
- [tunsave 214](#)

[commands syntax 209](#)

[initial setup 216](#)

[reboot tuning procedures 216](#)

[recovery procedure 216](#)

[SMIT interface 217](#)

## N

[Node Interfaces 194](#)

## P

### performance monitor API

[accuracy 57](#)

[common rules 66](#)

#### context and state

[state inheritance 58](#)

[system level context 57](#)

[thread context 57](#)

[thread counting-group and process context 57](#)

[programming 56](#)

- performance monitor API (*continued*)
  - security considerations [65](#)
  - thread accumulation [64](#)
  - thread group accumulation [64](#)
- perfstat
  - characteristics [88](#)
  - component-specific interfaces [109](#)
  - global interfaces [89](#)
  - perfstat\_ interface [115](#)
  - perfstat\_disk\_total Interface [96](#)
  - perfstat\_fcstat interface [144](#)
  - perfstat\_memory\_total Interface [94](#)
  - perfstat\_netadapter interface [156](#)
  - perfstat\_netinterface\_total Interface [96](#)
- perfstat API programming
  - see perfstat [88](#)
- perfstat\_cpu\_util interfaces
  - simplelparstat.c [124](#)
  - simplempstat.c [129](#)
- pm\_delete\_program [66](#)
- pm\_error [66](#)
- pm\_groups\_info\_t [67](#)
- pm\_info\_t [67](#)
- pm\_init API initialization [67](#)
- pm\_initialize [66](#)
- pm\_initialize API initialization [68](#)
- pm\_set\_program [66](#)
- pmapi library [66](#)
- PMU registers [78](#)
- POWERCOMPAT [59](#)
- procmon tool [223](#)
- profiling [226](#)

## R

- reboot procedure [216](#)
- recovery procedure [216](#)
- release specific features [202](#)
- Remote Statistics Interface (RSI)
  - A Full-Screen, character-based monitor [282](#)
  - Adding statistics to the Statset [278](#)
  - An Alternative way to decode data feeds [279](#)
  - Concepts and Terms [271](#)
  - Data structures [272](#)
  - Data-Consumer decoding of data feeds [278](#)
  - Defining a Statset [277](#)
  - Expanding the data-consumer program [279](#)
  - Identifying data suppliers [281](#)
  - Initializing and terminating the program [276](#)
  - Inviting data suppliers [281](#)
  - List of RSi Error Codes [282](#)
  - List of subroutines [270](#)
  - Request-Response Interface [274](#)
  - Resynchronizing [275](#)
  - RSI network driven interface [274](#)
  - Sample code [276](#)
  - Specifying port range for RSI communication [276](#)
  - Traversing contexts [279](#)

## S

- simple performance lock analysis tool (splat)
  - see splat [33](#)

- SMIT Interface [217](#)
- splat
  - address-to-name resolution [37](#)
  - AIX kernel lock details [41](#)
  - command syntax [33](#)
  - condition-variable report [54](#)
  - event explanation [35](#)
  - event name [35](#)
  - execution, trace, and analysis intervals [36](#)
  - flags [33](#)
  - hook ID [35](#)
  - measurement and sampling [35](#)
  - mutex function detail [51](#)
  - mutex pthread detail [51](#)
  - mutex reports [49](#)
  - parameters [33](#)
  - PThread synchronizer reports [49](#)
  - read/write lock reports [52](#)
  - reports
    - execution summary [37](#)
    - gross lock summary [38](#)
    - per-lock summary [39](#)
  - simple and runQ lock details [41](#), [44](#)
  - trace discontinuities [36](#)

## T

- thread counting-group information
  - consistency flag [70](#)
  - member count [70](#)
  - process flag [70](#)



