

AIX 7.3.2

Release Notes



Note

Before using this information and the product it supports, read the information in [“Notices” on page 23.](#)

First edition (November 2023)

This edition applies to AIX® 7.3 with Technology Level 2 and to all subsequent release and modifications until otherwise indicated in new editions.

© **Copyright International Business Machines Corporation 2023.**

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Contents

About this document.....	v
Highlighting.....	v
Case sensitivity in AIX.....	v
ISO 9000.....	v
AIX 7.3.2 Release Notes.....	1
Read before installing.....	1
Installation tips.....	1
Software license agreements.....	1
Software maintenance agreement.....	1
AIX Software Maintenance (SWMA) update access key.....	1
Fixes and problem-solving databases.....	1
Security advisories.....	1
Speculative-execution mitigation.....	2
System requirements.....	2
Required hardware.....	2
Firmware.....	2
Memory requirements.....	4
Paging space requirements.....	4
Boot logical volume size requirement.....	4
Disk requirements.....	4
Disk capacity.....	5
File system and file size capacity limitations.....	5
File system and logical volume manager updates.....	5
File extension update.....	6
Security enhancements.....	6
Active Memory Expansion (AME).....	6
AIX MPIO default settings updates.....	6
VPM throughput mode updates for Power10.....	7
Installing.....	7
Installing AIX 7.3.2.....	7
Network Installation Management.....	10
AIX mksysb image and DVD.....	10
AIX cloud-ready images.....	10
Java Technology Edition.....	11
New filesets.....	11
Fileset updates.....	12
Migrating.....	13
IBM License Metric Tool.....	13
IBM PowerSC Trusted Surveyor.....	14
Reliable Scalable Cluster Technology (RSCT).....	14
DSM.....	14
Thin Servers.....	14
IBM Subsystem Device Driver.....	14
Db2 migration.....	15
Configuring.....	15
Dynamic attribute update.....	15
Dynamic network options.....	15
libusb library.....	15
Diagnostics tasks.....	15

Trace facility.....	16
Updates in Korn shell.....	16
Collecting processor frequency and EnergyScale information.....	16
Updates in getcwd and getwd subroutines	16
Limitations and Restrictions.....	16
Limitations with Java8.jre 8.0.0.635.....	16
Upgrading IBM Security Verify Directory.....	16
OpenSSL version 3.0.....	17
OpenSSH Version 8.1p1.....	18
GSKit version requirement for NIST compliance.....	18
Perl.....	18
RPM package manager (RPM).....	18
DBX and IBM OpenXL C/C++ compiler.....	19
YUM and DNF.....	19
Code and functions removed from AIX 7.3.....	19
CIFS client fileset.....	19
CPU limit.....	19
Network Time Protocol (NTP) updates.....	19
Berkeley Internet Name Domain (BIND) updates.....	20
Additional information.....	21
IBM AIX 7.3 Documentation.....	21
AIX Dynamic System Optimizer.....	21
Server-side support for new Unicode locales.....	21
Notices.....	23
Privacy policy considerations.....	24
Trademarks.....	25

About this document

The Release Notes topics include late technical information that is not included in other topics, and they highlights new functions for the AIX 7.3 licensed program.

Highlighting

The following highlighting conventions are used in this document:

Bold	Identifies commands, subroutines, keywords, files, structures, directories, and other items whose names are predefined by the system. Bold highlighting also identifies graphical objects, such as buttons, labels, and icons that the you select.
<i>Italics</i>	Identifies parameters for actual names or values that you supply.
Monospace	Identifies examples of specific data values, examples of text similar to what you might see displayed, examples of portions of program code similar to what you might write as a programmer, messages from the system, or text that you must type.

Case sensitivity in AIX

Everything in the AIX operating system is case sensitive, which means that it distinguishes between uppercase and lowercase letters. For example, you can use the **ls** command to list files. If you type LS, the system responds that the command is not found. Likewise, **FILEA**, **FiLea**, and **filea** are three distinct file names, even if they reside in the same directory. To avoid causing undesirable actions to be performed, always ensure that you use the correct case.

ISO 9000

ISO 9000 registered quality systems were used in the development and manufacturing of this product.

AIX 7.3.2 Release Notes

Review the changes and issues for IBM® AIX 7.3.2.

Read before installing

Before you use this software, you must go to the [Fix Central](#) website and install the latest available fixes that address security vulnerabilities and other critical issues.

Installation tips

The installation hints and tips are available at the [AIX Installation tips](#) article.

Software license agreements

In some instances, the software license agreements (SLA) might not be displayed correctly. In this event, the license agreements can be viewed for all languages at the [Software license agreements](#) website.

Software maintenance agreement

In AIX 7.3, a separate software maintenance agreement (SWMA) acceptance window displays during installation immediately after the license acceptance window. The response to the SWMA acceptance (accept or decline) is stored on the system, and either response allows the installation to proceed, unlike license acceptance, which requires you to accept to proceed.

The **SWMA acceptance** window is displayed during a new overwrite or preservation installation from base DVD media.

For NIM installations, if licenses are accepted either from the choices that are made when you initialize the installation, or by using the ACCEPT_LICENSES field in a customized bosinst.data file, SWMA acceptance is constituted.

AIX Software Maintenance (SWMA) update access key

IBM Power10 processor-based servers, or later, include technology that helps you keep your Software Maintenance Agreements (SWMA) current so that you can apply AIX updates and receive support from IBM. The server uses an AIX update access key (UAK) that indicates the expiration date of the associated AIX SWMA agreement for the server and provides notification of SWMA expiration to ensure continued and uninterrupted software support. For more information about AIX UAKs, see the [AIX update access key](#) topic. You can find additional information in the [Management of AIX Update Access Keys](#) support article.

Fixes and problem-solving databases

You can download AIX fixes and search technical databases (including APARS and tips for AIX administrators) at the [Fix Central](#) website.

Security advisories

Security subscription services are available at the [My notifications](#) website.

After you subscribe to the AIX security advisories, you will receive the advisories by email when they are published.

Speculative-execution mitigation

AIX 7.3, and later includes support for enhancing AIX software with mitigation against speculative-execution vulnerabilities. AIX applications and kernel extensions can use the new `cpu_context_barrier` and `cpu_speculation_barrier` services to protect against attacks from untrusted sources. For more information about these services, view their description on the IBM Docs for [AIX Technical Reference](#).

System requirements

Review the following information to determine the minimum and recommended system requirements that are needed to run AIX 7.3.2.

Required hardware

Only 64-bit Common Hardware Reference Platform (CHRP) machines that are running selected POWER8, POWER9, and Power10 processors in POWER8, or later, processor compatibility mode that implement the Power Architecture® Platform Requirements (PAPR) are supported.

Note: IBM Hyperconverged Systems that are powered by Nutanix, with POWER8 processor-based servers (CS821 and CS822 models) do not support AIX 7.3, and later.

To see whether you have a supported machine, log in to the machine as the root user, and run the following command:

```
prtconf | grep 'Processor Type'
```

Firmware

I/O devices IPL limitation

Because of a limitation on the firmware memory size, only I/O devices in the first 144 I/O slots that are assigned to a logical partition or single system image partition can be used as an IPL (boot) source.

You can use the HMC to identify which devices are in the first 144 I/O slots by performing the following steps:

1. Select **Partition Properties > Hardware > I/O**.
2. Click the Bus column to sort the I/O devices in ascending order.

The first 144 I/O devices in the sorted list are in the bootable adapter slots.

If you are using a partition or single-system image partition with more than 144 assigned I/O slots, the following scenarios and their results and resolutions are possible.

Scenario	Result	Resolution
Attempting to boot from a device beyond the first 144 I/O slots for installation or diagnostic purposes.	The device is not selectable as a boot source from the SMS menus.	Use a device in the first 144 I/O slots.
Booting from a device in the first 144 I/O slots, and then attempt to select a target installation device in a slot beyond the first 144 I/O slots.	The boot succeeds to the installation menus, but devices beyond the first 144 I/O slots are not listed as bootable installation targets in the AIX menus.	Select a device that is available and marked as bootable.

Table 1. Scenarios for partitions with more than 144 assigned I/O slots (continued)

Scenario	Result	Resolution
Using an MPIO configuration where one adapter is in the first 144 I/O slots and another adapter is in a slot beyond the first 144 I/O slots. Both adapters are present at boot time.	The boot succeeds to the installation menus, and the device is listed as bootable in the AIX installation menus. The installation proceeds, but it fails with the bootlist command failure unable to set bootpath for all paths.	Use a device in the first 144 I/O slots for all paths.
Using DLPAR to add an adapter in a slot beyond the first 144 I/O slots, and then attempting to run the alt_disk_install command for the newly added device.	The device is not listed as bootable.	Use a device in the first 144 I/O slots.
Using DLPAR to add an adapter in a slot beyond the first 144 I/O slots, and by using the bootlist command to add the device as a bootable device (for example, by dynamically adding a redundant path to a current boot device or setting up for a network boot). Then removing the original adapter and rebooting.	The bootlist command succeeds, but the boot fails from the specified device, and AIX does not receive control.	Use a device in the first 144 I/O slots.
Using DLPAR to add an adapter whose probe order makes it displace a current bootable device, and then rebooting.	The boot fails, and AIX does not receive control.	Move the boot device to one of the first 144 I/O slots or remove the previously added device.
Selecting a device in a slot beyond the first 144 I/O slots as a dump device for a firmware-assisted dump.	The sysdumpdev command does not allow devices in slots beyond the first 144 I/O slots to be selected as firmware-assisted dump storage devices. An error occurs during the firmware-assisted dump configuration, and a traditional AIX dump automatically becomes available.	Use a device in the first 144 I/O slots for firmware-assisted dumps.
Using DLPAR to add an adapter whose probe order will make it displace a currently valid firmware-assisted dump target device, and then rebooting after the dump.	The firmware-assisted dump process fails during the boot process and displays an error message. The traditional AIX dump still runs to retrieve the dump image.	Avoid displacing the selected firmware-assisted dump target device or reconfiguring the sysdumpdev command for the firmware-assisted selection of the dump target device, and specify a device within the first 144 I/O slots.

Scenario	Result	Resolution
Using DLPAR to add an adapter whose probe order makes it displace a currently valid firmware-assisted dump target device, and then rebooting.	The sysdumpdev command does not allow devices in slots beyond the first 144 I/O slots to be selected as firmware-assisted dump storage devices. An error occurs during the firmware-assisted dump configuration, and a traditional AIX dump automatically becomes available.	Use a device in the first 144 I/O slots for firmware-assisted dumps.

Memory requirements

AIX 7.3.2 minimum current memory requirements vary, based on the configuration.

A minimum current memory requirement for AIX 7.3.2 is 2 GB.

AIX 7.3.2 requires the minimum current memory requirement to increase as the maximum memory configuration or the number of devices scales upward, or both. Larger maximum memory configurations, LMB sizes, or extra devices scale up the minimum current memory requirement. If the minimum memory requirement is not increased along with the maximum memory configuration, the partition hangs during the initial program load (IPL).

Paging space requirements

AIX 7.3, and later creates a 512 MB paging space (in the /dev/hd6 directory) for all new and complete overwrite installations.

Boot logical volume size requirement

Starting with AIX 7.3, the minimum size of the boot logical volume (hd5) is 40 MB.

The installation operation, which includes the operating system overwrite installation, operating system preservation installation, and operating system migration installation, create or increase the size of the hd5 logical volume to a minimum of 40 MB.

Before you migrate an operating system, run the pre-migration script that is available in the `usr/lpp/bos` directory, in your media, or in your NIM Shared Product Object Tree (SPOT). The pre-migration script checks whether the size of the hd5 boot logical volume is at least 40 MB. If the size of the hd5 logical volume does not meet the requirements, the pre-migration script checks whether the required free partitions are available. The partitions that are allocated for the hd5 boot logical volume must be contiguous and must be located within the first 4 GB space of the disk.

Disk requirements

AIX 7.3, and later, requires a minimum of 20 GB of physical disk space for a default installation that includes all devices, the Graphics bundle, and the System Management Client bundle.

Disk usage

The following table displays disk usage statistics:

File system	Allocated (Used)
/	128 MB (51 MB)
/usr	2368 MB (2123 MB)

File system	Allocated (Used)
/var	192 MB (39 MB)
/tmp	128 MB (2 MB)
/admin	128 MB (1 MB)
/opt	64 MB (18 MB)
/var/adm/ras/livedump	256 MB (1 MB)

Note:

1. If the /tmp directory has less than 64 MB, it is increased to 64 MB during a migration installation so that the AIX 7.3.2 boot image is successfully created at the end of the migration.

Format the SAS disk properly before you install the AIX operating system on it. The AIX operating system requires the disk to be formatted to a sector size supported by the attached SAS controller. All AIX SAS controllers support 512-byte sector SAS disks. The 522-byte sector SAS disks are supported only when they are attached to SAS RAID controllers. If the disk is formatted for SAS RAID, but is not attached to a SAS RAID controller, the disk might not configure. If the disk does configure, it might be unreadable in the AIX environment. In some instances, the certify function and the format function in AIX diagnostics can be used to reformat the disk for the attached SAS controller.

If any existing file system has a mount point in the /opt directory, or a mount point of /opt itself, the new logical volume, and file system are not created.

The AIX_FCPARRAY driver is not supported in AIX 7.3, and later. Before you migrate to AIX 7.3, or later, you must use the **manage_disk_drivers** command to convert any FCP array disks from the AIX_FCPARRAY driver to the AIX_AAPCM driver. The AIX_AAPCM driver supports Multipath I/O (MPIO) devices.

Disk capacity

Serial Attached SCSI (SAS) RAID controllers and Fibre Channel controllers support attached arrays and disks with capacities, which exceed 2 TB. The maximum supported capacity (beyond 2 TB) is limited by either the attached storage subsystem or the higher-level logical storage management.

For more information about SAS RAID controllers, see the [SAS RAID controller for AIX](#) topic.

For more information about AIX capacity limitations for logical storage, see the [Limitations for logical storage management](#) topic.

File system and file size capacity limitations

For AIX 7.3, and later, the qualified and supported maximum capacity of the Enhanced Journaled File System (JFS2) file and file system is 128 TB.

For AIX 7.3.1, and later, the network file system (NFS) client supports file sizes that are greater than 16 TB. The current tested and supported maximum file size is 256 TB. For improved performance, use the NFS direct I/O (DIO) option with very large files.

File system and logical volume manager updates

Consider the following default characteristics of a file system and logical volume manager:

- Larger maximum memory configurations
- The **mkvg** command by default creates a scalable type of volume group that can accommodate up to 1024 physical volumes, 256 logical volumes, and 32768 physical partitions. Use the **-a** flag in the **mkvg** command to create a small volume group type that can accommodate up to 32 physical volumes and 255 logical volumes.
- The **mkvg** command by default enables the data encryption in the volume group.

- The **mklv** command by default creates a `jfs2` type logical volume.
- The **mklv** command by default creates a logical volume with passive mirror write consistency as the default mirror write consistency policy for large type and scalable type of volume groups.
- The **crfs** command by default creates a file system with `INLINE` log device.

File extension update

Starting with AIX 7.3, the default file name extension is changed from `.Z` to `.gz` for the pax file that is compressed by using the **snap** command. The `snap.pax.gz` file is the default pax file that is compressed by using the **snap** command.

Security enhancements

Review the following security enhancements in AIX 7.3, and later:

- Uses `SSHA-256` as the default password algorithm for overwrite and migration installation. The passwords in the `SSHA-256` algorithm can contain up to 255 characters for the default AIX configuration.
- Enables UNIX password compatibility by default for overwrite and migration installation.
- Sets the permission for new users on the default home directory to `750` for overwrite and migration installation.
- Supports longer usernames for overwrite installation, by default.
- Removes the deprecated LDAP cache timeout functionality for overwrite installation.
- Strengthens the user default password policy with the latest security industry standards for overwrite installation.
- Strengthens security of AIXPert default password policy with the latest industry standards for overwrite installation.
- Enables the `sendmail` application to support Simple Authentication and Security Layer (SASL) based authentication.
- Encrypts the physical volume that uses the small computer systems Interconnect® (SCSI) protocol. You can use the **hdcryptmgr** command to manage encryption of physical volumes.
- Supports IBM Cloud® Hyper Protect Crypto Services (HPCS) for encryption in logical volumes and physical volumes.

Active Memory Expansion (AME)

AME on AIX now has a default page size of 64 KB on Power10 processor-based systems.

AIX MPIO default settings updates

To support Fibre Channel (FC) and Internet Small Computer Systems Interface (iSCSI)-attached devices in both the IBM DS8000® and the IBM SAN Volume Controller or IBM Flash Systems family, in AIX 7.3 and later, the default values of the following attributes are changed in the Object Data Manager (ODM) that is shipped with AIX:

- The **reserve_policy** attribute value is changed to `no_reserve`.
- The **algorithm** attribute value is changed to `shortest_queue`.
- The **queue_depth** attribute value is changed to 64 for the IBM DS8000 family and 32 for the IBM SAN Volume Controller or IBM Flash Systems family.

Also, the following ODM attributes that are associated with MPIO disks are changed to nondisplayable attributes: **clr_q**, **q_err** and **q_type**, **dist_err_pcmt** and **dist_tw_width**, **lun_reset_spt**, **reassign_to**, and **start_timeout**.

VPM throughput mode updates for Power10

When Power10 systems run in shared processor mode, the default value of the throughput mode for the virtual processor management (VPM) is 2. When you migrate the system to or from a Power10 system, and later, the AIX operating system automatically changes the default value of the throughput mode for the VPM. During boot operation, the AIX operating system selects the default value of the **vpm_throughput_mode** tunable parameter of the **schedo** command based on the type of server on which the LPAR is running. The value of the **vpm_throughput_mode** tunable parameter that is selected by the AIX operating system is preserved and used on the destination server.

>| Starting with AIX 7.3 Technology Level 2, the default value of the **vpm_throughput_mode** tunable parameter of the **schedo** command is selected based on the destination server. If the value of the **vpm_throughput_mode** tunable parameter is modified at the source server, the same value is preserved at the destination server. |<

On Power10 systems, you can switch to the recommended value of 2 for the **vpm_throughput_mode** tunable parameter by using the following command:

```
schedo -d vpm_throughput_mode
```

Note: When you migrate to or from a Power10 system, and later, it is recommended to move the operating system level to 7300-00, 7200-05-03-2147, 7200-04-05-2148, 7100-05-09-2148 or later. Without this feature that enables you to change the **vpm_throughput_mode** tunable parameter by using the **schedo** command, updating the operating system levels to 7200-05-00-2037, 7200-04-03-2038, and 7100-05-07-2037 might override the value set for the **vpm_throughput_mode** tunable parameter.

Installing

This section contains information about installing AIX 7.3, and later, that supplements the information that is contained in the [Installation and Migration](#) topic.

Installing AIX 7.3.2

The following methods can be used to install AIX 7.3.2:

- Complete overwrite installation
- Preservation installation
- Migration installation

Beginning with AIX 7.3, the OpenSSH client and server software are installed by default. The former bundle offerings no longer exist. The following `bos.net.tcp` filesets are not installed by default:

- `bos.net.tcp.ftp`
- `bos.net.tcp.ftpd`
- `bos.net.tcp.rcmd`
- `bos.net.tcp.rcmd_server`
- `bos.net.tcp.slip`
- `bos.net.tcp.telnet`
- `bos.net.tcp.telnetd`
- `bos.net.tcp.timed`
- `bos.net.tcp.x500`

Note:

- OpenSSH client and OpenSSH server filesets are installed by default for overwrite, preservation, and migration installations. Any `bos.net.tcp` filesets that are available on your system before migration remains on your system after migration, and those filesets will be upgraded to the newer levels.

- The `bos.net.tcp.bind` and `bos.net.tcp.bind_utils` filesets of AIX 7.3.0 are replaced by the `bind.rte` fileset. The `bind.rte` fileset is not installed by default.

A new bundle offering is available to install the following filesets that are not installed by default: `bos.net.tcp.ftp`, `bos.net.tcp.ftpd`, `bos.net.tcp.telnet`, and `bos.net.tcp.telnetd`.

Note: After you install or migrate a system to AIX 7.3, or later, you can install a previous level of AIX by restoring a system backup or by performing a new and complete overwrite operation by using base media. Preservation installations from AIX 7.3.2 to a previous level of AIX are not supported.

Note:

Using the update media is recommended for updates. If you use the base media to update, install the `bos.dsc` fileset first by using the following command:

```
# installp -e /tmp/install.log -aXd software_source bos.dsc
```

If you use the base media to update, some ODM settings (such as SRC subsystems settings) might be lost. If you use base media, or a software source that is created from base media, for an **update_all** operation, previous history of your software installation is removed. The history of the fileset installations is reset when a base image is installed. The history is maintained when service updates are used for an **update_all** operation.

The minimum size of the boot logical volume is 40 MB. If your current boot logical volume is lesser than this value, the installation process tries to increase it. However, partitions in a boot logical volume must be contiguous, and within the first 4 GB on the disk. If your system does not have free space that meets these requirements, a message indicates that the system does not have enough space to expand `hd5` (the boot logical volume).

To install AIX 7.3.2, follow the instructions in the [Installing the base operating system](#) topic.

Logical Volume encryption enhancements

Starting with AIX 7.3, encryption is enabled on the root volume group for new and complete overwrite installation. You can select the logical volumes that must be encrypted in the **Base Operating System Install** menus, or by using a `bosinst_data` resource for network installation.

You can select the following logical volumes to be encrypted during the installation: `hd2 (/usr)`, `hd9var (/var)`, `hd3 (/tmp)`, `hd1 (/home)`, `hd10opt (/opt)`, `hd11admin (/admin)`, `dumplv (lg_dumplv)`. For more information, see [BOS installation options](#).

All logical volumes that are encrypted during the operating system installation are initialized with the Platform keystore (PKS) authentication method. You are prompted to add a passphrase recovery method after the system starts. You can add other encryption key-protection methods to the logical volumes, but you must have the PKS method on logical volumes that are created during the installation. For more information, see [Encrypted logical volumes](#).

Starting with AIX 7.3 Technology Level 1, the Live Update operation supports encrypted logical volumes and PKS migration. Support for encrypted logical volumes is restricted to nonrootvg volume groups. Support for PKS migration is restricted to Power® Firmware Level at FW1030, or later.

Hardware requirement

POWER9 and later processor-based systems

Limitations

- For installations that use `mksysb` images, **alt_disk_copy** and **alt_disk_mksysb** commands, PKS and passphrase authentication methods are created again automatically. Any other encryption methods that were present must be created again by the system administrator.
- You can restore an encrypted data volume group or user volume group by using the **restvg** command or SMIT on the target system. You cannot restore an encrypted data volume group or user volume group by using NIM.
- The **multibos** command is not supported on a system that contains encrypted logical volumes.

Security model updates in AIX 7.3.2

Starting with AIX 7.3, the following security models are not available. The following security options are removed from the **Operating System Install** menus and from the `bosinst.data` templates:

- Trusted AIX
- Trusted AIX LAS/EAL4+ Configuration Install
- BAS and EAL4+ Configuration Install

The following security options are available for use:

- [Logical volume encryption](#)
- [Digital signature policy](#)
- [Secure by default](#)

Installing AIX by using a USB flash drive

AIX 7.3, and later, supports installation by using a USB flash drive on POWER8 systems, and later. A USB flash drive that contains an AIX installation image can be created by first downloading the AIX installation image from the [IBM Entitled System Support](#) website. A single volume installation image of AIX 7.3.2 is made available on the IBM Entitled System Support website for writing to USB flash memory. After downloading the AIX installation image, the image can be written to a USB flash drive. IBM recommends that you use a recently manufactured USB flash drive. The minimum capacity requirement of the USB flash drive for AIX installation is 16 GB. On an AIX or a Linux® based system, the image can be written to a USB flash drive by using the `dd` command.

Also, it is possible to create an installable USB flash drive by copying the image directly from AIX DVD installation media by using the following `dd` command:

```
$ dd if=/dev/cd0 of=/dev/usbms0 bs=4k
```

Comparable commands exist on Windows-based machines for writing the installation image to a USB flash drive.

After the USB flash drive AIX installation media is created, the media can be used on POWER8 systems, and later, similar to the DVD install media.

Note: The AIX `bootlist` command can recognize the USB flash drive (`usbmsX`) as a bootable device if the USB flash drive was present during IPL of the AIX partition. On POWER8 systems, and later, the SMS menus can always be used to assign the USB flash drive as the boot source.

AIX and IBM Power Systems USB implementation is compliant with relevant USB standards. In the unlikely event when a USB flash drive is not properly recognized by AIX, IBM recommends that you use a different brand of device.

NIM installations with updated LPP_SOURCE

To create a NIM SPOT from an LPP_SOURCE directory that contains base images from a prior release and that contains updates to the current release, there must be enough space in the SPOT's file system before you start. Failure while creating the SPOT include the following symptoms:

- When you run the `lsnim` command operation on the SPOT, the output shows missing images, similar to the following example output:

```
missing      = "network boot image"  
missing      = bos.net.nfs.client  
missing      = bos.net.tcp.bootp
```

- You might see errors with regards to space or `chfs` in the SPOT log file.

If any of these symptoms occur, remove the incomplete SPOT, increase the space in the file system, and re-create the SPOT.

NIM installations by using an LPP_SOURCE directory that contains base images from a prior release and that contains updates to the current release require that you use an image_data resource during operating system installations.

When you use an LPP_SOURCE directory that contains base images from a prior release and updates to the current release, create a image_data resource to use for any operating system installations. The SPOT must be updated with the updates that are added to the LPP_SOURCE directory, or a new SPOT must be created. In that SPOT, copy the image.template file that is found at SPOT_LOCATION/lpp/bosinst/image.template to a new location outside of the SPOT. Create a NIM image_data resource that points to that location. Use that NIM image_data resource for all operating system installations.

Certain file systems might grow in size, and the default image.data file that is used during an operating system installation comes from the BOS image in your LPP_SOURCE directory, which is the prior release image.data file.

> If you use a LPP_SOURCE directory that contains AIX version 7.3.0 base images and AIX version 7.3.2 updates for operating system (OS) installation operation, the following errors might appear during the installation of bos.net.tcp.sendmail fileset that relates to AIX version 7.3.0.0.

```
installp: APPLYING software for:
        bos.net.tcp.sendmail 7.3.0.0

Successfully updated the Kernel Authorization Table.
Successfully updated the Kernel Role Table.
Successfully updated the Kernel Command Table.
Successfully updated the Kernel Device Table.
Successfully updated the Kernel Object Domain Table.
Successfully updated the Kernel Domains Table.
Successfully updated the Kernel RBAC log level.
Successfully updated the Kernel Authorization Table.
Successfully updated the Kernel Role Table.
Successfully updated the Kernel Command Table.
Successfully updated the Kernel Device Table.
Successfully updated the Kernel Object Domain Table.
Successfully updated the Kernel Domains Table.
Successfully updated the Kernel RBAC log level.
exec(): 0509-036 Cannot load program /usr/sbin/sendmail because of the following errors:
        0509-022 Cannot load module /usr/lib/sasl/libntlm.so(shr.o).
        0509-150 Dependent module libcrypto_compat.a(libcrypto.so) could not be loaded.
        0509-022 Cannot load module libcrypto_compat.a(libcrypto.so).
        0509-026 System error: A file or directory in the path name does not exist.
```

⏪

> After installation of bos.net.tcp.sendmail fileset for AIX version 7.3.0.0, if the bos.net.tcp.sendmail fileset is updated to a later version during the OS installation operation, all the errors are resolved.⏪

Network Installation Management

Network Installation Management (NIM) includes a readme file that is installed with the NIM Master bos.sysmgt.nim.master fileset. The path name of the file is /usr/lpp/bos.sysmgt/nim/README.

AIX mksysb image and DVD

In AIX 7.3, and later, you can continue to use DVD media to write and restore the mksysb image. However, based on the broader industry trends, the AIX operating system has reduced emphasis on DVD as a core technology for the backup and restore operations of the mksysb image. If you rely only on DVD mksysb image, you are encouraged to explore alternative methods of using mksysb image capabilities.

AIX cloud-ready images

In addition to installation images, cloud-ready images are available in RAW format that can be readily deployed with PowerVC. These images contain a default AIX base media installation configuration that includes the cloud-init software package and its dependencies.

Starting with AIX 7.3, the cloud-ready images in qcow2 format are no longer available.

Java Technology Edition

IBM software development kit (SDK) and Java™ Runtime Environment (JRE) for AIX, Java Technology Edition is released in JavaV.x filesets, where V represents the version of Java, such as Java 8, and x is the individual fileset, such as Java8_64.sdk.

The following versions of Java Technology Edition are available on the AIX 7.3, and later, base media:

Java Version	Base media DVD1	Base media DVD2	Expansion pack
Java Version 6 (32 bit)	None	None	None
Java Version 6 (64 bit)	None	None	None
Java Version 7 (32 bit)	None	None	All
Java Version 7 (64 bit)	Java7_64.jre and Java7_64.sdk	Remaining Java7_64 software	None
Java Version 7.1 (32 bit)	None	None	None
Java Version 7.1 (64 bit)	None	None	None
Java Version 8 (32 bit)	None	None	All
Java Version 8 (64 bit)	All except non-Japanese message filesets	Remaining message filesets	None

Only Java Version 8, 64-bit, is installed for new overwrite or preservation operating system installation. For these installations, the *PATH* variable in the */etc/environment* file points to *java8_64*. If you perform an operating system migration to AIX 7.3, or later, all previous levels of Java remain on the system, and the */etc/environment PATH* variable is not changed. Later, if you remove the previous levels of Java (Java Version 6 and Java Version 7), then you must change the */etc/environment PATH* variable to point to *java8_64*.

It is recommended to use *java8_64*. There is no support for security vulnerabilities in Java Version 6.

To check whether a more recent service refresh is available for a version of Java, see the [AIX Download and service information website](#).

New filesets

python3.9.base

Python 3.9 64-bit binary distribution (installed by default)

python3.9.test

Python 3.9 64-bit self-test suite

bash.rte

Bash shell (installed by default). For more information about local support, see the [Bash Locale Support](#) technote.

pigz.rte

Parallel implementation of GZIP (installed by default)

bind.rte

BIND 9.16 Domain Name System support for the AIX operating system

Fileset updates

Starting with AIX version 7.3, Technology Level 1, the `bos.net.tcp.bind` and `bos.net.tcp.bind_utils` filesets are replaced by the `bind.rte` fileset. The `bind.rte` fileset is not installed by default.

Starting with AIX 7.3, the `bos.net.tcp.ntp` and `bos.net.tcp.ntpd` filesets are replaced by the `ntp.rte` fileset that is installed by default.

Starting with AIX 7.3, the zlibNX accelerated zlib compression library is moved from the expansion pack to the base media and the compression library is installed by default. The `bos.perf.pmaix` package is no longer part of the AIX operating system.

To provide you with more control over the software that is installed on your system, the `bos.net.tcp.client` and `bos.net.tcp.server` filesets are split into 31 new filesets. Beginning with AIX 7 with 7200-05, each of the `bos.net.tcp.*` filesets are shipped as individual images, instead of including them with the `bos.net` image. You can now remove unwanted filesets from a NIM installation that uses an LPP_SOURCE directory.

Note: Requisites for installing filesets are unchanged so you must be sure when you remove an image. This image might be required by other filesets that you might want to install.

The core code for each original fileset is in the `bos.net.tcp.client_core` and `bos.net.tcp.server_core` filesets. Requisites for software that is shipped with the AIX operating system (the `bos.net.tcp.client` and `bos.net.tcp.server` filesets) are changed to the `bos.net.tcp.client_core` and `bos.net.tcp.server_core` filesets. Additional requisites are added to the other new fileset as needed.

The original filesets still exist to satisfy any requisites from other software. The original filesets have requisites to all the new filesets to ensure that all the requirements are met.

To remove any of the new filesets, you must first remove either the `bos.net.tcp.client` fileset or the `bos.net.tcp.server` fileset. To remove the `bos.net.tcp.client` fileset, the `bos.net.tcp.server` fileset, or a new fileset, run the **lspp -d *fileset_name*** command. If no other software has requisites to the fileset that you want to remove, the removal is possible.

During an operating system migration, code changes occur, so that all the system configuration and user configurable files, which were owned by the `bos.net.tcp.client` and `bos.net.tcp.server` filesets, are merged by the new filesets that now own the files.

The list of new filesets follows:

- `bos.net.tcp.client_core`
- `bos.net.tcp.server_core`
- `bind.rte`
- `bos.net.tcp.bootp`
- `bos.net.tcp.dfpd`
- `bos.net.tcp.dhcp`
- `bos.net.tcp.dhcpd`
- `bos.net.tcp.ftp`
- `bos.net.tcp.ftpd`
- `bos.net.tcp.gated`
- `bos.net.tcp.imapd`
- `bos.net.tcp.mail_utils`
- `bos.net.tcp.pop3d`
- `bos.net.tcp.pxed`
- `bos.net.tcp.rcmd`
- `bos.net.tcp.rcmd_server`

- bos.net.tcp.sendmail
- bos.net.tcp.slip
- bos.net.tcp.slp
- bos.net.tcp.snmp
- bos.net.tcp.snmpd
- bos.net.tcp.syslogd
- bos.net.tcp.tcpdump
- bos.net.tcp.telnet
- bos.net.tcp.telnetd
- bos.net.tcp.tftp
- bos.net.tcp.tftpd
- bos.net.tcp.timed
- bos.net.tcp.traceroute
- bos.net.tcp.x500
- bos.net.tcp.cpd

The encoded software in the bos.net.uucp fileset moved to the bos.net.uucode fileset.

Migrating

You can migrate your operating system version to AIX 7.3.2 from any prior *version.release* of the AIX operating system, on a system that supports AIX 7.3.2 boot. Installing any new level of AIX requires more disk space than previous levels. Verify that you have enough free space in the file systems, or that you have free partitions in the rootvg. Migrating requires slightly more free space than a basic installation.

If you are using a NIM lpp_source created with a prior level base media and later levels of updates that are added, you must initially create the lpp_source with the base media at the same release date or later than the level of AIX 5.3, AIX 6.1, or AIX 7.1 that you are migrating from. The last 4 digits of the output of the **oslevel -s** command represent the year and week of the service pack currently installed (YYWW).

The default value of the **j2_inodeCacheSize** tunable parameter was changed from 400 to 200. The **j2_inodeCacheSize** tunable parameter allows approximately 50,000 open files per gigabyte (GB) of main memory, and improves system performance. However, the **j2_inodeCacheSize** tunable parameter value of 200 can cause issues in systems that have a small amount of main memory (4 GB or less) and many concurrent users or many concurrent open files. To fix these issues, you can change the values for the **j2_inodeCacheSize** and the **j2_metadataCacheSize** tunable parameters from 200 to the previous value of 400 by running the following command:

Note: When you run the following command, the current value and boot value of both the tunable parameters are reset.

```
ioo -p -o j2_inodeCacheSize=400 -o j2_metadataCacheSize=400
```

If the issues are not fixed after you change the values for the **j2_inodeCacheSize** and the **j2_metadataCacheSize** tunable parameters, you can contact IBM Support.

IBM License Metric Tool

The IBM License Metric Tool version 7.3 is no longer supported. To learn more about the replacement version of IBM License Metric Tool Version 9.x, go to [IBM License Metric Tool 9.2](#).

IBM PowerSC Trusted Surveyor

IBM PowerSC Trusted Surveyor is not supported in AIX 7.3, and later. If you are migrating to AIX 7.3, or later, you must remove the `powersc.ts` fileset before you start the migration process. If you have WPARs that you are migrating, you must verify that the `powersc.ts` fileset is not installed on the WPARs.

Reliable Scalable Cluster Technology (RSCT)

When you upgrade to AIX 7.3, or later, RSCT Version 3.3.0.0 is installed and replaces the previous version of RSCT. For more information about RSCT, see the IBM Docs for [RSCT 3.3](#).

AIX 7.3 (and later) and RSCT Version 3.3.0.0 no longer support the Virtual Shared Disk (VSD) and low-level application programming interface (LAPI) products. If these products are already installed from an older code level, both the `rsct.vsd` and `rsct.lapi.rte` filesets must be removed before migrating to AIX 7.3, or later. If you have third-party products that use VSD, you must review the current Spectrum Scale product offerings for a replacement.

In AIX 7.3, and later, RSCT stopped shipping the following old filesets:

- `rsct.basic.hacmp`
- `rsct.basic.sp`
- `rsct.compat.basic.hacmp`
- `rsct.compat.basic.sp`
- `rsct.compat.clients.hacmp`
- `rsct.compat.clients.sp`

The filesets that end with `.sp` are no longer used by any products currently. If you still have these filesets that are installed at any supported AIX version, you can uninstall them whenever convenient. The filesets that end with `.hacmp` are still needed by some products at older AIX versions, but no longer required in AIX 7.3, and later. If you still have these filesets that are installed after you migrate to AIX 7.3, or later, you can then remove them whenever convenient.

DSM

The `dsm.core` fileset ships a `/etc/ibm/sysmgt/dsm/overrides/dsm.properties` file that allows you to override SSH configuration. If this file was modified, the file needs to be backed up manually before an update or a migration, as it is overwritten.

Thin Servers

If you migrate any previous version of the AIX Common Operating System Image (COSI) and associated AIX Thin Servers to the AIX 7.3 (or later), it is recommended that you delete any dump device that is associated with the migrated Thin Servers and re-create the Thin Servers.

Also, you must install the `devices.tmiscsw.rte` fileset on the NIM master for the AIX 7.3 Thin Server to create a dump device. The `devices.tmiscsw.rte` fileset is available in the AIX Expansion Pack.

IBM Subsystem Device Driver

AIX Version 7.3, and later, does not support the IBM Subsystem Device Driver (SDD) for IBM TotalStorage Enterprise Storage Server®, the IBM TotalStorage DS family, and the IBM System Storage SAN Volume Controller. If you are using SDD, you must move to Subsystem Device Driver Path Control Module (SDDPCM) or AIX Path Control Module (PCM) for the multipath support on AIX for IBM SAN storage. SDD to SDDPCM migration scripts are available to help you with the transition.

Contact IBM storage technical support to request access to the migration scripts.

For more information about the available Multipath I/O solutions and supported AIX versions for IBM SAN storage products, see the [IBM System Storage Interoperation Center \(SSIC\)](#) website.

Db2 migration

IBM Db2® Version 11.1 with FP5 is available on the AIX base media. You can upgrade your Db2 environment from Db2 Version 10.5, 10.1, or 9.7 to Db2 Version 11.1. For more information about upgrading to Db2 Version 11.1, see the [Upgrade to Db2 Version 11.1](#) topic.

Configuring

This section contains information about configuring the AIX operating system.

Dynamic attribute update

When you change a device attribute while the device is in the open state, the device attribute changes dynamically. In the AIX operating system, you can change specific device attributes while the device is in the open state by running the **chdev** command with the **-U** flag. Some of the device attributes in AIX 7.3, and later, that support dynamic change are as follows:

- **queue_depth** attribute for MPIO disk devices
- **rw_timeout** attribute for Serial Attached SCSI (SAS) Fibre Channel and iSCSI disk
- **num_cmd_elems** attribute for Fibre Channel adapter protocol devices

Dynamic network options

You can adjust the protocol stack of your unique networking environment by using the AIX networking options. You can now use the **no** command to dynamically configure the following TCP retransmission timeout values:

- **rto_high**
- **rto_length**
- **rto_limit**
- **rto_low**

libusb library

The libusb library is an open source C library that is supported on AIX 7.3, and later. The libusb library provides generic access to USB devices. You can run libusb applications on AIX 7.3 (and later) by recompiling the applications with this new libusb package. You can download the libusb RPM Package Manager (RPM) from the <https://public.dhe.ibm.com/aix/freeSoftware/aixtoolbox/RPMS/ppc/libusb/> website. For more information about using the libusb library, see the following topics:

- [usblddev Special File](#)
- [USBLIBDD Passthru Driver](#)

Diagnostics tasks

AIX 7.3, and later, supports scheduling periodic diagnostics multiple times a day instead of only once per day. To schedule periodic diagnostics multiple times a day, run the **diag** command and select **Task Selection > Periodic Diagnostics** and specify a time interval between each test.

AIX 7.3, and later, supports formatting and certifying up to 10 disks in parallel instead of a single at a time. To format or certify multiple disks, run the **diag** command and from the **Task Selection** menu, select **Certify Media in Parallel** or **Format Media in Parallel**. All eligible resources are displayed in a list. You can select up to 10 disks from the list. The status of the operation is updated every 5 seconds. The time the operation takes to complete for each disk is based on various factors such as disk type, size, and speed.

Trace facility

The usage of the trace facility is now limited to the root user by default.

Updates in Korn shell

AIX 7.3, and later, updated the Enhanced Korn shell (**ksh93**) from the **t** version to the **u+** version. Applications that rely on the specific exit values for the shell (instead of 0 or nonzero) might not be compatible with the **u+** version of the ksh93 shell. The exit status of the **ksh93** shell is modified to align with the **ksh93** community. For compatibility with earlier versions of AIX, the default shell remains **ksh** (also known as **ksh88**). The **ksh** shell is not enhanced for any new functions or performance. However, if feasible, support is provided to address any critical security vulnerabilities. The users of the **ksh** shell must consider to use the **ksh93** shell. In AIX 7.3.2, the bash shell is also available. A future AIX update might replace the default AIX shell with the **ksh93** shell.

Collecting processor frequency and EnergyScale information

You can use the **lparstat -E 1** command to report the calculated processor frequency per logical partition. You can use the **mpstat -E 1** command to report the calculated processor frequency per virtual processor. AIX 7.3, and later, enhances the **pmcycles -M** command to report the measured processor frequency. AIX 7.3 (and later) also supports collection of EnergyScale power and performance mode and processor frequency information on Power10 processor-based servers, and later, by using the **lparstat -N** command.

Updates in getcwd and getwd subroutines

Starting with AIX 7.3, Technology Level 2, **getcwd** and **getwd** subroutines use a caching algorithm to retrieve the path name of the current working directory. To disable the caching operation, set the environment parameter **AIX_CWD_CACHE** to **OFF**.

Limitations and Restrictions

This section lists restrictions and limitations that apply to AIX 7.3, and later.

Limitations with Java8.jre 8.0.0.635

When you migrate from AIX 7.2 to AIX 7.3, or later, if the logical partition has Java 8 32-bit SR6FP35 (VRMF 8.0.0.635) installed, you must upgrade the Java version to a later level that can be downloaded from the [Java SDK on AIX](#) page. Java 8 32-bit SR6FP35 (VRMF 8.0.0.635) might not load properly on AIX 7.3 (or later).

If a newer version of Java is not available, Java 8 32-bit SR6FP30 (VRMF 8.0.0.630) images are provided on AIX 7.3.2 Expansion pack. You can force-install this Java image to revert to an earlier version that does not have any loading issues.

>Upgrading IBM Security Verify Directory

Starting with AIX 7.3 Technology Level 2, IBM Security Directory Server (ISDS) is upgraded and is renamed as IBM Security Verify Directory (ISVD). The fileset for ISDS Version 6.4.0.25 is upgraded to ISVD Version 10.0.0.1. The fileset version and the name change for the directory have no impact on how the ISVD functions. The ISVD Version 10.0.0.1 fileset is shipped with AIX 7.3 Technology Level 2 and AIX 7.2 Technology Level 5 base packs. The AIX 7.3 with Technology Level 2 base pack also includes the latest and stable Lightweight Directory Access Protocol (LDAP) filesets that provide fixes for the earlier issues.

Note: To support clients who are using AIX 7.2 with supported Technology Levels, ISVD version 10.0 will be provided as part of AIX 7.2 base pack as ISDS version 6.4 reaches end of support (EOS) in September 2024.

If you have ISDS Version 6.4, you must upgrade to ISVD Version 10.0. For more information about upgrading to ISVD version 10.0, see [Upgrade an instance of IBM Security Verify Directory](#) page.

Note: For ISVD Version 10.0 to function properly, you must complete the entire process, starting with [Setting the environment before you upgrade an instance to Links to client and server utilities](#).



OpenSSL version 3.0

Starting with AIX 7.3 Technology Level 1, Open Source Secure Sockets Layer (OpenSSL) is updated from version 1.0.2 to 3.0.7. As a result of new updates in AIX 7.3 Technology Level 1, a few APIs are deprecated, weak ciphers are removed, support for Transport Layer Security (TLS) version 1.3 is introduced, and provider concepts are introduced.

> Starting with AIX 7.3 Technology Level 2, the OpenSSL version is updated to 3.0.10.1001. The OpenSSL version 3.0.10.1001 contains performance optimization for Advanced Encryption Standard (AES) with Galois/Counter Mode (AES-GCM) cipher and ChaCha20 stream cipher on Power10 systems. <

The AIX operating system ensures that the existing applications do not get impacted by the version update. Hence, the shared objects of OpenSSL 1.0.2 and OpenSSL 1.1 are retained in the OpenSSL library. The applications that depend on OpenSSL libraries must migrate to OpenSSL 3.0 before the end of support for the previous versions.

Note: The support for OpenSSL 1.0.2 ends by the end of year 2023 and the support for OpenSSL 1.1 ends by the end of year 2024. Shared objects of OpenSSL 1.0.2 will be retained beyond the year 2023 for compatibility with earlier OpenSSL versions. The shared objects of OpenSSL version 0.9.8 are no longer supported and the **libcrypto_compat.a** and **libssl_compat.a** libraries are removed since they contain only 0.9.8 shared object. Also the libraries **libcrypto.a** and **libssl.a** does not have 0.9.8 shared objects in them. As a mitigation, customers who depend on these shared objects are now recommended to compile their applications against the latest supported shared objects. OpenSSL 1.1 shared objects that are provided in the OpenSSL 3.0 library are from the corresponding latest release of the library that is provided with strong-cipher support. Customers who prefer to use this shared object are requested to compile applications by using the 1.1 library with strong-cipher support that is provided in AIX Web Download Pack Programs.

The command line tool **openssl** and **openssl64** are linked with the shared object of OpenSSL 3.0. Due to compatibility issues, the commands might not function properly.

Note: Many options are added to OpenSSL 3.0; hence, it is mandatory to validate the command line tools (**openssl** and **openssl64**) before using them.

The OpenSSL 3.0 is compiled by using the following configuration options:

- no-idea
- no-rc5
- no-weak-ssl-ciphers
- no-psk
- no-srp
- no-deprecated

The new symbols that are introduced in the OpenSSL 3.0 configuration file are stored in the `/var/ssl/openssl.cnf` file. It is recommended to backup and save the changes in the old configuration file because the old OpenSSL configuration file is not retained for the use.

To use the legacy providers that are built inside the application, make the following changes in the new configuration file:

```
openssl_conf = openssl_init

[openssl_init]
providers = provider_sect
```

```
[provider_sect]
default = default_sect
legacy = legacy_sect

[default_sect]
activate = 1

[legacy_sect]
activate = 1
```

Note: Native AIX applications that used OpenSSL version 1.0.2 shared object are updated to use OpenSSL version 1.1.1 and the preceding shared objects.

For more information about updates between OpenSSL 1.0.2 and OpenSSL 3.0, see the community migration guide (https://www.openssl.org/docs/man3.0/man7/migration_guide.html).

To raise any queries, see [IBM AIX support website](#).

OpenSSH Version 8.1p1

The OpenSSH file set is updated to the open source community 8.1p1 release with VRMF 8.1.112.2000 in AIX.

- The OpenSSH file set includes the patch for GSSAPI Key Exchange feature.
- The OpenSSH file set is compiled with OpenSSL 1.1.1t version.
- All the vulnerabilities reported in the higher version of OpenSSH (including the 8.7p1 release) are back ported to this fileset.

Note: All OpenSSH versions with VRMF 8.1.102.xxxx are no longer supported as support for OpenSSL 1.0.2 version ended in the year 2023. You must update to OpenSSH versions with VRMF 8.1.112.2000 or a later version. You can download the latest version of the OpenSSH fileset from the [AIX Web Download Pack Programs website](#).

OpenSSH 6.0p1 with VRMF 6.0.0.6204, or earlier, OpenSSH 7.1p1 with VRMF 7.1.102.1100, or earlier, and OpenSSH 7.5p1 with VRMF 7.5.102.1600 or earlier are no longer supported. You can download the latest version of the OpenSSH fileset from the [AIX Web Download Pack Programs website](#).

AIX 7.3, and later, includes OpenSSH as part of the minimal AIX installation.

GSKit version requirement for NIST compliance

GSKit version 8.0.55.19 is provided on the AIX 7.3 Expansion Pack media.

Use GSKit version 8.0.50.10, or later, when you use IP Security with Rivest-Shamir-Adleman (RSA) key lengths that are greater than 2048 bits. The minimum RSA key length of 2048 bits is a requirement for complying with the National Institute of Standards and Technology (NIST) standard as defined in Special Publication 800-131A. When you generate certificates for IP security (IPsec), consider the requirements that are listed in [Installing the IP security feature](#).

Perl

The previous version of Perl was upgraded to Perl Version 5.34.1.0. Perl is a separate 3rd-party open source package that is not owned by IBM. The Perl package might not preserve full compatibility across all versions. If you are moving Perl scripts to version 5.34.1.0, you must complete an evaluation of the scripts to verify that they continue to work as expected. For more information about Perl, see the [Perl Programming Documentation website](#).

> RPM package manager (RPM)

Starting with AIX 7.3 Technology level 2, the RPM version is upgraded to 4.18.1. The RPM version 4.18.1 uses `sqlite3` library package as a database backend instead of the `db` library package and is built with OpenSSL instead of `nss` and `nspr` library packages. The `nss`, `nspr`, and `db` library packages are removed

from the AIX base image as these library packages were used internally and are no longer needed. You can get the `nss`, `nsspr`, and `db` library packages from the [AIX toolbox](#) if required.



DBX and IBM OpenXL C/C++ compiler

The DBX debugger utility is not compatible with IBM OpenXL C/C++ compiled binary files because of the missing features in DBX DWARF support. Full DWARF support is available in a subsequent release of DBX.

YUM and DNF

AIX 7.3, and later, does not support YUM as RPM package manager from the [AIX toolbox](#). DNF (dandified yum, the next-generation of the Yellowdog Updater) can be installed from [AIX toolbox](#) and must be used to manage RPM packages.

Code and functions removed from AIX 7.3

The following code and functions are removed from AIX 7.3, or later:

- The InfiniBand adapter feature 5283 and feature 5285 (PCIe2 dual-port 4X InfiniBand QDR adapter) are not supported in AIX 7.3.
- The CAPI adapter feature EJ17 and feature EJ18 (PCIe3 CAPI Fibre Channel (FC) Flash Accelerator adapters) are not supported in AIX 7.3.
- The AIX Multipath I/O (MPIO) Active Passive (AP) PCM is removed from AIX 7.3.
- AIX USB support for diskette and audio devices is removed from AIX 7.3.
- IPFilter version 4.1.13 (`ipfl.rte 5.3.0.7`) is removed from AIX 7.3.
- Filesets for devices that are not supported by POWER8, and later systems are removed from AIX 7.3.
- Trusted AIX is removed in AIX 7.3. If you want to implement a fine-grained security model where privileges are separated across different users based on applying a labeled model to users and resources, consider the [AIX Domain RBAC](#) feature.

CIFS client fileset

The `bos.cifs_fs` software package is moved to the AIX 7.3 Expansion Pack media. The Common Internet File System (CIFS) client is provided as-is (without support).

Note: > AIX 7.3 supports an SMB client file system that is based on Server Message Block (SMB) protocol version 2.1 and version 3.0.2. The SMB client file system is a replacement of the CIFS client. The CIFS client is based on SMB protocol version 1. For more information, see [SMB client file system](#). <

CPU limit

The AIX operating system supports up to 240 dedicated or virtual processors. AIX 7.3 supports Simultaneous Multi-threading (SMT-8, SMT-4, SMT-2), and single-threaded (SMT-1) configuration. Each processor contains up to eight hardware threads that allows up to 1920 logical processors to be assigned to a single LPAR when the AIX operating system is configured in SMT-8 mode. You can use the `smtctl` command to switch the SMT mode that is used by the AIX operating system.

Network Time Protocol (NTP) updates

AIX 7.2, and earlier, supports both NTP version 3 and NTP version 4. Both NTP versions are supported by using symbolic links from the `/usr/sbin` directory to the NTP binary files of one of the NTP versions. Starting with AIX Version 7.3, support for NTP version 3 is removed. For compatibility with earlier versions of NTP, the symbolic links point to NTP version 4 binary files by default so that the same commands continue to work.

The following list contains a mapping of NTP binary directories in AIX 7.3 and later:

<i>Table 3. Mapping of NTP binary directories</i>	
NTPv4 binary files in the /usr/sbin/ntp4 directory	Default symbolic link to NTP version 4 binary files from the /usr/sbin directory
ntpd4	/usr/sbin/xntpd-->/usr/sbin/ntp4/ntpd4
ntpdate4	/usr/sbin/ntpdate-->/usr/sbin/ntp4/ntpdate4
ntpdc4	/usr/sbin/xntpdc-->/usr/sbin/ntp4/ntpdc4
ntpq4	/usr/sbin/ntpq-->/usr/sbin/ntp4/ntpq4
ntp-keygen4	/usr/sbin/ntp-keygen-->/usr/sbin/ntp4/ntp-keygen4
ntptrace4	/usr/sbin/ntptrace-->/usr/sbin/ntp4/ntptrace4
sntp4	/usr/sbin/sntp-->/usr/sbin/ntp4/sntp4

Berkeley Internet Name Domain (BIND) updates

AIX version 7.3, and earlier, supports BIND version 9.4.1. Starting with AIX 7.3, Technology Level 1, support for BIND version 9.4.1 is removed and support for BIND version 9.16 is added. For compatibility with earlier versions of BIND, the symbolic links point to BIND version 9.16 binary files to ensure that the same commands continue to work.

Note: Starting from AIX 7.3, Technology Level 1, the /usr/bin/hostnew binary file is removed.

BIND version 9.16 is included in the bind.rte fileset in AIX 7.3, Technology Level 1, base media package. The bind.rte fileset is not installed by default. During migration from the previous AIX version to AIX 7.3, Technology Level 1, the bos.net.tcp.bind and bos.net.tcp.bind_utils filesets that are installed on the previous AIX versions are removed, and the bind.rte BIND fileset is installed. During the update operation, the bind.rte fileset must be explicitly selected for installation. Otherwise, the bos.net.tcp.bind and bos.net.tcp.bind_utils BIND filesets remain in the updated system.

The following list contains a mapping of BIND binary directories in AIX 7.3, Technology Level 1 and later:

<i>Table 4. Mapping of BIND 9.16 binary directories</i>	
BIND binary files in /usr/sbin/bind_9_16 directory	Default symbolic link to BIND version 9.16 binary files
named-checkconf	/usr/sbin/named-checkconf-->/usr/sbin/bind_9_16/named-checkconf
named-checkzone	/usr/sbin/named-checkzone-->/usr/sbin/bind_9_16/named-checkzone
rndc-confgen	/usr/sbin/rndc-confgen-->/usr/sbin/bind_9_16/rndc-confgen
dig	/usr/bin/dig-->/usr/bin/bind_9_16/dig
host9	/usr/bin/host9-->/usr/bin/bind_9_16/host9
nslookup	/usr/bin/nslookup-->/usr/bin/bind_9_16/nslookup

Table 4. Mapping of BIND 9.16 binary directories (continued)

BIND binary files in /usr/sbin/bind_9_16 directory	Default symbolic link to BIND version 9.16 binary files
dnssec-keygen	/usr/sbin/dnssec-keygen-->/usr/sbin/bind_9_16/dnssec-keygen
dnssec-signzone	/usr/sbin/dnssec-signzone-->/usr/sbin/bind_9_16/dnssec-signzone
named9	/usr/sbin/named9-->/usr/sbin/bind_9_16/named9
nsupdate	/usr/sbin/nsupdate-->/usr/sbin/bind_9_16/nsupdate
rndc	/usr/sbin/rndc-->/usr/sbin/bind_9_16/rndc

Additional information

IBM AIX 7.3 Documentation

To view the most current version of the AIX 7.3 information, see the [AIX Documentation](#) website.

AIX Dynamic System Optimizer

The IBM AIX Dynamic System Optimizer (DSO) extends the features that are provided by the Active System Optimizer (ASO) to automatically adjust some system settings to maximize the efficiency of the AIX operating system. The DSO automates the difficult job of manually tuning the specific system settings to optimize eligible workloads. The additional features that are provided by DSO are large page optimization and data stream prefetch optimization.

DSO is no longer a stand-alone feature and is included in AIX 7.3, Technology Level 1, or later, as a part of ASO. For more information about DSO and ASO, see [AIX Dynamic System Optimizer](#).

Server-side support for new Unicode locales

For more information about server-side support for new Unicode locales, see the [Supported languages and locales](#) topic.

Notices

This information was developed for products and services offered in the US.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not grant you any license to these patents. You can send license inquiries, in writing, to:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

For license inquiries regarding double-byte character set (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

*Intellectual Property Licensing
Legal and Intellectual Property Law
IBM Japan Ltd.
19-21, Nihonbashi-Hakozakicho, Chuo-ku
Tokyo 103-8510, Japan*

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some jurisdictions do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM websites are provided for convenience only and do not in any manner serve as an endorsement of those websites. The materials at those websites are not part of the materials for this IBM product and use of those websites is at your own risk.

IBM may use or distribute any of the information you provide in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

*IBM Director of Licensing
IBM Corporation
North Castle Drive, MD-NC119
Armonk, NY 10504-1785
US*

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

The performance data and client examples cited are presented for illustrative purposes only. Actual performance results may vary depending on specific configurations and operating conditions.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

Statements regarding IBM's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

All IBM prices shown are IBM's suggested retail prices, are current and are subject to change without notice. Dealer prices may vary.

This information is for planning purposes only. The information herein is subject to change before the products described become available.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to actual people or business enterprises is entirely coincidental.

COPYRIGHT LICENSE:

This information contains sample application programs in source language, which illustrate programming techniques on various operating platforms. You may copy, modify, and distribute these sample programs in any form without payment to IBM, for the purposes of developing, using, marketing or distributing application programs conforming to the application programming interface for the operating platform for which the sample programs are written. These examples have not been thoroughly tested under all conditions. IBM, therefore, cannot guarantee or imply reliability, serviceability, or function of these programs. The sample programs are provided "AS IS", without warranty of any kind. IBM shall not be liable for any damages arising out of your use of the sample programs.

Each copy or any portion of these sample programs or any derivative work must include a copyright notice as follows:

© (your company name) (year).

Portions of this code are derived from IBM Corp. Sample Programs.

© Copyright IBM Corp. _enter the year or years_.

Privacy policy considerations

IBM Software products, including software as a service solutions, (“Software Offerings”) may use cookies or other technologies to collect product usage information, to help improve the end user experience, to tailor interactions with the end user or for other purposes. In many cases no personally identifiable information is collected by the Software Offerings. Some of our Software Offerings can help enable you to collect personally identifiable information. If this Software Offering uses cookies to collect personally identifiable information, specific information about this offering’s use of cookies is set forth below.

This Software Offering does not use cookies or other technologies to collect personally identifiable information.

If the configurations deployed for this Software Offering provide you as the customer the ability to collect personally identifiable information from end users via cookies and other technologies, you should seek your own legal advice about any laws applicable to such data collection, including any requirements for notice and consent.

For more information about the use of various technologies, including cookies, for these purposes, see IBM's Privacy Policy at <http://www.ibm.com/privacy> and IBM's Online Privacy Statement at <http://www.ibm.com/privacy/details> the section entitled "Cookies, Web Beacons and Other Technologies" and the "IBM Software Products and Software-as-a-Service Privacy Statement" at <http://www.ibm.com/software/info/product-privacy>.

Trademarks

IBM, the IBM logo, and [ibm.com](http://www.ibm.com) are trademarks or registered trademarks of International Business Machines Corp., registered in many jurisdictions worldwide. Other product and service names might be trademarks of IBM or other companies. A current list of IBM trademarks is available on the web at [Copyright and trademark information at www.ibm.com/legal/copytrade.shtml](http://www.ibm.com/legal/copytrade.shtml).

INFINIBAND, InfiniBand Trade Association, and the INFINIBAND design marks are trademarks and/or service marks of the INFINIBAND Trade Association.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle and/or its affiliates.

Windows is a trademark of Microsoft Corporation in the United States, other countries, or both.

